



TIBCO ActiveSpaces® - Enterprise Edition

Installation

Version 5.0.0 | February 2025



Contents

Contents	2
About This Product	4
Product Overview	5
Preparing for Installation	7
Requirements	7
Guidelines for UNIX	8
Guidelines for Microsoft Windows	9
Installation	10
Installing on Windows	10
Installing in GUI Mode	10
Installing in Console Mode	11
Postinstallation Steps	12
Verifying the Installation on Windows	12
Installing on Mac	12
Installing in GUI Mode	12
Installing in Console Mode	14
Postinstallation Steps	14
Verifying the Installation on Mac	15
Installing on Linux	15
Postinstallation Steps	18
Verifying the Installation on Linux	19
Uninstallation	20
Uninstalling on Windows	20
Uninstalling on Mac	20

Uninstalling on Linux	21
Upgrading from an Earlier Version	24
TIBCO Documentation and Support Services	28
Legal and Third-Party Notices	29

About This Product

The TIBCO ActiveSpaces® - Enterprise Edition software is a distributed in-memory data grid product. Some features of ActiveSpaces® - Enterprise Edition include the use of familiar database concepts, high I/O capacity, and network scalability. It is ideal for all application development projects, and for deploying and managing applications in the production environment of an enterprise.

TIBCO FTL® is an embedded and bundled component of ActiveSpaces® - Enterprise Edition.

Product Overview

The ActiveSpaces software is a distributed in-memory data grid product. ActiveSpaces features familiar database concepts and provides high I/O capacity and network scalability.

Motivation

The rise of *big data* and the *internet of things* places new and larger demands on databases. Traditional relational database implementations can exhibit *bandwidth bottlenecks* as more frequent queries with larger result sets overwhelm their I/O capacity.

With ActiveSpaces data grids, you can scale I/O capacity by adding host computers to the data grid.

Redesigned from the Ground Up

ActiveSpaces software features a complete redesign and reimplementations of the product and is straightforward to understand, use, and administer.

Database

Use ActiveSpaces data grid software as a system of record. An ActiveSpaces data grid provides a consistent, fault-tolerant system that supports mixed read and write workloads in a scalable manner.

ActiveSpaces software presents application programmers with familiar database concepts, such as tables, rows, and columns. Programs can insert, delete, and retrieve individual rows. Programs can query for rows that match a specified pattern of data.

Administrators define and configure a data grid. Administrators deploy and manage the component processes that implement the data grid. Administrators define tables, indexes, and their parameters.

Process Memory Storage

ActiveSpaces software caches data in process memory for fast read access, and writes data to persistent storage for safety.

Communications

ActiveSpaces software uses fast TIBCO FTL messaging software in these key roles:

- Communication between application programs and the data grid
- Data type foundation in application programs and the data grid
- Internal communication among data grid component processes
- Configuration, monitoring, and management of data grid components

For the minimum supported release of TIBCO FTL software, see the [Readme file](#).

Preparing for Installation

Complete these steps before you begin to install ActiveSpaces.

Procedure

1. If you are upgrading from an earlier release of the ActiveSpaces software, see [Upgrading from an Earlier Release](#).
2. Refer to the readme file. Verify that the product supports your platforms and versions.

You can find the readme file on the TIBCO download site and on the product distribution, in the same directory as the installation files.
3. Read the TIBCO Software Inc. License Agreement included with the product.
4. Read the sections in this book that pertain to your operating system platforms.
5. Verify that the host computer satisfies the requirements for installation, and that the prerequisite software is already installed. For more information, see [Requirements](#).

Requirements

Required Software

- Java Runtime Environment (JRE), version 1.8 or later, 64-bit, is required to run your Java application programs.
- Java Developer Kit (JDK), version 1.8 or later, 64-bit, is required to develop Java application programs.
- TIBCO FTL[®]. For the minimum supported release of TIBCO FTL software, see the Readme file.

Each ActiveSpaces data grid depends on a TIBCO FTL realm service to supply configuration data to its components.

Installer Accounts

Platform	Account Privileges
Microsoft Windows	<p>You must have administrator privileges for the computer on which this product is installed. If you do not have administrator privileges, the installer exits. To continue, either log out of the system and log in as a user with the required privileges, or request your system administrator to assign the privileges to your account.</p> <p>To install the product on a network drive, ensure that the account used for installation has permission to access the network drive.</p>
Linux	<p>For system-based installers, you need superuser (root) privileges for installation. However, for extracting TAR files, you do not need to have superuser (root) privileges. Ensure that the same user account is used to install TIBCO FTL.</p>
macOS	<p>Administrator privileges are required for installation.</p>

Guidelines for UNIX

Before installing on a UNIX platform, read this platform-specific information.

Installation Packages

ActiveSpaces software is available on the UNIX operating systems listed in the following table. For the latest changes, see the readme file.

All installer package names begin with a prefix from the first table and end with a suffix from the second table.

Edition	Installer Package Prefix
Community Edition	TIB_as-ce_5.0.0_
Enterprise Edition	TIB_as_5.0.0_

UNIX Distribution Directories

OS	Hardware	Installer Package Suffix	Notes
Red Hat Enterprise Linux Novell SUSE Linux Enterprise Server	Intel x86_64	linux_x86_64.zip	64-bit OS only.
macOS X 10.12.x	Intel x86_64	macosx_x86_64.zip	64-bit OS only.

Guidelines for Microsoft Windows

Before installing on a Microsoft Windows platform, read this platform-specific information.

Installation Packages

ActiveSpaces software is available for the Windows platforms listed in the following table. For the latest changes, see the Readme file.

All installer package names begin with a prefix from the first table and end with a suffix from the second table.

Edition	Installer Package Prefix
Community Edition	TIB_as-ce_5.0.0_
Enterprise Edition	TIB_as_5.0.0_

Microsoft Windows Distribution Directories

OS	Hardware	Installer Package Suffix	Notes
Windows 10 64-bit Windows Server 2016 64-bit Windows Server 2019 64-bit	Intel x86_64	win_x86_64.zip	64-bit OS only.

Installation

ActiveSpaces is installed by using platform-native installers.

- **Installing on Mac and Windows**

Use the platform-native installer to install the product on Mac and Windows platforms. You can install the product in any of the following modes: GUI or console.

- **Installing on Linux**

Use the platform-native installer to install the product on Linux platforms. The installer provides you with a collection of RPM/DEB packages that you must install. You have the flexibility to install the RPM/DEB packages based on your requirements.

Installing on Windows

You can install the product in the GUI or console mode.

Installing in GUI Mode

Follow these steps to install ActiveSpaces by using the GUI mode.

Before you begin

TIBCO FTL must be installed on your computer. For the minimum supported release of TIBCO FTL software, see the Readme file.

Procedure

1. Download the installation package.
2. Extract the ActiveSpaces archive file to a temporary directory.
3. Navigate to that temporary directory.
4. Run the platform-specific installer executable. Click **Next** on the Welcome window.

5. Read the License Agreement, select **I Agree**.
6. Choose the install location. Accept the default location or click **Browse** to choose a different location. Click **Next**.
7. Choose the **Start Menu** folder and click **Next**.
8. Choose which components of ActiveSpaces you want to install.
By default, all components are installed. Uncheck the components that you do not want to install.
Click **Install**.
9. Click **Finish**.

Installing in Console Mode

In the console mode, a command line starts the installer.

Before you begin

TIBCO FTL must be installed on your computer. For the minimum supported release of the TIBCO FTL software, see the Readme file.

Procedure

1. Download the installation package.
2. Extract the ActiveSpaces archive file to a temporary directory.
3. In a console window, navigate to that temporary directory.
4. Run the executable in console mode.

Option	Description
<code><Windows installer executable> /S</code>	The <code>/S</code> option installs in the silent mode.
<code><Windows installer executable> /S /D=<installation directory></code>	The <code>/D</code> option installs in the specified directory.

5. Complete the installation by responding to the console window prompts.

Postinstallation Steps

These are additional tasks that you must perform after installation.

- Set up your TIBCO FTL environment by running `C:\tibco\ftl\<version>\samples\setup.bat`.
- Before running any ActiveSpaces executables, set up your ActiveSpaces environment by running `C:\tibco\as\5.0\samples\setup.bat`.

Verifying the Installation on Windows

Follow these steps to verify the installation on Windows platforms.

Procedure

1. Navigate to `c:\tibco\as\5.0\samples`.
2. Follow the directions in the `README.md` file to set up your environment.
3. Navigate to `c:\tibco\as\5.0\samples\scripts`.
4. Run the `as-start` script.
5. Verify that the message `Grid is online` is displayed in your command window where you ran the `as-start` script.
6. Run the `as-stop` script.

Installing on Mac

You can install the product in the GUI or console modes.

Installing in GUI Mode

Follow these steps to install ActiveSpaces on Mac by using the GUI mode.


Before you begin

TIBCO FTL must be installed on your computer. For the minimum supported release of the TIBCO FTL software, see the [Readme](#) file.

Procedure

1. Download the installation archive package.
2. Extract the ActiveSpaces archive file to a temporary directory.
3. Double-click the installation package to run the installer executable or run the following command from a console window:

```
sudo open <Mac installer executable>
```

 **Note:** When you double-click `TIB_as_5.0.0_macosx_x86_64.pkg`, it might give you the following error: “`TIB_as_5.0.0_macosx_x86_64.pkg`” can’t be opened because it is from an unidentified developer. To resolve this issue, right-click `TIB_as_5.0.0_macosx_x86_64.pkg`, and select **Open**.

Provide your password if prompted and follow the installation prompts.

4. The Introduction window is displayed. Click **Continue**.
5. The License Agreement is displayed. Click **Agree**.
6. Select where you want to install the software and click **Continue**.
7. Choose the installation type.
 - Click **Install** to choose the standard installation.
This is the default choice.
 - Click **Customize** to choose the specific packages you want to install and then click **Install**.
 - Provide your password and click **Install Software**, if prompted.

Result

The **Summary** window confirms whether the installation was successful.

Installing in Console Mode

In the console mode, a command line starts the installer.

Before you begin

TIBCO FTL must be installed on your computer. For the minimum supported release of TIBCO FTL software, see the Readme file.

Procedure

1. Download the installation package.
2. Extract the ActiveSpaces archive file to a temporary directory.
3. From a console window, navigate to that temporary directory.
4. Run the installer executable in console mode.

Option	Description
<code>sudo installer -pkg ./<Mac installer executable> -target /</code>	The <code>-target</code> option allows you to install to a disk.

5. Complete the installation by responding to the console window prompts.

ActiveSpaces is successfully installed under `<target>/opt/tibco/as/<version>`.

Postinstallation Steps

These are optional additional tasks that you must perform after installation.

You are required to perform these tasks if:

- you installed ActiveSpaces without first installing TIBCO FTL.
- you installed a new version of TIBCO FTL and want your ActiveSpaces installation to point to the new version.

Procedure

1. Navigate to `/opt/tibco/as/5.0/scripts/post_install`.

2. Run the following script:

```
./activespaces_postinstall.sh <path to the TIBCO FTL installation>
```

Verifying the Installation on Mac

The installation can be verified by performing the following steps:

Procedure

1. Navigate to `/opt/tibco/as/5.0/samples/scripts` and run the following commands:

```
.. ./setup  
./as-start
```

2. Verify that all ActiveSpaces processes start up correctly.
3. Run the following script:

```
./as-stop
```

4. Verify that all ActiveSpaces processes shut down.

Installing on Linux

Use the platform-native installer to install the product on Linux platforms. The installer provides you with a collection of RPM and DEB packages to install.

Before you begin

TIBCO FTL must be installed on your computer. For the minimum supported release of the TIBCO FTL software, see the Readme file.

Procedure

1. Download the installation package.
2. Extract the ActiveSpaces archive file to a temporary directory. The ActiveSpaces

archive contains a top-level directory named `TIB_as_VERSION` (where `VERSION` is the product version number). The top-level directory contains folders with different types of installation artifacts that include RPMs and DEBs.

3. Install by using either the RPM or DEB, depending on the Linux platform variant. Navigate to one of the following directories under the temporary directory.

Linux Variant	Directory under the temporary directory	Description
Red Hat or SUSE	<code>rpm</code>	Contains the RPM installation packages that you can install by using the <code>yum</code> package manager or <code>zypper</code> .
Debian	<code>deb</code>	Contains the DEB installation packages that you can install by using the Debian <code>dpkg</code> package manager.
Other Linux variants	<code>tar</code>	If your Linux variant does not include <code>yum</code> , <code>dpkg</code> , or <code>zypper</code> , you can use <code>tar</code> . <pre>for f in tar/*; do tar zxfv \$f; done</pre> <p>Tip: You must have root privileges to write to the root / directory.</p>

4. Install by using either the RPM or DEB packages, depending on the Linux platform variant.

In all cases, use the following sequence:

- a. ActiveSpaces third party
- b. ActiveSpaces runtime
- c. ActiveSpaces servers
- d. ActiveSpaces java
- e. ActiveSpaces tools

- f. ActiveSpaces development
- g. ActiveSpaces Administration
- h. ActiveSpaces monitoring

Either follow the order of the commands mentioned in the table, or install the components that you need. You can also install by using the wildcard * as in by using "*.rpm" or "*.deb" instead of giving the individual file names.

Linux Variant	Command
Red Hat	<pre> sudo yum install -y TIB_as_5.0.0_linux_x86_64- thirdparty.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64-runtime.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64-servers.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64-java.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64-tools.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64- development.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64-admin.rpm sudo yum install -y TIB_as_5.0.0_linux_x86_64- monitoring.rpm </pre>
Debian	<pre> sudo dpkg -i TIB_as_5.0.0_linux_x86_64-thirdparty.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-runtime.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-servers.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-java.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-tools.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-development.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-admin.deb sudo dpkg -i TIB_as_5.0.0_linux_x86_64-monitoring.deb </pre>
SUSE	<pre> sudo zypper install TIB_as_5.0.0_linux_x86_64- thirdparty.rpm sudo zypper install TIB_as_5.0.0_linux_x86_64-runtime.rpm </pre>

Linux Variant	Command
	<pre>sudo zypper install TIB_as_5.0.0_linux_x86_64-servers.rpm sudo zypper install TIB_as_5.0.0_linux_x86_64-java.rpm sudo zypper install TIB_as_5.0.0_linux_x86_64-tools.rpm sudo zypper install TIB_as_5.0.0_linux_x86_64- development.rpm sudo zypper install TIB_as_5.0.0_linux_x86_64-admin.rpm sudo zypper install TIB_as_5.0.0_linux_x86_64- monitoring.rpm</pre>
	<p>Note: In case you encounter issues with dependencies, ignore those dependencies, and proceed with the installation.</p>

ActiveSpaces is successfully installed under `/opt/tibco/`. The archive utility tar installs the ActiveSpaces software under `./opt/tibco/`.

Postinstallation Steps

These postinstallation steps on Linux are optional.

You need these steps only if you want to manage symbolic links in ActiveSpaces by using the alternative system. The script creates an alternative link group called `activespaces` and adds symbolic links for ActiveSpaces binaries, libraries, and header files to `/usr/bin`, `/usr/lib`, and `/usr/include` respectively.

Procedure

1. Navigate to `/opt/tibco/as/5.0/scripts/post_install`.

The scripts add symbolic links to `/usr/bin` and `/usr/lib` for the TIBCO binaries and libraries. This way, you need not add `/opt/tibco/as/5.0/bin` to the `PATH`, or add `/opt/tibco/as/5.0/lib` to `LD_LIBRARY_PATH`.

2. Run the installation scripts.

```
sudo activespaces_alternatives_install.sh
```

Verifying the Installation on Linux

The installation can be verified by looking for the last RPM or Debian file installed.

Linux Variant	Command
Red Hat	<pre>su -c 'yum list' grep "tib_as"</pre>
Debian	<pre>dpkg-query -l grep "tib_as"</pre>
SUSE	<pre>zypper se grep "tib_as"</pre>

i **Note:** Alternatively, examine the log files at `/var/log`.

Uninstallation

Use the platform-specific steps to uninstall the product.

Uninstalling on Windows

Follow these steps to uninstall ActiveSpaces.

Procedure

1. Navigate to the directory where you installed ActiveSpaces and double-click `Uninstall.exe`.
Alternatively, access the uninstaller from the **Start** menu.
2. Click **Uninstall** to confirm that you want to install from the displayed location.
3. Click **Close** to complete the uninstallation process.

Uninstalling on Mac

ActiveSpaces provides a script to help with the uninstallation process.

Procedure

1. Create a temporary directory outside of the ActiveSpaces installation folder.
2. Copy the file `/opt/tibco/as/<version>/scripts/post_install/activespaces_uninstall.sh` to your temporary directory.
3. Navigate to the temporary directory.
4. To uninstall ActiveSpaces, run the following command:

```
./activespaces_uninstall.sh
```

Uninstalling on Linux

Uninstall the RPM/DEB files in the reverse order of installation.

Procedure

1. If you had used postinstallation scripts after installing the RPM or Debian packages, you must perform the following steps to remove the symbolic links:
 - a. Navigate to the `/opt/tibco/as/5.0/scripts/post_install` folder.
 - b. Run the following command:

```
sudo ./activespaces_alternatives_uninstall.sh
```

2. Uninstall by using either the RPM or DEB packages, depending on the Linux platform variant.
 - a. Navigate to `/opt/tibco/as/5.0`.
 - b. To get a list of the packages to be uninstalled, run the following command:

Linux Variant	Command
Red Hat	<pre>su -c 'yum list' grep tib_as</pre>
Debian	<pre>dpkg-query -l grep tib_as</pre>
SUSE	<pre>zypper se grep "tib_as"</pre>

- c. While uninstalling the packages, use the following sequence:
 - i. ActiveSpaces development
 - ii. ActiveSpaces tools
 - iii. ActiveSpaces java
 - iv. ActiveSpaces servers

- v. ActiveSpaces runtime
- vi. ActiveSpaces third party
- vii. ActiveSpaces administration
- viii. ActiveSpaces monitoring

Linux Variant	Command
Red Hat	<pre data-bbox="485 621 1203 884">sudo yum remove tib_as_5.0.0-development.x86_64 sudo yum remove tib_as_5.0.0-tools.x86_64 sudo yum remove tib_as_5.0.0-java.x86_64 sudo yum remove tib_as_5.0.0-servers.x86_64 sudo yum remove tib_as_5.0.0-runtime.x86_64 sudo yum remove tib_as_5.0.0-thirdparty.x86_64 sudo yum remove tib_as_5.0.0-admin.x86_64 sudo yum remove tib_as_5.0.0-monitoring.x86_64</pre> <p data-bbox="472 961 1370 1066">Warning: While uninstalling ActiveSpaces Community Edition, exclude <code>com.tibco.activespaces.monitoring</code> as it is not included in the package.</p>
Debian	<pre data-bbox="485 1157 1052 1419">sudo dpkg -r tib_as_5.0.0-development sudo dpkg -r tib_as_5.0.0-tools sudo dpkg -r tib_as_5.0.0-java sudo dpkg -r tib_as_5.0.0-servers sudo dpkg -r tib_as_5.0.0-runtime sudo dpkg -r tib_as_5.0.0-thirdparty sudo dpkg -r tib_as_5.0.0-admin sudo dpkg -r tib_as_5.0.0-monitoring</pre> <p data-bbox="472 1497 1370 1602">Warning: While uninstalling ActiveSpaces Community Edition, exclude <code>com.tibco.activespaces.monitoring</code> as it is not included in the package.</p>

Linux Variant	Command
SUSE	<pre data-bbox="485 359 1174 621">sudo zypper rm tib_as_5.0.0-development sudo zypper rm tib_as_5.0.0-tools sudo zypper rm tib_as_5.0.0-java sudo zypper rm tib_as_5.0.0-servers sudo zypper rm tib_as_5.0.0-runtime sudo zypper rm tib_as_5.0.0-thirdparty sudo zypper rm tib_as_5.0.0-admin.x86_64 sudo zypper rm tib_as_5.0.0-monitoring.x86_64</pre> <p data-bbox="474 699 1370 800">Warning: While uninstalling ActiveSpaces Community Edition, exclude <code>com.tibco.activespaces.monitoring</code> as it is not included in the package.</p>

Upgrading from an Earlier Version

Read these instructions before upgrading from an earlier version of ActiveSpaces. If you are running multiple data grids, TIBCO recommends upgrading one data grid at a time.

Before you begin

You must take a backup of all data directories: the realm server, all state keepers, and nodes. The location of the data directory for the realm server can be found in the *TIBCO FTL® Administration* guide. The location of the data directories for the ActiveSpaces processes can be found in *TIBCO ActiveSpaces® - Enterprise Edition Administration*.

i Note: During the upgrade process, do not change the data grid configuration such as adding or removing tables and adding or removing indexes.

Procedure

1. Determine if the TIBCO FTL realm server needs to be upgraded to a later version of TIBCO FTL. See the *TIBCO ActiveSpaces readme* file for the versions of TIBCO FTL that can be run with this version of ActiveSpaces. If you must upgrade TIBCO FTL, follow the "Upgrade Migration to a New Release" section documented in the document *TIBCO FTL® Administration*.

i Note: When migrating to TIBCO FTL 6.1 or later, ActiveSpaces uses the realm service capabilities of TIBCO FTL and does not use its other services such as the persistence, transport bridge, or disaster recovery services.

Note the following when migrating TIBCO FTL versions for use with ActiveSpaces:

- a. Use `tibftlserver` instead of `tibrealmserver`. For more information about converting TIBCO FTL 5.x `tibftlserver` command-line options into the appropriate configuration options for `tibrealmserver`, see "FTL Server Configuration" in *TIBCO FTL Administration*. Most of the options use the same name. For example, `--server.user` is the `server.user` configuration file option.

- b. Use the `ftl-internal` authorization group.

i Note: As of TIBCO FTL 6.0, the authorization groups `ftl-primary`, `ftl-satellite`, `ftl-backup`, and `ftl-dr` are obsolete.

2. Install the latest version of ActiveSpaces on all computers running the data grid processes (`tibdgnode`, `tibdkeeper`, `tibdproxy`, `tibdgadmind`), and the systems that run the `tibdg` tool to administer the data grid.
3. If you are running `tibdgadmind`, perform the following steps for each `tibdgadmind` process to be upgraded:
 - a. Make sure that the latest version of ActiveSpaces has been installed on the computer running `tibdgadmind`.
 - b. Stop the `tibdgadmind` process that you want to upgrade by using the following command:

```
tibdg -t <tibdgadmind_listen_URL> admin stop
```

i Note: By default, `tibdbadmind` listens on `http://localhost:7171`

- c. Restart the `tibdgadmind` process using the latest installed version of ActiveSpaces.
4. Run the following command from the latest version on an existing data grid before you start any of the nodes in the latest version:

```
tibdg -r <realm_service_URL> grid rebuild <grid_name>
```

i Note: Before upgrading ActiveSpaces components, the ActiveSpaces administrative command `tibdg grid rebuild` must be run on the existing data grid.

5. Before upgrading each state keeper in your quorum, use the following command to check the role of each state keeper:

```
tibdg -r <realm_service_URL> [-g <grid_name>] status
```

i Note: When upgrading the state keepers, start with the state keepers that are not lead state keepers and then upgrade the lead state keeper in the end. To identify the lead state keeper, run the `tibdg status` command and look for the text `leader` in the `ROLE` column.

6. To upgrade an individual state keeper, perform the following steps:
 - a. Install the latest version of ActiveSpaces on the computer running the state keeper.
 - b. Stop the existing state keeper by using the following command:

```
tibdg -r <realm_service_URL> [-g <grid_name>] keeper stop
<keeper_name>
```

- c. Restart the state keeper by using the latest installed version of ActiveSpaces. See the section "Starting a State Keeper" in *TIBCO ActiveSpaces® - Enterprise Edition Administration*.
7. Before upgrading each node in your copysets, use the following command to check the role of each node:

```
tibdg -r <realm_service_URL> [-g <grid_name>] status
```

i Note: When upgrading the nodes of each copyset, start by upgrading one or more secondary nodes followed by the primary node.

8. To upgrade an individual node, perform the following steps:
 - a. Install the latest version of ActiveSpaces on the computer running the node.
 - b. Stop the existing node by using the following command:

```
tibdg -r <realm_service_URL> [-g <grid_name>] node stop <node_
name>
```

- c. Restart the node by using the latest installed version of ActiveSpaces. See the section "Starting a Node" in *TIBCO ActiveSpaces® - Enterprise Edition Administration*.
 - d. For each copysset, repeat step 7 to upgrade one or more secondary nodes followed by the primary node.
9. To upgrade an individual proxy, perform the following steps:
- a. Install the latest version of ActiveSpaces on the computer running the proxy.
 - b. Stop the existing proxy by using the following command:

```
tibdg -r <realm_service_URL> [-g <grid_name>] proxy stop  
<proxy_name>
```

- c. Restart the proxy by using the latest installed version of ActiveSpaces. See the section "Starting a Proxy" in *TIBCO ActiveSpaces® - Enterprise Edition Administration*.
 - d. Repeat Step 8 to upgrade all proxies.
10. To upgrade an individual client, perform the following steps:
- a. Install the latest version of ActiveSpaces on the computer running the client.
 - b. Review the *TIBCO ActiveSpaces® - Enterprise Edition Release Notes* for any changes to the API that might affect your client application.
 - c. Stop the client.
 - d. Make the necessary changes to your client application, if any.
 - e. Restart the client by using the latest installed version of ActiveSpaces.



Note: The steps for stopping and restarting your ActiveSpaces clients depends on the design of your clients.

- f. Repeat step 9 to upgrade all clients.

TIBCO Documentation and Support Services

How to Access TIBCO Documentation

Documentation for TIBCO products is available on the [Product Documentation website](#), mainly in HTML and PDF formats.

The [Product Documentation website](#) is updated frequently and is more current than any other documentation included with the product.

Product-Specific Documentation

The documentation for this product is available on the [TIBCO ActiveSpaces® - Enterprise Edition Documentation](#) page.

How to Contact Support for TIBCO Products

You can contact the Support team in the following ways:

- To access the Support Knowledge Base and getting personalized content about products you are interested in, visit our [product Support website](#).
- To create a Support case, you must have a valid maintenance or support contract with a Cloud Software Group entity. You also need a username and password to log in to the [product Support website](#). If you do not have a username, you can request one by clicking **Register** on the website.

How to Join TIBCO Community

TIBCO Community is the official channel for TIBCO customers, partners, and employee subject matter experts to share and access their collective experience. TIBCO Community offers access to Q&A forums, product wikis, and best practices. It also offers access to extensions, adapters, solution accelerators, and tools that extend and enable customers to gain full value from TIBCO products. In addition, users can submit and vote on feature requests from within the [TIBCO Ideas Portal](#). For a free registration, go to [TIBCO Community](#).

Legal and Third-Party Notices

SOME CLOUD SOFTWARE GROUP, INC. (“CLOUD SG”) SOFTWARE AND CLOUD SERVICES EMBED, BUNDLE, OR OTHERWISE INCLUDE OTHER SOFTWARE, INCLUDING OTHER CLOUD SG SOFTWARE (COLLECTIVELY, “INCLUDED SOFTWARE”). USE OF INCLUDED SOFTWARE IS SOLELY TO ENABLE THE FUNCTIONALITY (OR PROVIDE LIMITED ADD-ON FUNCTIONALITY) OF THE LICENSED CLOUD SG SOFTWARE AND/OR CLOUD SERVICES. THE INCLUDED SOFTWARE IS NOT LICENSED TO BE USED OR ACCESSED BY ANY OTHER CLOUD SG SOFTWARE AND/OR CLOUD SERVICES OR FOR ANY OTHER PURPOSE.

USE OF CLOUD SG SOFTWARE AND CLOUD SERVICES IS SUBJECT TO THE TERMS AND CONDITIONS OF AN AGREEMENT FOUND IN EITHER A SEPARATELY EXECUTED AGREEMENT, OR, IF THERE IS NO SUCH SEPARATE AGREEMENT, THE CLICKWRAP END USER AGREEMENT WHICH IS DISPLAYED WHEN ACCESSING, DOWNLOADING, OR INSTALLING THE SOFTWARE OR CLOUD SERVICES (AND WHICH IS DUPLICATED IN THE LICENSE FILE) OR IF THERE IS NO SUCH LICENSE AGREEMENT OR CLICKWRAP END USER AGREEMENT, THE LICENSE(S) LOCATED IN THE “LICENSE” FILE(S) OF THE SOFTWARE. USE OF THIS DOCUMENT IS SUBJECT TO THOSE SAME TERMS AND CONDITIONS, AND YOUR USE HEREOF SHALL CONSTITUTE ACCEPTANCE OF AND AN AGREEMENT TO BE BOUND BY THE SAME.

This document is subject to U.S. and international copyright laws and treaties. No part of this document may be reproduced in any form without the written authorization of Cloud Software Group, Inc.

TIBCO, the TIBCO logo, the TIBCO O logo, FTL, eFTL, and Rendezvous are either registered trademarks or trademarks of Cloud Software Group, Inc. in the United States and/or other countries.

All other product and company names and marks mentioned in this document are the property of their respective owners and are mentioned for identification purposes only. You acknowledge that all rights to these third party marks are the exclusive property of their respective owners. Please refer to Cloud SG’s Third Party Trademark Notices (<https://www.cloud.com/legal>) for more information.

This document includes fonts that are licensed under the SIL Open Font License, Version 1.1, which is available at: <https://scripts.sil.org/OFL>

Copyright (c) Paul D. Hunt, with Reserved Font Name Source Sans Pro and Source Code Pro.

Cloud SG software may be available on multiple operating systems. However, not all operating system platforms for a specific software version are released at the same time. See the “readme” file for the availability of a specific version of Cloud SG software on a specific operating system platform.

THIS DOCUMENT IS PROVIDED “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENT COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THIS DOCUMENT. CLOUD SG MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S), THE PROGRAM(S), AND/OR THE SERVICES DESCRIBED IN THIS DOCUMENT AT ANY TIME WITHOUT NOTICE.

THE CONTENTS OF THIS DOCUMENT MAY BE MODIFIED AND/OR QUALIFIED, DIRECTLY OR INDIRECTLY, BY OTHER DOCUMENTATION WHICH ACCOMPANIES THIS SOFTWARE, INCLUDING BUT NOT LIMITED TO ANY RELEASE NOTES AND "README" FILES.

This and other products of Cloud SG may be covered by registered patents. For details, please refer to the Virtual Patent Marking document located at <https://www.cloud.com/legal>.

Copyright © 2009-2025. Cloud Software Group, Inc. All Rights Reserved.