

TIBCO Spotfire®

Deployment and Administration Manual

Software Release 6.5
April 2014

Important Information

SOME TIBCO SOFTWARE EMBEDS OR BUNDLES OTHER TIBCO SOFTWARE. USE OF SUCH EMBEDDED OR BUNDLED TIBCO SOFTWARE IS SOLELY TO ENABLE THE FUNCTIONALITY (OR PROVIDE LIMITED ADD-ON FUNCTIONALITY) OF THE LICENSED TIBCO SOFTWARE. THE EMBEDDED OR BUNDLED SOFTWARE IS NOT LICENSED TO BE USED OR ACCESSED BY ANY OTHER TIBCO SOFTWARE OR FOR ANY OTHER PURPOSE.

USE OF TIBCO SOFTWARE AND THIS DOCUMENT IS SUBJECT TO THE TERMS AND CONDITIONS OF A LICENSE AGREEMENT FOUND IN EITHER A SEPARATELY EXECUTED SOFTWARE LICENSE AGREEMENT, OR, IF THERE IS NO SUCH SEPARATE AGREEMENT, THE CLICKWRAP END USER LICENSE AGREEMENT WHICH IS DISPLAYED DURING DOWNLOAD OR INSTALLATION OF THE SOFTWARE (AND WHICH IS DUPLICATED IN THE LICENSE FILE) OR IF THERE IS NO SUCH SOFTWARE LICENSE AGREEMENT OR CLICKWRAP END USER LICENSE AGREEMENT, THE LICENSE(S) LOCATED IN THE "LICENSE" FILE(S) OF THE SOFTWARE. USE OF THIS DOCUMENT IS SUBJECT TO THOSE TERMS AND CONDITIONS, AND YOUR USE HEREOF SHALL CONSTITUTE ACCEPTANCE OF AND AN AGREEMENT TO BE BOUND BY THE SAME.

This document contains confidential information that is subject to U.S. and international copyright laws and treaties. No part of this document may be reproduced in any form without the written authorization of TIBCO Software Inc.

TIBCO, Two-Second Advantage, TIBCO Spotfire, TIBCO Enterprise Runtime for R, TIBCO Spotfire Server, TIBCO Spotfire Web Player, TIBCO Spotfire Statistics Services, S-PLUS, and TIBCO Spotfire S+ are either registered trademarks or trademarks of TIBCO Software Inc. in the United States and/or other countries.

Enterprise Java Beans (EJB), Java Platform Enterprise Edition (Java EE), Java 2 Platform Enterprise Edition (J2EE), and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle Corporation in the U.S. and other countries.

All other product and company names and marks mentioned in this document are the property of their respective owners and are mentioned for identification purposes only.

THIS SOFTWARE MAY BE AVAILABLE ON MULTIPLE OPERATING SYSTEMS. HOWEVER, NOT ALL OPERATING SYSTEM PLATFORMS FOR A SPECIFIC SOFTWARE VERSION ARE RELEASED AT THE SAME TIME. SEE THE README FILE FOR THE AVAILABILITY OF THIS SOFTWARE VERSION ON A SPECIFIC OPERATING SYSTEM PLATFORM.

THIS DOCUMENT IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENT COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THIS DOCUMENT. TIBCO SOFTWARE INC. MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S) AND/OR THE PROGRAM(S) DESCRIBED IN THIS DOCUMENT AT ANY TIME.

THE CONTENTS OF THIS DOCUMENT MAY BE MODIFIED AND/OR QUALIFIED, DIRECTLY OR INDIRECTLY, BY OTHER DOCUMENTATION WHICH ACCOMPANIES THIS SOFTWARE, INCLUDING BUT NOT LIMITED TO ANY RELEASE NOTES AND "READ ME" FILES.

Copyright © 1996-2014 TIBCO Software Inc. ALL RIGHTS RESERVED.

TIBCO Software Inc. Confidential Information

Contents

TIBCO Spotfire Server Documentation and Support Services	4
Spotfire Deployment and Administration	5
The Spotfire Administrator	6
TIBCO Spotfire Administrative Tools	7
TIBCO Spotfire Server Logs and Diagnostics	7
Set Up TIBCO Spotfire	9
Spotfire Package Deployment	9
Deploying Spotfire Packages	10
Installing TIBCO Spotfire on a Computer	11
Verifying That You Can Log In	12
Copying a Deployment to the Default Deployment Area	12
Set Up Users	13
Set Up Groups	13
Roles and Special Groups	13
Set Up Licenses	14
Set Up Preferences	15
Set Up Connection to TIBCO Spotfire Statistics Services	15
Set Up the Spotfire Library	16
Spotfire Licenses and Features	17
TIBCO Spotfire Diagnostics License	18
TIBCO Spotfire Web Player License	19
TIBCO Spotfire Enterprise Player License	19
TIBCO Spotfire Professional License	20
TIBCO Spotfire Business Author License	23
TIBCO Spotfire Advanced Analytics License	24
TIBCO Spotfire Extensions License	26
TIBCO Spotfire Information Modeler License	27
TIBCO Spotfire Administrator License	27
TIBCO Spotfire Qualification License	28
TIBCO Spotfire Connectors License	28

TIBCO Spotfire Server Documentation and Support Services

All TIBCO documentation is available in the TIBCO Documentation Library, which can be found here:

<https://docs.tibco.com>

TIBCO Spotfire Server Documentation

The following documents for this product can be found in the TIBCO Documentation Library:

- *TIBCO Spotfire® Server Release Notes*
- *TIBCO Spotfire® Server Quick Start Guide*
- *TIBCO Spotfire® Server Installation and Configuration Guide*
- *TIBCO Spotfire® Server Web Services API*
- *TIBCO Spotfire® Server Platform API Reference*
- *TIBCO Spotfire® Server Information Services API Reference*
- *TIBCO Spotfire® Server License Agreement*
- *TIBCO Spotfire® Server Language Pack Deployment Kit (Language Deployment Kit only)*

Product System Requirements

For a list of system requirements for this product and other TIBCO Spotfire® products, visit this site:

<http://support.spotfire.com/sr.asp>

How to Contact TIBCO Support

For comments or problems with this manual or the software it addresses, contact TIBCO Support as follows:

- For an overview of TIBCO Support, and information about getting started with TIBCO Support, visit this site:

<http://www.tibco.com/services/support>

- If you already have a valid maintenance or support contract, visit this site:

<https://support.tibco.com>

Entry to this site requires a user name and password. If you do not have a user name, you can request one.

How to Join TIBCOCommunity

TIBCOCommunity is an online destination for TIBCO customers, partners, and resident experts. It is a place to share and access the collective experience of the TIBCO community. TIBCOCommunity offers forums, blogs, and access to a variety of resources. To register, go to:

<http://www.tibcommunity.com>

Spotfire Deployment and Administration

After installing the TIBCO Spotfire® Server, the administrator works in both in the server and in the Spotfire Professional Client to configure user lists, packages, and account settings.

Spotfire Deployment and Administration are composed of two distinct sets of tasks.

- Spotfire deployment includes deploying packages to be downloaded automatically by Spotfire clients, creating users and groups, setting up licenses, and setting up the library.
- Spotfire administration includes performing tasks like adding new users and groups to the system, manage licenses, and upgrading to new versions.

All of these tasks are performed using different tools available in Spotfire. You can find further assistance in the online help of each tool.

The Spotfire Administrator

The Spotfire Administrator (Admin) is a Spotfire user with administrative privileges. The Admin is responsible for adding users and groups, configuring licenses and preferences, and deploying new packages.

The Admin can be, but does not need to be, the same person as the TIBCO Spotfire® Server administrator. When the Spotfire Server is installed, the server administrator assigns Spotfire Admin privileges to a Spotfire user (and creates it if necessary). This user becomes the first Spotfire Admin. He or she can then assign Admin privileges to other Spotfire users as needed.

TIBCO Spotfire Administrative Tools

Spotfire has three tools for performing administrative tasks. Spotfire Admins must be familiar with all three tools.

TIBCO Spotfire Administration Console

Each TIBCO Spotfire® Server has a web-based administration UI called the TIBCO Spotfire Administration Console. Use the Administration Console to:

- Set up users and groups.



If your organization uses an external mechanism such as an LDAP server for user and group management, then you do not use the Administration Console for user and group management.

- Create and upload deployments.

The Administration Console can be reached by a standard web browser using the URL `http://spotfireserver/spotfire/administration/`, where `spotfireserver` is the hostname of a Spotfire Server. If you work in a clustered environment, it does not matter which server in the cluster you use. Changes made to one server are stored in the Spotfire Database and are available to all servers.



If your Spotfire Server cluster deployment includes a load balancer, to use the Administration Console, use the load balancer hostname in place of `spotfireserver`.

TIBCO Spotfire Administration Manager

In the Spotfire client, on the **Tools** menu, you can find the Administration Manager. Use the Administration Manager to:

- Set up licenses and preferences.
- Create new users and groups.

TIBCO Spotfire Library Administration

The Library Administration tool, also available in the Spotfire client, is used to administer the Spotfire Library. Spotfire users publish and share analyses and data with each other using the Spotfire Library.

Use the Library Administration tool to export or import Library content, for example when you need to back up the contents, or to move content from one server to another, such as from a test instance to one used in production.

TIBCO Spotfire Server Logs and Diagnostics

For each TIBCO Spotfire® Server, you can view logs and diagnostics in the Server Logs and Diagnostics tool, available at the URL `http://spotfireserver:80/spotfire` (where `spotfireserver` is the name of the Spotfire Server.)

Log in as a user who has either Spotfire Administrator or Spotfire Diagnostics Administrator permissions. For more information about Spotfire permissions and administrator roles, see [Set Up Groups](#).

- Server logs can provide detailed information about what is happening on the server, such as access logs, SOAP communication, Information Links that are used, and so on.
- Diagnostics can provide information about the server itself, such as information about the database server, the operating system, Spotfire Server, the cluster configuration, the application server, the system, and the Java version.



Any changes made to the log configuration using this tool are reverted when the Spotfire Server is restarted. To change the default log level, you must manually edit a configuration file on the Spotfire Server. See the *TIBCO Spotfire Server - Installation and Configuration Manual* for more information about changing the logging level.

Set Up TIBCO Spotfire

After the TIBCO Spotfire® Server is installed and configured, the Spotfire Admin must complete the a series of configuration and deployment tasks before users can begin to use Spotfire.

Study the Spotfire deployment model and the user and group model, and read the various tools' associated help before you begin the series of tasks required for a successful Spotfire deployment.

1. Deploy Spotfire packages.
2. Install Spotfire on a computer.
3. Set up Users, Groups, Licenses and Preferences.
4. Set up the Spotfire Library.
5. Install Spotfire for all users.

Spotfire Package Deployment

After installing TIBCO Spotfire® Server, the Spotfire Admin must create an initial deployment. It is also important that any client hotfixes released by TIBCO, or any other add-on software, are deployed to the server. It is important that these packages are deployed to the server for the clients to work properly. Then, when a user logs into Spotfire, the client checks for new software packages on the server and automatically updates the client if any are found.

When you install the Spotfire Server for the first time, the default deployment area is created, and the name of that area is set to "Production". Deployment areas can then be set for groups in the Spotfire database, and when one is set for a group, all group members can access the deployments in that area.

You do not need to specify a deployment area for the Deployment Administrator and Administrator groups. These groups can access all deployment areas.




It is possible to add, delete and rename deployment areas. The default deployment area can be changed but not removed. The default deployment area is ignored for a user as soon as a deployment area is specified for a group the user belongs to. If no deployment area is set for a group, the group members get the default deployment area.

The Administrator uses the **Groups** tab to assign deployment areas. When a user logs into the Spotfire client, one of the following happens:

Deployment Area Specified	Result
Specified for one, and only one, of the groups the user is amember of.	The user gets the packages for the specified area and is not prompted to choose deployment area.
More than one deployment area is available because the user belongs to several groups with different deployment areas assigned.	The user is prompted to choose between the deployment areas set for the different groups.
No deployment area is specified for any groups the user belongs to.	The user gets the default deployment area.

Example: Multiple Deployment Areas



When users in the following groups log into Spotfire, the following occurs:

- Group 1: Because no deployment area is assigned, these users get the default deployment area. They are not prompted to select a deployment area.
- Group 2: Users get the Chemistry deployment area. They are not prompted to select deployment area.
- Group 3: Users get the Statistics deployment area. They are not prompted to select deployment area.
- Group 4: Users are prompted to select between the Statistics and the Chemistry deployment areas.

If a group of users cannot run a certain version of the Spotfire client, or if you want to specify a group of "early adopters" try out a new version of the Spotfire client, for example, you can do this easily by assigning a specific deployment area to those groups, so other users not in the group are not affected. By assigning different deployment areas to different groups, you can have fine-grained control over the deployments available to any group.

A test area can be created and used as a staging server, and when confident that everything works as it should, you can move that deployment to areas "in production".

It is recommended to think carefully through how to set up the deployment areas and make sure that users are prompted as rarely as possible to choose deployment area.

Further help is also available in the Administration Console online help.

Deploying Spotfire Packages

You can deploy Spotfire packages to the Spotfire Server to give end users access to more features or updated features in Spotfire.

See the online help for the Administration Console for detailed information about this tool.

Procedure

1. Open web browser and browse to the Administration Console, located at <http://spotserver/spotfire/administration> (where `spotserver` is the name of one of your Spotfire Servers).
2. Log in as a Spotfire Admin.
3. Select the **Deployment** tab.

4. Select an existing deployment area from the **Deployment Area** list, or create a new deployment area to which to deploy packages.



We recommend using an area that is not in production, especially if you are upgrading from a previous version of Spotfire. For example, you can create a “test deployment area,” and then later copy the deployment from that “test area” after you have installed a Spotfire client and verified that the deployment is downloaded and installed upon login.

5. If you have old packages in the environment, click **Clear** to remove all packages.



If you have any third-party packages that you know work with this version of Spotfire, you can keep these. In this scenario, rather than clicking **Clear**, remove any unwanted packages one by one.

6. Click **Add**.

The Add to Deployment dialog appears.

7. Click **Browse**.

The File Upload dialog appears.

8. Browse to a package file (.spk) or a distribution file (.sdn) that you want to include in the deployment.

A distribution (.sdn) file is composed of package (.spk) files that might have dependencies on one another. The `Spotfire.Dxp.sdn` distribution is the most frequently encountered example of a distribution file and is located in the deployment kit folder `TIB_spotdeploy_6.5.0_win\Products\TIBCO Spotfire Distribution`.

9. In the Add to Deployment dialog, click **OK** to upload and add the file to the distribution. The list of packages is updated with the contents of the file.

10. Remove any unwanted files from the list by selecting them and clicking **Remove**.

11. Click **Validate** to make sure the deployment is not corrupted.

12. Click **Save** to save and publish the deployment. The Save Deployment dialog appears.

13. Provide a version number and a description for the deployment, and then click **OK**.

Installing TIBCO Spotfire on a Computer

After creating a deployment you must install a Spotfire client on your computer, to verify that the deployment works, and to get access to the Administration Manager and the Library Administration tools.

Spotfire is installed using an installer found in the `\Products\TIBCO Spotfire Installer` folder of the Spotfire distribution.

Procedure

1. Copy the Client Installer folder to your local disk, and run the `setup.exe` file. The installer starts, and the Welcome screen is shown.
2. Click **Next** to continue.
3. Read the Spotfire license agreement. Select the **I accept** radio button to accept and click **Next** to continue.
4. Specify the **URL** of your TIBCO Spotfire® Server. Click **Next** to continue.



If there are several TIBCO Spotfire® Servers installed, and a load balancer is in place in front of them, specify the load balancer URL.

5. Click **Install** to start the installation.

- When Spotfire is installed, click **Finish** to close the installer.
Spotfire is now installed.

Verifying That You Can Log In

After deploying packages you should start Spotfire on your computer and log into the deployment area to which packages were deployed. In the following instructions it is assumed that packages were deployed to an area named “test”. Log in to the “test” deployment area on your server to verify that login works and that you receive Spotfire package updates.

Procedure

- Start Spotfire
Spotfire starts and displays a login dialog.
- Click **Manage Servers**, and then in the **Manage Servers** dialog, click **Add**.
The **Add Server** dialog appears.
- Click **Add**.
- Enter the URL to your Spotfire Server, and then click **OK** twice.
- Enter your username and password to log in to the Spotfire Server.
- Click **Login**.

You are logged in to the Spotfire Server. You should also receive package updates from the deployment in the Test Environment.



You might be prompted to select a Deployment Area. See the example in [Example: Multiple Deployment Areas](#).



Package "updates" might, in fact, be "downgrades", if the files deployed to the server are older than the installed Spotfire. This can be a useful in a situation where, for some reason, an administrator wants to downgrade all clients. However, it is not possible to downgrade to a lower major version, for example from 6.5 to 6.0, or even to log into a server with a deployment with a lower major version number than the client. For this reason, you must deploy 6.5 packages to the server before you can log in to it with a 6.5 client.

Copying a Deployment to the Default Deployment Area

In the Spotfire Administration Console, you can copy a tested deployment to the **Default Deployment Area**.



When you receive new updates from TIBCO or from a third-party, deploy these updates to the test environment and test them before you copy them to the production environment. This way you can test a new deployment without disturbing your Spotfire users.

Procedure

- In the Spotfire Administration Console, select the **Deployment** tab.
- Select the “test” area.
- Click **Copy**.
The **Copy Deployment** dialog appears.
- Select to copy the deployment to the **Default Deployment Area**.
- Click **OK**.
The content of the “test” area is copied to the production area.

Set Up Users

During TIBCO Spotfire® Server installation and configuration, Spotfire Authentication is set up. Spotfire can authenticate users using either internal authentication (Spotfire Database) or external authentication (LDAP directory or Windows Domain).

- If internal authentication is used, you can add and delete users and change their passwords using either the Administration Console or the Administration Manager.
- If external authentication is used, users are imported into the Spotfire Database when they first log in. You cannot remove imported users from within the Spotfire system.

Users can be managed in the Administration Console or in the Administration Manager on the **Users** tabs in both tools. Refer to their online helps for detailed instructions.

Set Up Groups



Spotfire groups are used to organize users. Groups can be synchronized from an external source, such as an LDAP directory or a Windows Domain, or created and managed locally in the Spotfire Database. This is set up during TIBCO Spotfire® Server installation.




Synchronized groups cannot be deleted from within the Spotfire system. However, you can create local Spotfire groups and place imported users and synchronized groups in them, which is important when you set licenses on groups.

Groups can be managed in the Administration Console or in the Administration Manager on the **Groups** and **Groups and Licenses** tabs respectively. Refer to their online helps for detailed instructions.

Roles and Special Groups

In the TIBCO Spotfire® system, there are a number of special groups that are present at installation and are not possible to remove. These groups define different roles. Roles can be viewed as different sets of tasks the members of the groups are supposed to and allowed to perform. To assign a role to a user, simply add him or her to one of the special groups. Note that some roles require not only membership in the group, but also that a specific license be enabled for the group in question.


Role	Description
Administrator	<p>All users that need administrator privileges on the TIBCO Spotfire Server must be members of this group. Membership in this group grants all permissions described below in addition to administration of preferences, licenses, and user directory.</p> <p> This group must have the TIBCO Spotfire Administrator license enabled to be able to administer the Spotfire system (to get access to the Administration Manager tool).</p>
Library Administrator	<p>Membership in this group grants full permission to the library. It overrides all folder permissions set in the library, granting full control over all content and includes the permission to import and export library content. All users and groups that need administrative privileges in the library must belong to this group or the Administrator group.</p> <p> This group must have the TIBCO Spotfire Library Administrator License enabled to be able to administer the library (to get access to the Library Administration tool).</p>

Role	Description
Deployment Administrator	<p>Membership in this group grants permission to deploy packages to the server. Note that these users can deploy to any area on the server, as well as delete any existing deployment.</p> <p> The number of logging configurations available can be decided by the server administrator. For more information about this see the <i>TIBCO Spotfire Server Installation and Configuration Manual</i>.</p>
Diagnostics Administrator	<p>Membership in this group grants permission to view server logs and diagnostics, as well as to set server logging configurations. It also grants permission to view information in the Web Player diagnostics page.</p>
Impersonator	<p>Membership in this group grants permission to Impersonate. It is recommended that users belonging to this group do not have additional privileges. See the <i>TIBCO Spotfire Server Installation and Configuration Manual</i> for more information about Impersonation.</p>
Web Player Administrator	<p>Membership in this group grants permission to view Spotfire Web Player diagnostics and to set up Scheduled Updates tasks.</p>
Scheduled Updates Users	<p>Membership in this group grants permission to perform Scheduled Updates of analysis files.</p>
Custom Query Author	<p>Membership in this group grants permission to create and sign custom queries for data access using data connections.</p>
Script Author	<p>Membership in this group grants permission to author scripts.</p> <p> The user must also have the Author Scripts license in order to author scripts.</p> <p> Scripts executed by the Spotfire Web Player can essentially do anything deployed packages can do. Therefore you should only grant this permission to trusted users.</p>
Everyone	<p>This is group always contains all users in the Spotfire system. No users can be removed from it, but you can set licenses for it if you like.</p>

Set Up Licenses

Spotfire licenses control what features are available to users. Licenses are always configured per group, never on individual users. When a user logs in, only the features enabled to the groups the user belongs to appear in Spotfire. You should apply licenses to groups when you create them. Because groups can belong to groups, licenses are inherited from the parent group.

Example:



In this example, the license Spotfire Professional is set on the group ACME Spotfire Users. This license is then inherited by all groups belonging to the ACME Spotfire Users group, situated below it in this illustration. The license TIBCO Spotfire Metrics is set on the group ACME Analysts and inherited by its child groups, ACME Food Analysts and ACME Drink Analysts.

When initially setting up Spotfire licenses, it is a good idea to set licenses as “high up” in the hierarchy as possible, to take full advantage of group inheritance.

Licenses are set on the **Groups and Licenses** tab in the Administration Manager in the Spotfire client. For detailed instructions on how to use this tool, see its online help.

For a full list of Spotfire licenses, see [Spotfire Licenses and Features](#).

Set Up Preferences

Spotfire preferences control the Spotfire experience. Preferences define which font to use for labels, which default marker shape to use for scatter plots, and many other things. They are set on groups and inherited just like licenses.

Preferences are set on the **Preferences** tab in the Administration Manager in the Spotfire client. For detailed instructions on how to use this tool, see its online help.



Users can set their own preferences from the Tools > Options dialog in the Spotfire client. Preferences set in the Administration Manager come into effect if a user has not set any individual preferences for a particular area.

Set Up Connection to TIBCO Spotfire Statistics Services

Spotfire 6.5 provides support for connecting to TIBCO Spotfire® Statistics Services.

Most settings for this configuration are set in the Spotfire client. See its online help for more information. URLs to Spotfire Statistics Services servers running S-PLUS or open-source R engines are also configurable as Spotfire preferences in the Administration Manager. On the **Preferences** tab, select the group for which the URLs should be set, and then select the tab **Preferences**. Find TIBCO Spotfire Statistics Services in the list and click **Edit**. Enter the URL to the Spotfire Statistics Services server running a S-PLUS engine and/or the Spotfire Statistics Services server running an open-source R engine. For detailed instructions on how to use the Administration Manager, see its online help.



Open-source R is available under separate open source software license terms and is not part of TIBCO Spotfire Statistics Services. As such, open-source R is not within the scope of your license for TIBCO Spotfire Statistics Services. Open-source R is not supported, maintained, or warranted in any way by TIBCO Software Inc. Download and use of open-source R is solely at your own discretion and subject to the free open source license terms applicable to open-source R.

Set Up the Spotfire Library

The Library is where users store and share analyses. A TIBCO Spotfire® Administrator, or a Library Administrator assigned by the Spotfire Administrator, should set up the library before the users start storing analyses here.

Setting up the Library includes building a folder structure with appropriate permissions for the different groups to read and write to the different folders. By setting “owner” permissions for a certain group to a number of folders, you can delegate responsibility for that part of the Library to a certain group within your organization.

When you export and import from the Library you can select **Include Permissions**. If this is selected on both import and export, the imported content gets the same permissions as the content originally had when it was exported.



Permissions can be set only if the user or group exists in the new Library. Just importing does not assign a privilege to a user that does not exist. This has an extra implication: If you want to import users and groups as well as library content, you should start to import the users and groups.

Library Administrators

Library Administrators are Spotfire users belonging to the special Library Administrator group. Library Administrators have sufficient permissions to create folders on the root level of the Library, and also have full access to the entire Library. As a Spotfire Administrator, you could make yourself a Library Administrator, or you can delegate this responsibility to others.

Design Guidelines



The key to a successful Library design is structure. How you structure your Library is up to you. Consider the following suggestions:




- By department. For example, this would, allow all engineers to access the same analyses.
- By project. This would allow all users working in the same project to access the same analyses. Using inheritance, you could allow different sub-projects to access their parent project files, and still restrict sister-projects from reaching each other’s material.
- By geography. For example, this would allow different offices to have access to different parts of the Library.

It is usually a good idea to have the Library structure reflect the structure of your organization.

Spotfire Licenses and Features

The administrator enables the required licenses for the different users.

License or Feature	Description
TIBCO Spotfire Web Player	<p>The license for TIBCO Spotfire® Web Player.</p> <p> Any groups with this license enabled must also have the Open File and Open from Library features under the TIBCO Spotfire Enterprise Player License license enabled.</p>
TIBCO Spotfire Enterprise Player	<p>The license for TIBCO Spotfire Enterprise Player license enables access to basic features such as saving files to disk or to the library, opening files from the library, opening linked data, and exporting to various formats. While this functionality is crucial for all users, it is necessary that all users that have the TIBCO Spotfire Professional license also have the TIBCO Spotfire Enterprise Player license. For technical reasons, certain features under this license are also required to run Spotfire Web Player.</p>
TIBCO Spotfire Professional	<p>The license for running Spotfire Professional, which includes all the standard features in the Spotfire client, except the features included in the license Spotfire Enterprise Player.</p> <p> Any groups with this license enabled must also have the Spotfire Enterprise Player license enabled.</p>
TIBCO Spotfire Business Author	<p>Users can create and edit analyses from a web client.</p>
TIBCO Spotfire Advanced Analytics	<p>Controls access to additional analytic features such as custom expressions, the box plot visualization, various statistical features, and advanced aggregation methods. Most users of Spotfire Professional need this license.</p>
TIBCO Spotfire Extensions	<p>Users can use custom extensions, which developers in your organization can add. When new custom license features are deployed to the Spotfire Server, they appear under this license.</p>
TIBCO Spotfire Information Modeler	<p>Enables tools and permissions needed to set up and edit data sources used by information links</p>

License or Feature	Description
TIBCO Spotfire Administrator	<p>Enables access to the Administration Manager and the Library Administration tool (the administration tools available within the Spotfire client).</p> <p> To administer the Spotfire system, this license is not enough. The user must also be a Spotfire Admin, that is a member of the special Administrator group. If the users needs full access to the library, they must also be members of the special Library Administrator group.</p> <p> If you are a member of the Library Administrator group, you are granted full control over all content. By default, the Administrator group is a member of the Library Administrator group and thus has full access control over the library.</p>
TIBCO Spotfire Qualification	Enables TIBCO Spotfire Qualification.
TIBCO Spotfire Diagnostics	Enables access to the Application Profiler tool, used for gathering information about analysis files.
TIBCO Spotfire Connectors	<p>Users can connect and analyze data from external systems either in-database or in-memory, using one or more data connectors.</p> <p> All users with the TIBCO Spotfire Connctetors License must also have the Open Database Data and the Manage Data Tables license features under the TIBCO Spotfire Professional license enabled, in order to use any connectors.</p>

Each of these licenses consists of a set of license features.

TIBCO Spotfire Diagnostics License

The TIBCO Spotfire Diagnostics license gives you access to the Application Profiler which is used for gathering information about analysis files.

License or Feature	Description
Application Profiler	<p>Enables the Tools > Diagnostics > Application Profiler menu item.</p> <p>The Application Profiler is a tool used to scan the Spotfire library and acquire information about the available analyses. With the Application Profiler you can automatically run tests on a large set of DXP files, or answer questions about the analyses, such as the time an analysis takes to load, the time it takes to render visualizations and you can also use it to search for errors.</p>

TIBCO Spotfire Web Player License

The TIBCO Spotfire Web Player license enables the TIBCO Spotfire® Web Player which is needed for users who should have access to analyses in a web browser.



The **Open File** and **Open from Library** features under the TIBCO Spotfire Enterprise Player License must also be enabled for all users who should have access to analyses in the Spotfire Web Player. Other license features under the TIBCO Spotfire Enterprise Player License and the TIBCO Spotfire Business Author License may also be applicable.

License or Feature	Description
TIBCO Spotfire Web Player	License to use the Spotfire Web Player in consumer mode.
External updates of analysis files in TIBCO Spotfire Web Player	Users can perform updates of analysis files through the Spotfire Web Player server Updater Service API.

TIBCO Spotfire Enterprise Player License

The TIBCO Spotfire Enterprise Player license enables access to basic features such as Saving files to disk or to the library, Opening files from the library, Opening linked data, and Exporting to various formats. While this functionality is crucial for all users, it is necessary that all users that have the TIBCO Spotfire Professional license also have the TIBCO Spotfire Enterprise Player license. For technical reasons, some license features under this license are also needed for users running TIBCO Spotfire Web Player.

License or Feature	Description
Open File	Enables the File > Open menu item and makes files available in the list of most recently used files. Without this, a user cannot open files from within Spotfire .
Open from Library	Users can open a file from the Spotfire library.
Open Linked Data	Users can open an analysis file with linked data.
Save Spotfire Analysis File	Users can save a Spotfire analysis file.
Save to Library	Users can save a file to the Spotfire library.
Export to PowerPoint	Users can export to Microsoft® PowerPoint.
Export to PDF	Users can export to PDF
Export Image	Users can export a visualization as an image.
Export Data	Users can export or copy the data used in a visualization.
Print	Users can print visualizations to paper.
Details on Demand	Users can display the Details-on-Demand panel.


License or Feature	Description
Undo/Redo	Users can Undo or Redo actions
Bookmarks	Users can work with bookmarks.
Capture Private Bookmarks	Users can work with private bookmarks.
Capture Private and Public Bookmarks	Users can work with private and public bookmarks.
Change Password	Users can change password.
Share to tibbr®	Users can share visualizations via tibbr®.
Collaboration Panel	Users can use the Collaboration panel.

TIBCO Spotfire Professional License

The TIBCO Spotfire® Professional license is the main license for users running the full Spotfire client. All the base functionality of Spotfire is contained here, except the features listed for the TIBCO Spotfire Enterprise Player license. It is therefore vital that any user that has the TIBCO Spotfire Professional license also gets the TIBCO Spotfire Enterprise Player license.

License or Feature	Description
Open File Data	A user can always open *.dxp files from the Open menu provided the "Open File" license feature under TIBCO Spotfire Enterprise Player is enabled. This license feature enables a user to also open *.sfs, *.sdf, *.txt, *.csv, *.xml, and *.xls files, and to paste data from the clipboard.
Open Library Data	Users can open data files stored in the library.
Open Database Data	Users can open data from databases.
Open Information Links	Users can open data from information links.
Open Custom Made File	Users can open custom made files.
Replace Data	Enables the File > Replace Data Table menu item. The available sources from which data can be replaced are determined by the four "Open" license functions above.
Open Empty Data	Users can open an analysis file even if a data source is unavailable.
Merge Data	Users can insert and merge additional data into an open analysis. This is done from the Replace Data Table and Insert Column/Rows options.
Insert New Column	Users can insert a new column of data into an open analysis.
Manage Data Tables	Users can add and work with more than one data table in an analysis.

License or Feature	Description
Load Data on Demand	Users can load data from data connections and information links on demand.
Create Information Link	Users can create a new information link using predefined elements.
Create Page	Users can create a new page.
Create Table	Users can create a new Table visualization.
Create Graphical Table	Users can create a new Graphical Table visualization.
Create Cross Table	Users can create a new Cross Table visualization.
Create Bar Chart	Users can create a new Bar Chart visualization.
Create Line Chart	Users can create a new Line Chart visualization.
Create Combination Chart	Users can create a new Combination Chart visualization.
Create Pie Chart	Users can create a new Pie Chart visualization.
Create Scatter Plot	Users can create a new Scatter Plot visualization.
Create 3D Scatter Plot	Users can create a new 3D Scatter Plot visualization.
Create Map Chart	Users can create a new Map Chart visualization.
Create Treemap	Users can create a new Treemap visualization.
Create Heat Map	Users can create a new Heat Map visualization.
Create Parallel Plot	Users can create a new Parallel Coordinate Plot visualization.
Create Summary Table	Users can create a new Summary Table visualization.
Create Text Area	Users can create a new Text Area.
Action Links	Users can create Action Links.
Change Column Selector	Users can interact with column selectors and data table selectors in a visualization. Also, users can adjust binning sliders and hierarchy sliders, and to alter the order of multiple columns on an axis.
Simple Visualization Properties	Users can change visualization properties using the axis selectors, or to drag and drop columns from other visualizations or the Filters panel. (This license feature also enables everything in the Change Column Selector license feature.)

License or Feature	Description
Advanced Visualization Properties	Users can change all visualization properties via the Visualization Properties dialog. (This license feature also enables everything in the Change Column Selector and Simple Visualization Properties license feature.)
Error Bars	Users can display error bars in a visualization.
Simple Filter Panel Properties	Users can change filter type.
Advanced Filter Panel Properties	Users can hide, move and group filters, and access the Filtering Scheme Properties dialog and Organize Filters dialog.
Simple Data Properties	Grants access to the Edit > Column Properties dialog.
Advanced Data Properties	Enables additional functionality in the Column Properties dialog such as Details, Edit, Freeze Columns, Insert, Column Properties, Sort Order, and Hierarchies .
Advanced Document Properties	Grants access to the Edit > Document Properties dialog, the Tools > Options dialog. Also, users can assign a filtering scheme to a page.
Data Panel	Users can the Data panel.
Tags	Users can work with Tags.
Use Custom Made Tools	Users can open custom made tools.
Change Exportability for Web Player Table Data	Users can specify whether the data in a Table, Summary Table, or Cross Table should be able to be exported if the analysis is opened in the Spotfire Web Player. If disabled, a default value or preference determines if the data in the table can be exported from Spotfire Web Player. Set these preferences from the Preferences tab.
Lists	Users can work with Lists.
Custom Query in Connection	<p>Allows a user to create and sign custom queries for data access using data connections.</p> <div style="border-left: 1px solid #ccc; padding-left: 10px; margin-top: 10px;">  <p>This license can only be enabled for members of the Custom Query Author group or the Administrator group. However, members which only belong to the Administrator group can only save local copies of the analysis to disk, not publish signed analyses to the library. Custom queries are signed when a member of the Custom Query Author group saves an analysis file, or data connection to the library. Only files published to the library can be signed.</p> </div>

TIBCO Spotfire Business Author License

The TIBCO Spotfire Business Author license allows you to create and edit analyses from a web client.



License or Feature	Description
TIBCO Spotfire Business Author	The license for TIBCO Spotfire Business Author.
Open File Data	Users can always open *.dxd files via the Open analysis button provided the "Open File" license feature under TIBCO Spotfire Enterprise Player is enabled. This license feature enables a user to open local data files such as *.txt, *.csv, *.xlsx, *.xls, *.stdf, and *.sddf.
Open Library Data	Users can open data files stored in the library.
Open Information Links	Users can open data from information links.
Replace Data	Enables the Replace data button in the toolbar.
Open Empty Data	Users can open an analysis file even if a data source is unavailable.
Manage Data Tables	Users can work with more than one data table in an analysis
Create Page	Users can create a new page.
Create Table	Users can create a new Table visualization.
Create Cross Table	Users can create a new Cross Table visualization.
Create Bar Chart	Users can create a new Bar Chart visualization.
Create Line Chart	Users can create a new Line Chart visualization.
Create Combination Chart	Users can create a new Combination Chart visualization.
Create Pie Chart	Users can create a new Pie Chart visualization.
Create Scatter Plot	Users can create a new Scatter Plot visualization.
Create Treemap	Users can create a new Treemap visualization.
Create Parallel Plot	Users can create a new Parallel Coordinate Plot visualization.
Change Column Selector	Users can interact with column selectors and data table selectors in a visualization. Also, users can adjust binning sliders and hierarchy sliders, and alter the order of multiple columns on an axis.
Simple Visualization Properties	Users can change visualization properties using the axis selectors. (This license feature also enables everything in the Change Column Selector license feature.)

License or Feature	Description
Advanced Visualization Properties	Users can change all visualization properties via the Visualization Properties panel. (This license feature also enables everything in the Change Column Selector and Simple Visualization Properties license feature.)
Error Bars	Users can display error bars in a visualization.
Simple Filter Panel Properties	Users get access to the context menu used for switching filter types and resetting filters.

TIBCO Spotfire Advanced Analytics License

The TIBCO Spotfire Advanced Analytics license grants access to additional analytic features such as custom expressions, the box plot visualization, various statistical features, and advanced aggregation methods. Most users of TIBCO Spotfire Professional will need this license as well.

License or Feature	Description
Create Box Plot	The user can create a new Box Plot visualization.
Advanced Aggregation Methods	The user has access to more aggregation methods, in addition to the standard Sum, Average, Count, and Unique Count.
Custom Expressions	The user can use the Custom Expressions option on the column selectors.
Set Column From Marked	The user can use the Column from Marked option on the column selectors.
Line Similarity	The user can use the Line Similarity tool.
K-Means Clustering	The user can use the K-Means Clustering tool.
Hierarchical Clustering	The user can use hierarchical clustering.
Data Relationships	The user can use the Data Relationships tool.
Curve Draw	The user can add a curve to a visualization by entering an expression for the curve.
Curve From Data Table	The user can add a curve to a visualization by importing it from a data table.
Straight Line	The user can add a Straight Line Fit to visualizations.
Polynomial Curve	The user can add a Polynomial Curve to visualizations.
Logistic Regression Curve	The user can add a Logistic Regression Curve to visualizations.
Power Curve	The user can add a Power Curve to visualizations.

License or Feature	Description
Gaussian Curve	The user can add a Gaussian Curve to visualizations.
Logarithmic Curve	The user can add a Logarithmic Curve to visualizations.
Exponential Curve	The user can add an Exponential Curve to visualizations.
Register Data Functions	<p>The user can create, edit, import, and export a data function or expression function. The user can register a new data function and edit an existing script (including the data function parameters and output).</p> <p>The user can refresh or delete a data function or expression function from the library (if it is not embedded in an analysis.) The user can sync the data function from the library.</p> <p>The user can add a data table, and then add a data function transformation to that data table.</p> <p>If this license is not granted, the Tools > Register Data Function and the Edit > Data Function Properties menu items do not appear. Without this license, the user cannot create, edit, or delete data functions or expression functions. Also, the Data Function option is disabled in the File > Add Data Table dialog Add drop-down.</p> <p>Even if a user lacks this license, any existing analyses containing predicted columns continue to function and update based on the data as necessary. (That is, the underlying data functions continue to work.)</p> <div data-bbox="611 1018 1476 1176">  <p>This license should be granted in conjunction with the Execute Data Functions license, or the user can register but not test (execute) a data function or an expression function. If you do not grant this license, you should not grant licenses for Predictive Modeling or Insert Predicted Columns.</p> </div>
Execute Data Functions	<p>The user can create, edit, run, or remove a data function or an expression function. The user can edit an existing script (including the data function parameters and output), and specify where to run the data function (locally or on a server with TIBCO Spotfire Statistics Services).</p> <p>The user can access and change the settings for type of data used by the data function.</p> <p>If this license is not granted, the Insert > Data Function menu item is disabled, and the Settings button in the Edit > Data Table Properties dialog is disabled.</p> <p>Even if a user lacks this license, any existing analyses containing predicted columns continue to function and update based on the data as necessary. (That is, the underlying data functions continue to work.)</p> <div data-bbox="611 1669 1452 1764">  <p>If you do not grant this license, you should not grant licenses for Register Data Functions, Predictive Modeling, or Insert Predicted Columns.</p> </div>

License or Feature	Description
Predictive Modeling	<p>The user can create, edit, and manage Regression and Classification Models.</p> <p>If this license is not granted, the Regression Modeling and Classification Modeling menu items do not appear.</p> <p>Even if a user lacks this license, any existing analyses containing results from the predictive modeling tools continue to function and update based on the data as necessary. (That is, the underlying data functions continue to work.)</p> <p>If this license is granted, you should also grant a license for Register Data Functions and Execute Data Functions.</p>
Insert Predicted Column	<p>A user can use a predictive model in an analysis to add predicted columns to a data table.</p> <p>If this license is not granted, the Insert > Predicted Columns menu item does not appear.</p> <p>Even if a user lacks this license, any existing analyses containing predicted columns continue to function and update based on the data as necessary. (That is, the underlying data functions continue to work.)</p> <p>If this license is granted, you should also grant a license for Register Data Functions and Execute Data Functions.</p>


TIBCO Spotfire Extensions License

The TIBCO Spotfire Extensions license enables users to view and use custom extensions that developers at your company can add. When new custom license features are deployed on the Spotfire Server, they appear under this license. Then you can enable or disable each individual license feature if needed.

License or Feature	Description
Access to Extensions	Users can view and use custom extensions, which developers at your company can add. When new custom license features are deployed on the Spotfire Server, they appear under this license. You can then enable or disable each individual license feature.
Author Scripts	Users can author scripts. The user must also be a member of the Script Author group.
Automation Services Job Builder Tool	Users can access to the Automation Services Job Builder tool.
Qualification Compare Tool	Users can use the Qualification Compare tool.
Qualification Export Tool	Users can use the Qualification Export tool.
SDFParser	Users can use the SDFParser tool.

TIBCO Spotfire Information Modeler License

The TIBCO Spotfire Information Modeler license contains tools and permissions needed to set up and edit data sources used by information links

License or Feature	Description
Administration	<p>Users can modify data sources, joins and other elements when working with Information Links.</p> <p> The user must also have the Create Information Link feature enabled to access the tool itself.</p>
Prompt for Parameter	<p>This license feature is intended for users creating and testing parameterized Information Links. While you work with this tool, if you encounter a parameterized Information Link that is not provided with a value for a parameter, you see a Prompt for Parameter dialog.</p>

TIBCO Spotfire Administrator License



The TIBCO Spotfire Administrator license allows access to the Administration Manager and the Library Administration tools.



You must also be a member of the Administrator group to get the actual privileges to work on the server.




If you are also a member of the Library Administrator group, you override all folder permissions in the Library, granting full control over all content. (By default, the Administrator group is a part of the Library Administrator group and thus have full access control over the library as well.)

License or Feature	Description
Administration	<p>Grants access to Administration Manager and its functionality.</p> <p> You must be a member of the Administrator group to get the actual privileges to work on the server.</p>
Library Administration	<p>Grants access to the Library Administration tool and its functionality.</p> <p> Administrators who need full access control over the entire Library, must also be a member of the Library Administrator group. Being a member of this group overrides all folder permissions in the Library, granting full control over all content. (By default, the Administrator group is a part of the Library Administrator group and thus has full access control over the library as well.)</p> <p>The users who require administration control over parts of the library (but not all), should not be a part of this group, the Library Administration license is enough. This is the recommended option for the users who administer sections of the Library.</p>

TIBCO Spotfire Qualification License

The TIBCO Spotfire Qualification license allows users to compare analyses on different installations against a gold standard.




License or Feature	Description
TIBCO Spotfire Qualification	Users can verify that analyses in TIBCO Spotfire® yield the same results on different installations of Spotfire.  Sold as a separate license.








TIBCO Spotfire Connectors License






With a TIBCO Spotfire Connectors license, users can connect and analyze data in-database.



All users with the TIBCO Spotfire Connectors License must also have the **Open Database Data** and the **Manage Data Tables** license features under the TIBCO Spotfire Professional license enabled, in order to use any connectors.

License or Feature	Description
ADS Composite Information Server	Users can add connections to ADS Composite Information Server and analyze data in-database or in-memory.  This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.
IBM Netezza	Users can add connections to IBM® Netezza® and analyze data in-database or in-memory.  This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.
Microsoft SQL Server	Users can add connections to Microsoft® SQL Server® and analyze data in-database or in-memory.
Microsoft SQL Server Analysis Services	Users can add connections to Microsoft SQL Server Analysis Services and analyze data in-database.
Oracle	Users can add connections to Oracle® and analyze data in-database or in-memory.
Oracle MySQL	Users can add connections to Oracle MySQL and analyze data in-database or in-memory.  This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.

License or Feature	Description
PostgreSQL	<p data-bbox="612 226 1487 289">Users can add connections to PostgreSQL[®] and analyze data in-database or in-memory.</p> <div data-bbox="612 310 1487 409">  <p data-bbox="724 310 1487 409">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>
SAP Business Information Warehouse (SAP BW)	<p data-bbox="612 451 1487 514">Users can add connections to SAP[®] Business Information Warehouse (SAP BW) and analyze data in-database.</p> <div data-bbox="612 535 1487 634">  <p data-bbox="724 535 1487 634">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>
Teradata	<p data-bbox="612 676 1487 739">Users can add connections to Teradata[®] and analyze data in-database or in-memory.</p>
Cloudera Hive	<p data-bbox="612 772 1487 835">Allows a user to add connections to Cloudera Hive and analyze data in-database or in-memory.</p> <div data-bbox="612 856 1487 955">  <p data-bbox="724 856 1487 955">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>
Cloudera Impala	<p data-bbox="612 997 1487 1060">Allows a user to add connections to Cloudera Impala and analyze data in-database or in-memory.</p> <div data-bbox="612 1081 1487 1180">  <p data-bbox="724 1081 1487 1180">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>
Greenplum	<p data-bbox="612 1222 1487 1285">Allows a user to add connections to Pivotal Greenplum and analyze data in-database or in-memory.</p> <div data-bbox="612 1306 1487 1404">  <p data-bbox="724 1306 1487 1404">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>
Hortonworks	<p data-bbox="612 1446 1487 1509">Allows a user to add connections to Hortonworks and analyze data in-database or in-memory.</p> <div data-bbox="612 1530 1487 1629">  <p data-bbox="724 1530 1487 1629">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>
HP Vertica	<p data-bbox="612 1671 1487 1734">Allows a user to add connections to HP Vertica and analyze data in-database or in-memory.</p> <div data-bbox="612 1755 1487 1854">  <p data-bbox="724 1755 1487 1854">This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p> </div>

License or Feature	Description
IBM DB2	<p>Allows a user to add connections to IBM DB2 and analyze data in-database or in-memory.</p> <p> This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p>
Oracle Essbase	<p>Allows a user to add connections to Oracle Essbase and analyze data in-database.</p> <p> This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p>
Pivotal HAWQ	<p>Allows a user to add connections to Pivotal HAWQ and analyze data in-database or in-memory.</p> <p> This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p>
SAP HANA	<p>Allows a user to add connections to SAP HANA and analyze data in-database or in-memory.</p> <p> This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p>
Teradata Aster	<p>Allows a user to add connections to Teradata Aster and analyze data in-database or in-memory or in-memory.</p> <p> This is an additional connector that can be deployed on the server. It is not embedded in the standard Spotfire distribution.</p>