



# TIBCO Data Virtualization<sup>®</sup>

## User Guide

*Version 8.4*

*Last Updated: March 9, 2021*

## **Important Information**

SOME TIBCO SOFTWARE EMBEDS OR BUNDLES OTHER TIBCO SOFTWARE. USE OF SUCH EMBEDDED OR BUNDLED TIBCO SOFTWARE IS SOLELY TO ENABLE THE FUNCTIONALITY (OR PROVIDE LIMITED ADD-ON FUNCTIONALITY) OF THE LICENSED TIBCO SOFTWARE. THE EMBEDDED OR BUNDLED SOFTWARE IS NOT LICENSED TO BE USED OR ACCESSED BY ANY OTHER TIBCO SOFTWARE OR FOR ANY OTHER PURPOSE.

USE OF TIBCO SOFTWARE AND THIS DOCUMENTATION IS SUBJECT TO THE TERMS AND CONDITIONS OF A LICENSE AGREEMENT FOUND IN EITHER A SEPARATELY EXECUTED SOFTWARE LICENSE AGREEMENT, OR, IF THERE IS NO SUCH SEPARATE AGREEMENT, THE CLICKWRAP END USER LICENSE AGREEMENT WHICH IS DISPLAYED DURING DOWNLOAD OR INSTALLATION OF THE SOFTWARE (AND WHICH IS DUPLICATED IN THE LICENSE FILE) OR IF THERE IS NO SUCH SOFTWARE LICENSE AGREEMENT OR CLICKWRAP END USER LICENSE AGREEMENT, THE LICENSE(S) LOCATED IN THE "LICENSE" FILE(S) OF THE SOFTWARE. USE OF THIS DOCUMENTATION IS SUBJECT TO THOSE TERMS AND CONDITIONS, AND YOUR USE HEREOF SHALL CONSTITUTE ACCEPTANCE OF AND AN AGREEMENT TO BE BOUND BY THE SAME.

This document is subject to U.S. and international copyright laws and treaties. No part of this document may be reproduced in any form without the written authorization of TIBCO Software Inc.

TIBCO and the TIBCO logo are either registered trademarks or trademarks of TIBCO Software Inc. in the United States and/or other countries

TIBCO, Two-Second Advantage, TIBCO Spotfire, TIBCO ActiveSpaces, TIBCO Spotfire Developer, TIBCO EMS, TIBCO Spotfire Automation Services, TIBCO Enterprise Runtime for R, TIBCO Spotfire Server, TIBCO Spotfire Web Player, TIBCO Spotfire Statistics Services, S-PLUS, and TIBCO Spotfire S+ are either registered trademarks or trademarks of TIBCO Software Inc. in the United States and/or other countries.

All other product and company names and marks mentioned in this document are the property of their respective owners and are mentioned for identification purposes only.

THIS SOFTWARE MAY BE AVAILABLE ON MULTIPLE OPERATING SYSTEMS. HOWEVER, NOT ALL OPERATING SYSTEM PLATFORMS FOR A SPECIFIC SOFTWARE VERSION ARE RELEASED AT THE SAME TIME. SEE THE README FILE FOR THE AVAILABILITY OF THIS SOFTWARE VERSION ON A SPECIFIC OPERATING SYSTEM PLATFORM.

THIS DOCUMENTATION IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENTATION COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THIS DOCUMENTATION. TIBCO SOFTWARE INC. MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S) AND/OR THE PROGRAM(S) DESCRIBED IN THIS DOCUMENTATION AT ANY TIME.

THE CONTENTS OF THIS DOCUMENTATION MAY BE MODIFIED AND/OR QUALIFIED, DIRECTLY OR INDIRECTLY, BY OTHER DOCUMENTATION WHICH ACCOMPANIES THIS SOFTWARE, INCLUDING BUT NOT LIMITED TO ANY RELEASE NOTES AND "READ ME" FILES.

Copyright © 2002-2021 TIBCO Software Inc. ALL RIGHTS RESERVED.

TIBCO Software Inc. Confidential Information



# Contents

<b>Preface</b> .....	<b>16</b>
Product-Specific Documentation .....	16
How to Access TIBCO Documentation .....	17
How to Contact TIBCO Support .....	17
How to Join TIBCO Community .....	17
<b>Overview of Studio</b> .....	<b>19</b>
About Studio .....	19
Modeler Resource Tree .....	21
Desktop .....	22
Data Services .....	22
My Home .....	23
Shared .....	24
<TDV Host> .....	24
Opening Studio and Switching User .....	25
Starting Studio .....	25
Starting Studio from the Command Line .....	26
Changing the Connection Type .....	26
Customizing Studio .....	27
Customizing Studio Using the Studio Options Dialog .....	27
Customizing Studio Result Panel XML Text .....	33
Modifying Studio Memory Usage .....	34
Changing Your TDV Password .....	34
Using the Code Editor Text Editing Commands .....	35
Editor Text Editing Command Reference .....	36
Security Features .....	39
<b>Studio Resource Management Overview</b> .....	<b>41</b>
About Resource Management .....	41
Creating a TDV Resource .....	42
Locating a Container for a TDV Resource .....	42
Creating a Resource .....	43
Copying Privileges to Another Resource .....	43
Opening a Resource .....	44
Getting Information about a Resource .....	44
Annotating a Resource .....	46

Moving, Copying, Deleting, or Renaming a Resource .....	46
Searching for Resources in the Server .....	48
Impacted Resources .....	49
Managing the Display of Impacted Resources .....	49
Investigating Impacted Resources .....	50
Repairing Impacted Resources .....	51
Exporting (Archiving) and Importing Resources .....	52
Access Rights for Export and Import .....	52
Exporting Resources .....	53
Export and Import Locked Resources .....	55
Marking Rebindables .....	55
Rules for Importing Resources .....	56
Importing a Resource .....	57
Rebinding an Imported Resource .....	61
Using Studio for a Full Server Backup .....	62
Working with Resource Locks .....	63
Locking and Unlocking a Resource .....	64
Identifying Locked Resources .....	64
Change History of a Lock .....	65
<b>Working with Data Sources .....</b>	<b>67</b>
About Data Sources and TDV .....	67
About TDV Adapters .....	68
About Introspection .....	68
About Federated Queries .....	68
Data Source Categories .....	69
Adding a Data Source .....	70
Custom Adapters .....	72
Auto-Discovering Data Sources .....	73
Editing or Reviewing Configuration Information for a Data Source .....	73
Viewing Data Source Table Details .....	75
Adding and Removing Data Source Resources .....	76
Testing the Connection to Your Data Source .....	77
TDV Configuration Parameters Common to Multiple Data Sources .....	78
Data Source Connection Pool Checkout Timeout .....	79
Buffer Flush Threshold .....	79
Column Delimiter .....	80
Enable String Data Normalization .....	80
Escape Character .....	80
Row Delimiter .....	81
Default Commit Row Limit .....	81

Default Execution Timeout . . . . .	81
Delayed Connection Commit/Rollback Timeout . . . . .	82
Delayed Statement Close Timeout. . . . .	82
Enable Data Source Connection Pool Checkout Timeout . . . . .	83
Introspectable Resource Id Cache Expiration Period . . . . .	83
Introspectable Resource Id Cache Cache Purge Frequency . . . . .	83
Introspection Full Report Size Threshold . . . . .	84
Default OAuth Page Execution Timeout . . . . .	84
Push Oracle/Vertica query hints . . . . .	85
Suppress Data Source Properties Validation Errors. . . . .	85
Trace level . . . . .	85
<b>Configuring Relational Data Sources . . . . .</b>	<b>87</b>
About Pass-Through Login . . . . .	87
About Data Source Native Load Performance Options . . . . .	89
Adding Relational Data Sources . . . . .	90
Enabling Bulk Loading for SELECT and INSERT Statements. . . . .	92
<b>Configuring Advanced Adapters . . . . .</b>	<b>93</b>
Adapter Data Type Limitation . . . . .	93
Dynamics CRM Adapter ID Ordering. . . . .	93
Upgrading the ADO.NET Driver for Sharepoint Adapters . . . . .	94
Configuring OAuth 2.0 for TDV Advanced Adapters . . . . .	94
Installing the Siebel Data Bean JARs . . . . .	99
Registering with the SAP System Landscape Directory . . . . .	99
Installing the SAP Java Connector Library . . . . .	100
Verifying a Successful Activation of an Adapter . . . . .	104
Increasing the Maximum Size of Excel Sheets for SharePoint . . . . .	105
<b>Retrieving Data Source Metadata . . . . .</b>	<b>107</b>
About Introspection and Reintrospection. . . . .	108
Introspecting Data Sources . . . . .	109
Invoking Data Source Introspection . . . . .	109
Introspecting a Data Source . . . . .	110
Tracking and Viewing the Introspection Process . . . . .	118
Tracking Introspection . . . . .	118
Viewing the Introspection Task Status Report . . . . .	118
Viewing the Introspection Report for a Data Source. . . . .	119
Introspecting Data Source Table and Column Comment Metadata . . . . .	120

Setting Introspection Filters on a Resource .....	121
Reintrospecting Data Sources .....	124
Reintrospecting a Data Source Immediately .....	125
Scheduling Reintrospection .....	125
Triggering Reintrospection .....	126
Tips on Introspecting Multiple Files in a Network Share Folder .....	127
Tips on Introspecting Based on a CREATE TABLE Statement .....	128
Tips on Introspecting Large Data Sources .....	128
Understanding the Resource ID Fetching Phase .....	129
Understanding the Introspection Plan Creation Phase .....	130
Understanding the Introspection Plan Implementation Phase .....	130
Tips to Improve Performance of Resource ID Fetching .....	131
Tips to Improve Performance of Introspection Implementation .....	131
Tips for Reintrospecting Large Data Sets .....	132
<b>Views and Table Resources .....</b>	<b>133</b>
About Composite Views .....	133
Creating a New View .....	134
Setting Default Query Options .....	135
Commenting SQL .....	136
Adding Column Level Annotations .....	137
SQL Request Annotation Pass-Through .....	137
Designing a View and Table Resource .....	138
Designing a View in the Model Panel .....	138
Adding a Resource to the Model Panel .....	139
Joining Tables in the Model Panel .....	140
Enforcing Join Ordering .....	142
Creating a Union .....	143
Controlling the Number of UNION ALL and JOIN Flips .....	145
Navigating between Tables in the Model Panel .....	145
Specifying the DISTINCT Query Option .....	146
Specifying Query Hints .....	146
Designing a View in the Grid Panel .....	148
Listing All Columns from a Table .....	148
Adding an Individual Column .....	149
Creating an Alias for a Column .....	150
Changing a Column Data Type using the CAST Function .....	150
Including a Column in the ORDER BY Clause .....	150
Specifying a GROUP BY Clause .....	151
Specifying Criteria on a Column .....	151
Including a Function in a SELECT or WHERE Clause .....	152
Declaring a Variable in a SELECT Statement .....	152



Designing SQL for a View in the SQL Panel .....	155
Defining Primary Key for a View or Table in the Indexes Panel .....	156
Defining a Foreign Key for a View or Table Resource .....	157
Generating a Model from the SQL Panel .....	159
Working with Views and JSON .....	160
Using a JSON Table Within a TDV View .....	160
JSON Table Examples .....	161
Designing Column Projections Using the Columns Panel .....	162
Obtaining View Details .....	163
Executing a View .....	163
Generating a Query Execution (Explain) Plan .....	164
Generating an Explain Plan and Displaying it in a Client Application .....	164
Rebinding a View .....	165
Displaying the Lineage of a View .....	166
View Column Dependencies and References .....	168
Getting Column Dependencies Using the API .....	169
Getting Column References Using the API .....	175
Creating a View from a Cube .....	178
Ad Hoc SQL and the SQL Scratchpad Editor .....	178
Opening the SQL Scratchpad Editor .....	179
Composing and Executing an Ad Hoc SQL Query .....	180
The SQL Scratchpad History Pane .....	181
The SQL Scratchpad Result Panel .....	182
<b>Procedures .....</b>	<b>185</b>
About Procedures .....	185
Creating a SQL Script Procedure .....	186
Working with SQL Scripts .....	188
Designing Parameters for a SQL Script .....	189
Promoting Procedures to Custom Functions .....	191
Pushing a Custom Function to the Native Data Source .....	192
Using Pipes and Cursors .....	194
Java Procedures .....	195
Viewing Java Procedure Parameters .....	195
XQuery Procedures .....	196
Creating an XQuery Procedure .....	196
Designing Parameters for an XQuery .....	197
XQuery 3.0 Support .....	199
XPath 3.0 Support .....	199
XSLT Procedures .....	200

Creating an XSLT Procedure . . . . .	200
Designing Parameters for an XSLT Procedure . . . . .	201
Packaged Queries . . . . .	203
Creating a Packaged Query . . . . .	204
Specify Input Parameters for a Packaged Query . . . . .	206
Multiple SQL Execution Statements in a Packaged Query . . . . .	211
Parameterized Queries . . . . .	212
Quick Steps for Creating a Parameterized Query . . . . .	212
Add Input Parameters . . . . .	213
Adding a Parameter to a SELECT Clause . . . . .	214
Adding a Parameter to a WHERE Clause . . . . .	215
Adding a Parameter to a FROM Clause . . . . .	215
Physical Stored Procedures . . . . .	217
Editing a Stored Procedure in an Introspected Data Source . . . . .	218
Specifying the Direction of Scalar Parameters and Cursors . . . . .	218
Defining a Cursor for Projection . . . . .	219
Designing a Cursor by Example . . . . .	220
Editing a Stored Procedure in Microsoft SQL Server . . . . .	221
Editing a Stored Procedure in DB2 . . . . .	221
Using Stored Procedures . . . . .	222
Rebinding a Procedure . . . . .	222
Setting Transaction Options for a Procedure . . . . .	223
Executing a Procedure or Parameterized Query . . . . .	224
Executing a Procedure in Studio . . . . .	224
Executing a Parameterized Query . . . . .	225
Executing a Stored Procedure . . . . .	226
Executing a Procedure through JDBC . . . . .	227
Using Design Procedure By Example for Introspected Procedures . . . . .	229
<b>Using Transformations . . . . .</b>	<b>231</b>
Studio Transformation Types . . . . .	232
Creating an XML, XSLT, or Streaming Transformation . . . . .	234
Adding a New Transformation (XML, XSLT, or Streaming) . . . . .	235
Adding an XSLT Transformation for a Table, a View, or a Function . . . . .	236
Mapping Source Data to Target Output Columns (XSLT or Streaming) . . . . .	236
Adding Target Columns through the Outputs Panel (XSLT) . . . . .	239
Creating an XQuery Transformation . . . . .	240
Specifying a Target Value . . . . .	242
Viewing the Source Scope . . . . .	243
Specifying the Source for a Top-Level Element . . . . .	245
Specifying Settings for Target Sources in an XQuery Transformation . . . . .	245
Specifying Global Input Parameters in an XQuery Transformation . . . . .	247

Viewing and Editing the XQuery . . . . .	247
Viewing Output Parameters in the XQuery Transformation . . . . .	248
Upgrading XML to Tabular Mapping Transforms . . . . .	249
Upgrading and Creating a Backup of an XML to Tabular Mapping Transform . . . . .	250
Creating an Upgraded XML to Tabular Mapping Transform . . . . .	250
Executing a Transformation . . . . .	251
Converting XML to JSON using Design By Example . . . . .	252
JSON XML List Formatting Example . . . . .	253
<b>Using the Any-Any Transformation Editor . . . . .</b>	<b>255</b>
Transformation Editor Concepts . . . . .	255
The Transformation Editor Window . . . . .	256
Transformation Editor Terminology . . . . .	257
About Transformation Editor Operations and Parameter Containers . . . . .	257
Transformation Editor Limitations . . . . .	258
Using the Transformation Editor . . . . .	260
Creating a New Transform . . . . .	261
Undoing and Redoing Actions in the Transformation Editor . . . . .	262
Zooming and Arranging the Model . . . . .	262
Editing Operations in the Transformation Editor Model . . . . .	263
Adding Resources . . . . .	265
Working with Connections and Loops . . . . .	265
Adding Assign Links . . . . .	266
Adding Loop Links . . . . .	266
Using Auto Map Link Mode . . . . .	267
Using Auto Fill Link Mode . . . . .	268
Editing Loop Operations . . . . .	269
Adding Cast Operations to Connection Lines . . . . .	271
Working with Expressions . . . . .	271
About Expressions . . . . .	272
Adding Expression Operations . . . . .	274
Working with Operations . . . . .	275
Designing a Query Operation . . . . .	275
Adding Cast Operations from the Palette . . . . .	277
Adding Union Operations . . . . .	278
Adding Switch Operations . . . . .	279
Using the Create Operation Button . . . . .	282
Working with Operation and Parameter Container Details . . . . .	282
Defining Element Facets . . . . .	282
Defining Constant Values . . . . .	283
Editing Import Paths . . . . .	284
Edit Namespace Prefix Maps . . . . .	286
Using Cycle I/O Direction to Add or Delete Parameters . . . . .	288

Deleting Operations in the Transformation Editor .....	288
Working with Messages .....	289
Viewing Messages .....	289
Using Messages to Refine Your Transform .....	290
Editing Parameters on the Parameters Tab .....	291
Rebinding Transformation Operations .....	292
Working with the Transformation Editor XQuery Tab .....	293
Viewing and Copying the XQuery Code From Your Transform .....	294
Validating the Transform XQuery Code Using Studio .....	294
Using a Transform as a Resource in Another Transform .....	295
Caching Transform Data .....	295
<b>Definition Sets .....</b>	<b>297</b>
About Definition Sets .....	297
Creating a Definition Set .....	298
Creating a SQL Definition Set .....	299
Creating an XML Definition Set .....	302
Creating a WSDL Definition Set .....	304
Using a SQL Definition Set .....	305
Using an XML Definition Set .....	306
Using a WSDL Definition Set .....	307
<b>Triggers .....</b>	<b>309</b>
About Triggers .....	309
Creating a JMS Event Trigger .....	314
Creating a System Event Trigger .....	315
Creating a Timer Event Trigger .....	318
Creating a User-Defined Event Trigger .....	320
Creating Email Alerts .....	322
<b>Publishing Resources .....</b>	<b>325</b>
Updating Published Resources .....	325
About Publishing Resources .....	326
About the TDV DDL Feature .....	327
About the OData Feature .....	328
OData Support Limitations .....	329
OData v4 Support Limitations .....	329
OData Features .....	330
Reformatted Results .....	330
System Query Options .....	330

OData v4 Features . . . . .	333
Supported Operators . . . . .	333
. . . . .	334
Supported Functions . . . . .	334
Support for Published Resources . . . . .	336
Supported Query options . . . . .	336
OData to TDV Data Type Mappings . . . . .	337
Accessing REST-Based Web Services Using JSON. . . . .	338
Publishing Resources (Creation, Access, and Deletion) . . . . .	339
Publishing Resources to a Database Service . . . . .	340
Publishing Resources to a Database Service with OData . . . . .	342
Configuring DDL for a Data Service. . . . .	343
Configuring TEMP Table Space for a Data Service. . . . .	345
Publishing Resources to a Web Service . . . . .	346
About WSDL and Web Service Data Services . . . . .	346
Publishing a SOAP Data Service . . . . .	347
Publishing a Contract-First WSDL and SOAP Data Service . . . . .	353
Moving the Namespace Declaration From Elements to the Soap Header . . . . .	356
Publishing a REST Service. . . . .	357
Configuration Options for Publishing a REST Service . . . . .	357
Publishing a REST Data Service. . . . .	359
Accessing the Published REST Services . . . . .	364
Web Services Security. . . . .	364
Supported Web Service Security Standards . . . . .	365
Using a Predefined Security Policy for a Web Service. . . . .	366
Creating and Using a Custom Security Policy for a Web Service . . . . .	367
Security and Privileges on Published Resources . . . . .	368
Disable OData for Published Data Sources. . . . .	369
Unsupported Resource List Limit. . . . .	370
<b>Exploring Data Lineage . . . . .</b>	<b>371</b>
About Data Lineage . . . . .	371
Displaying Data Lineage . . . . .	374
Working with the Data Lineage Graph. . . . .	376
Changing the Resource Focus . . . . .	377
Changing What Is Displayed . . . . .	378
Filtering the Visible Columns . . . . .	379
Getting Resource Summary Information . . . . .	379
Getting Resource Details . . . . .	380
Using the History Feature. . . . .	382
Refreshing the Lineage Graph . . . . .	383

Printing the Lineage Graph .....	383
Exporting Lineage Reports to a Comma-Separated-Values File .....	385
Lineage Information for Different Resource Types .....	387
<b>TDV Caching .....</b>	<b>391</b>
Overview of TDV Caching .....	392
TDV Caching Concepts .....	393
What Is a Cache? .....	394
Why Use Caching? .....	394
When Should You Configure Caching? .....	394
What Types of Caching Are Available? .....	394
What is a Full Refresh Versus an Incremental Refresh? .....	395
What Are the Incremental Caching Options? .....	395
What TDV Resources Can I Cache? .....	396
What Cache Storage Options Are Available? .....	396
What Is a Cache Target? .....	396
What Refresh Options Are Available for a Cache? .....	397
What is a Cache Policy? .....	397
When Does Cache Data Expire and Get Removed From the Cache? .....	398
What is Cache Versioning, Transaction Integrity, and When Are Old Cache Contents Cleared Out? .....	399
Can Caches Be Exported and Imported? .....	399
How Does Error Handling Work for Resources that use Cache Policies? .....	399
How Does Error Handling Work for Resources with Individually Defined Cache Refresh and Expiration Schedules? .....	399
How Does TDV Caching Work? .....	400
How Does Table and View Caching Work? .....	400
What Is Procedure Caching? .....	401
What Is Transaction Result Caching for Procedures? .....	403
How Does Caching Data in a Cluster Environment Work? .....	404
TDV-Created Caching Objects .....	405
What Incremental Caching Options Are Available in TDV? .....	407
Pull-Based Incremental Caching .....	407
Push-Based Incremental Caching .....	407
About Native and Parallel (Bulk) Caching .....	408
Cache Status and Events Reporting .....	409
Cache Requirements and Limitations .....	409
Supported Data Sources for Caching .....	410
Supported Cache Target Storage Types .....	410
Privileges and Caching .....	415
Caching Limitations .....	416
Native (Bulk) Caching DDL Creation Limitations .....	417
Setting Up Caching .....	417
Caching Transaction Results of a Procedure .....	418
Caching to the Default Database Target .....	418

Caching to a File Target .....	420
Pre-Creating Caching Objects for Database Caching .....	421
Caching to a Single-Table Database Target .....	423
Creating a Multiple Table Cache on a Database Target .....	425
Configuring Teradata for Use as a Multi-Table Cache Target .....	425
Enabling Caching to Multiple Tables .....	426
Enabling Cache Data Storage to Multiple Data Sources .....	429
Setting Up Native (Bulk) Caching Options .....	431
Configuring TDV Native Loading Option for DB2 .....	432
Configuring TDV Native Loading Option for Microsoft SQL Server .....	434
Configuring Native Caching for Netezza .....	437
Configuring Native Caching for Oracle .....	439
Configuring Native Caching Option for Sybase IQ .....	439
Configuring Native Caching Option for Vertica .....	443
Setting Up the Parallel Cache Option .....	443
Enabling JDBC-Only Cache Loading .....	444
Canceling a Cache Refresh that Is Using Native or Parallel Loading .....	445
Defining Cache Refresh Behavior .....	445
Refresh Owner .....	446
Controlling Cache Refresh Behavior for Individual Resources .....	446
Refreshing and Clearing the Cache for One Resource Using Studio .....	446
Refreshing and Clearing Your Cache Programmatically .....	448
Controlling Cache Refresh Behavior for Multiple Resources .....	449
Defining a Cache Policy .....	450
Assigning Resources to a Cache Policy .....	452
Assigning a Cache Policy to a Resource .....	453
Defining Pre- and Post-Actions for a Full Refresh Mode Cache .....	454
Setting Up Pull-Based Incremental Cache .....	455
Pull-Based Incremental Cache Initialization Sample Script .....	458
Pull-Based Incremental Cache Refreshing Sample Script .....	459
Setting Up Push-Based Incremental Caching for Oracle .....	460
Cache Maintenance .....	460
Indexing Your Cache .....	460
Managing Configuration Changes and Cache Behavior .....	462
Displaying the Dependencies of a Cached View .....	463
Displaying the Dependencies of a Cache Policy .....	464
Managing Import and Export Cache Information .....	465
Exporting Your Cache Information .....	465
Importing Your Cache Information .....	465
Caching Tips from an Expert .....	466
Destroying a File or Default Cache .....	466
Managing Cache Status Table Probe Row Conflicts .....	466
Managing Unresponsive Cache Tables .....	467
Managing Open Connection Threads .....	468

Managing Buckets . . . . .	468
Managing Cache Data . . . . .	469
<b>TDV Configuration Parameters . . . . .</b>	<b>471</b>
Viewing or Editing Configuration Parameters . . . . .	471
Finding Parameters in the Configuration Window . . . . .	473
<b>Performance Tuning . . . . .</b>	<b>475</b>
About Performance Tuning in TDV . . . . .	475
Working with the SQL Execution Plan . . . . .	477
Generating and Displaying a SQL Execution Plan . . . . .	478
Execution Plan Nodes in the Tree Panel . . . . .	479
Execution Plan Query Attributes in the Details Panel . . . . .	482
Execution Plan Node Attributes in the Details Panel . . . . .	484
Updating the Query Execution Plan . . . . .	486
Viewing How Much Data was Processed by a Query . . . . .	487
Refreshing All Execution Plan Caches . . . . .	488
Creating Cardinality Statistics for Cost-Based Optimization . . . . .	489
Creating Cardinality Statistics for a View . . . . .	490
Creating Cardinality Statistics on a Data Source . . . . .	492
Scheduling Cardinality Statistics Refresh . . . . .	494
Refreshing Cardinality Statistics . . . . .	495
Using TDV API Procedures to Refresh or Cancel Resource Statistics . . . . .	496
Use Indexes, and Primary and Foreign Keys, to Improve Query Performance . . . . .	496
Types of Joins . . . . .	497
Automatic Option . . . . .	498
Hash Join Option . . . . .	498
NESTEDLOOP Join Option . . . . .	498
SORTMERGE Join Option . . . . .	499
SQL Join Reordering . . . . .	499
Multiple Join Conditions . . . . .	501
Semijoin Optimization Option . . . . .	503
About the Semijoin Optimization . . . . .	503
Semijoin Option Syntax Examples . . . . .	505
Setting Semijoin Configuration Parameters . . . . .	505
Configuring Your Data Source for the Semijoin Optimization . . . . .	507
Using the Semijoin Option . . . . .	508
Semijoin with Non-Equality Conditions Scenarios . . . . .	509
Star Schema Semijoin . . . . .	510
Using Oracle SQL Optimizer Hints . . . . .	511
Tuning Nested Aggregate Function Behavior . . . . .	512



Tuning Database Channel Queue Size .....	513
Specifying the Fetch Size for Oracle and MS SQL Server .....	513
<b>TDV Query Engine Optimizations .....</b>	<b>515</b>
Subquery Optimizations .....	515
Partition or Join Pruning Optimization .....	516
DATA_SHIP_MODE Values .....	517
Performance Configuration Parameter Tips from an Expert .....	517
<b>Data Ship Performance Optimization .....</b>	<b>519</b>
About Data Ship .....	520
Data Ship Support and Requirements .....	521
Data Ship Limitations .....	524
Defining TDV Data Ship Configuration Parameters .....	526
Configuring Data Ship .....	529
Configuring Data Ship for DB2 .....	530
Configuring Data Ship Bulk Loading Option for DB2 .....	531
Configuring Data Ship for Microsoft SQL Server .....	533
Configuring Data Ship for Netezza .....	535
Configuring Data Ship for Oracle .....	536
Configuring Data Ship for Sybase IQ .....	537
Configuring Data Ship for Sybase IQ Targets with Location .....	540
Configuring Data Ship for PostgreSQL and Vertica .....	540
Finishing Data Ship Configuration for Data Sources .....	540
Evaluating Queries for Data Ship Using Execution Plans .....	545
Using Time Series Functions for Vertica Data Ship Targets .....	546
Disabling Data Ship for Specific Query SQL .....	548
Managing Open Connection Threads .....	548
Using Data Ship for Prepared Statements .....	549
<b>Configuring the TDV Massively Parallel Processing Engine .....</b>	<b>551</b>
About the TDV MPP Engine Configuration .....	551
MPP Engine OS Support .....	552
Supported Data sources .....	553
Ports used for TDV MPP Engine .....	553
Setting Up and Configuring the TDV MPP Engine .....	554
When should the MPP Engine be engaged? .....	556
Configuring the MPP engine from the Query Execution Plan Viewer .....	557
Considerations for using MPP Engine .....	561

JOIN Restrictions . . . . .	562
Tuning the Server Configuration . . . . .	563
SQL Functions . . . . .	566
Canceling Jobs When MPP Engine is Active . . . . .	574
<b>Push-Based Incremental Caching . . . . .</b>	<b>575</b>
View Requirements and Restrictions for Push-Based Incremental Caching . . . . .	575
Requirements for Push-Based Incremental Caching . . . . .	576
Configuring Oracle Database for Push-based Incremental Caching . . . . .	577
Installing and Configuring Oracle GoldenGate . . . . .	578
Installing the TIBCO JAR File . . . . .	581
Configuring JMS Pump for Oracle GoldenGate Using TIBCO EMS . . . . .	581
Adding the Change Notification Custom Java Procedures . . . . .	582
Defining Connectors . . . . .	583
Install the Central Server. . . . .	584
Configuring Push-Based Incremental Caching and Change Management. . . . .	584
Publishing the cms_call_propagator Procedure . . . . .	585
Configuring Oracle Data Sources for Change Notification . . . . .	585
Setting Up an Push-Based Incremental Cache in Studio . . . . .	586
Publish Push-Based Incremental Caches. . . . .	588
Recovering from a Messaging Error . . . . .	588
Push-Based Incremental Caching Configuration Parameters. . . . .	590
<b>Legacy Web Services . . . . .</b>	<b>599</b>
Limitations for Legacy Web Service Conversion. . . . .	599
Converting Legacy WSDL Data Sources to SOAP Data Sources . . . . .	600
Converting Legacy Web Service. . . . .	600
<b>Studio User Interface Reference . . . . .</b>	<b>603</b>
Studio Menus . . . . .	603
File Menu . . . . .	604
Edit Menu . . . . .	604
View Menu . . . . .	604
Resource Menu . . . . .	605
Studio Status Bar . . . . .	605
Studio Text Editing . . . . .	606
Line numbers in the SQL Editor. . . . .	606
Studio Code Editing Keyboard Shortcuts. . . . .	607
View and Table Editor Panel Reference . . . . .	611

Model Panel .....	611
Grid Panel .....	611
SQL Panel .....	612
Columns Panel .....	612
Indexes Panel .....	612
Foreign Keys Panel .....	612
Cardinality Statistics Panel .....	612
Rebind Panel .....	612
Result Panel .....	613
Execution Plan Panel .....	613
Procedure Editor Panel Reference .....	613
Introduction to Procedure Panels and Tabs .....	614
Model Panel .....	615
Grid Panel .....	616
SQL Script Panel .....	616
SQL Panel .....	616
Parameters Panel .....	617
Data Map Panel .....	617
XSLT Panel for XSLT Transformations .....	617
XSLT Panel for XSLT Procedures .....	618
XQuery Panel .....	618
Inputs Panel .....	618
Outputs Panel .....	618
XSLT Debug Input Panel .....	619
XSLT Debug Output Panel .....	619
Trigger Editor Panel Reference .....	619
Condition Tab .....	620
Action Pane .....	621
SQL Definition Set Editor .....	624
SQL Definition Set Editor Toolbars .....	624
XML Definition Set Editor .....	624
XML Schema Panel (XML Definition Set) .....	625
XML Schema Panel Toolbar .....	625
WSDL Definition Set Editor .....	626
WSDL Panel .....	626
WSDL Panel Toolbar .....	627

# Preface

---

Documentation for this and other TIBCO products is available on the TIBCO Documentation site. This site is updated more frequently than any documentation that might be included with the product. To ensure that you are accessing the latest available help topics, please visit:

- <https://docs.tibco.com>

## Product-Specific Documentation

The following documents form the TIBCO® Data Virtualization(TDV) documentation set:

- **Users**
  - TDV Getting Started Guide
  - TDV User Guide
  - TDV Client Interfaces Guide
  - TDV Tutorial Guide
  - TDV Northbay Example
- **Administration**
  - TDV Installation and Upgrade Guide
  - TDV Administration Guide
  - TDV Active Cluster Guide
  - TDV Security Features Guide
- **Data Sources**
  - TDV Adapter Guides
  - TDV Data Source Toolkit Guide (Formerly Extensibility Guide)
- **References**
  - TDV Reference Guide
  - TDV Application Programming Interface Guide

- **Other**
  - TDV Business Directory Guide
  - TDV Discovery Guide
- *TIBCO TDV and Business Directory Release Notes* Read the release notes for a list of new and changed features. This document also contains lists of known issues and closed issues for this release.

## How to Access TIBCO Documentation

Documentation for TIBCO products is available on the TIBCO Product Documentation website mainly in the HTML and PDF formats.

The TIBCO Product Documentation website is updated frequently and is more current than any other documentation included with the product. To access the latest documentation, visit <https://docs.tibco.com>.

Documentation for TIBCO Data Virtualization is available on <https://docs.tibco.com/products/tibco-data-virtualization-server>.

## How to Contact TIBCO Support

You can contact TIBCO Support in the following ways:

- For an overview of TIBCO Support, visit <https://www.tibco.com/services/support>.
- For accessing the Support Knowledge Base and getting personalized content about products you are interested in, visit the TIBCO Support portal at <https://support.tibco.com>.
- For creating a Support case, you must have a valid maintenance or support contract with TIBCO. You also need a user name and password to log in to <https://support.tibco.com>. If you do not have a user name, you can request one by clicking **Register** on the website.

## How to Join TIBCO Community

TIBCO Community is the official channel for TIBCO customers, partners, and employee subject matter experts to share and access their collective experience. TIBCO Community offers access to Q&A forums, product wikis, and best practices. It also offers access to extensions, adapters, solution accelerators, and tools that extend and enable customers to gain full value from TIBCO products. In addition, users can submit and vote on feature requests from within the [TIBCO Ideas Portal](#). For a free registration, go to <https://community.tibco.com>.



# Overview of Studio

---

This topic describes Studio, the main tool for working with TIBCO® Data Virtualization (TDV). It covers how to run Studio and describes its user interface.

- [About Studio, page 19](#)
- [Opening Studio and Switching User, page 25](#)
- [Customizing Studio, page 27](#)
- [Modifying Studio Memory Usage, page 34](#)
- [Changing Your TDV Password, page 34](#)
- [Security Features, page 39](#)


## About Studio

Studio is the primary tool you use to work with TDV. Studio has three major components, accessed using tabs along the left side of the Studio window:

- **Modeler**
  - Model, manage, and publish data sources, transformations, views, SQL scripts, parameterized queries, packaged queries, definition sets, triggers, TDV databases, and Web services.
  - Define and refine resource properties and parameters using one of the work space editors.
  - Archive, export, and import TDV resources.
  - Configure TDV components and operational controls.
- **Manager**
  - Monitor and manage resource activities, including data source interactions with TDV. See the *TDV Administration Guide* for more information.

- Discovery
  - Reveal hidden correlations in enterprise data so you can build data models for data virtualization and reporting.
  - Scan data and metadata from across data repositories, whether they are applications, databases, or data warehouses.
  - Using Discovery's graphical tools, create data models based on system metadata and discovered relationships. For details, see the *Discovery User Guide*.

The following graphic identifies the main components of the Modeler window.



For more information about the Modeler resource tree, see [Modeler Resource Tree](#), page 21.




The contents of the Modeler work space depends on the type of resource you have opened. Each resource has its own resource editor, and the editor usually has multiple tabs. To learn about the work space contents and how to work with each type of resource, refer to the appropriate topic of this manual.

## Modeler Resource Tree

The Modeler resource tree is a hierarchical structure of all currently defined resources. TDV uses the term *resources* to collectively refer to all objects that are used for data modeling and building business solutions using TDV software. These resources include data sources, views, parameterized queries, SQL scripts, Java procedures, packaged queries, transformations, and TDV data services (which are available as TDV databases and Web services). See these sections for more details about the Modeler resource tree:

If you hover the pointer over the name of a resource, a tooltip displays information about the resource. The tooltip contents depends on the resource type.



The parent container path plus the resource name make up a unique identifier for invoking and referencing any TDV-defined resource. For example, the `inventorytransactions` table is referred to as `/shared/examples/ds_inventory/inventorytransactions`. This reference to this table is different from the XML schema definition set with the same name—`/shared/examples/InventoryTransactions`—both because the parent container path is different and because the name and path used to refer to the resource are case-sensitive.

**Note:** The resource tree displays only the resources the current user has permissions to view and use.

### Location where Resource Tree Items Are Saved

The following table lists the relationship between the resources displayed in the resource tree.

Resource in the workspace and published areas	Resource in <TDV Host>
Desktop <current user>	/users/<domain>/<current user>

Resource in the workspace and published areas	Resource in <TDV Host>
Desktop <current user>/Data Services	/services
Desktop <current user>/Data Services/Databases	/services/databases
Desktop <current user>/Data Services/Web Services	/services/webservices
Desktop <current user>/My Home	/users/<domain>/<current user>
Desktop <current user>/Shared	/shared

The resource tree displays all system-created containers and all resources currently defined in TDV. When you create a new resource to use in the system, you add that resource to a container. None of the top-level system-created containers can be edited or deleted. The system-created nodes in the resource tree are described in the following sections:

- [Desktop, page 22](#)
- [Data Services, page 22](#)
- [My Home, page 23](#)
- [Shared, page 24](#)
- [<TDV Host>, page 24](#)

## Desktop

The Desktop represents the current user's virtual work area on TDV Server. Some container names shown on the Desktop are shortcuts that provide easy access to containers deeper in the server's resource hierarchy (Data Services, My Home, Shared). The fourth container on the desktop, <TDV Host>:<port id>, represents the complete resource hierarchy of the server, including the contents of the other three Desktop containers.

**Note:** You cannot add a resource directly to the Desktop node of the resource tree.

## Data Services

The Data Services folder contains two system-created containers, neither of which can be edited or deleted:

- **Databases**, into which you publish the resources that you want to make available to client applications that connect to TDV Server.
- **Web Services**, into which you publish the resources that you want to expose to Web Services clients.

Databases and Web Services within Data Services display all the resources published by any user in the system. Each published resource is tied to an unpublished resource residing elsewhere in the system.

For details on publishing, see [Publishing Resources, page 325](#). For details on how clients can access the published resources, see the *TDV Client Interfaces Guide*.


The **Databases/system** folder of the resource tree contains system tables that are used by the TDV system. For details on the contents of Databases/system, see the *TDV Reference Manual*.

**Note:** The system tables are subject to change with new releases of the system.

## My Home

My Home is a semi-private (visible only to you and an administrator with full privileges) work area where you can design, develop, and test resources prior to exposing them as shared resource definitions or publishing them as externally available resources.

My Home is a shortcut to the directory folder `<hostname>/users/<Domain>/<CurrentUser>`. The name of the Studio user appears in parentheses at the top of the Studio navigation tree.



My Home cannot be deleted, and ownership of the container is ordinarily not reassigned. My Home can contain any other type of resource. These resources can reference other shared or published resources. For details about adding and publishing resources, see [Publishing Resources to a Database Service, page 340](#).

## Shared

Shared is a system-created container that contains all resources made available to all users in the system with appropriate access privileges. It is a place to store projects for teams to work on. For details about access privileges, see the *TDV Administration Guide*.

### Shared/examples

This folder contains sample resources. For more information, see the *TDV Getting Started Guide*.

## <TDV Host>

<TDV Host> is the name and port ID (in the form <TDV Host:Port ID>) of the TDV server to which Studio is connected. If Studio is connected to TDV on the local computer, the hostname is localhost by default. The default port number is 9400. <TDV Host> represents the entire contents of the TDV Server on your machine and has the following system-created containers:

Containers	Description
services	The services container has the same contents as the desktop folder named Data Services.
lib	The lib container contains all the system API calls. For details, see the <i>TDV Application Programming Interfaces Guide</i> .
security policy	This container holds security policies. TDV comes with a set of prebuilt security policies and if you define custom security policies, they are saved in this location.
shared	The shared container has the same contents as the desktop folder named Shared. When you add any resource to <TDV Host>/shared, the change is reflected in the structure of Desktop/Shared. For details, see <a href="#">Location where Resource Tree Items Are Saved, page 21</a> .
policy	Contains security and cache policies.

Containers	Description
users	<p>The users container has one container for each security domain in the server. The default domain composite is system-created, and cannot be edited or deleted. The system-created user named admin belongs to the domain composite.</p> <p>Each domain in users is represented by a folder-container, and each domain has a container for each user in that domain. These containers are referred to as those users' "home folders."</p> <p>You cannot add a resource directly to the users node, but when an administrator adds a user to a domain in the system, the new user's name and resources are displayed here. For details on adding users to the system, see the <i>TDV Administration Guide</i>.</p> <p>From users, you can view other users in the system and use their resources if you have appropriate access privileges.</p> <p>If you view your home folder from users, you see your Desktop/My Home, because My Home represents your home folder.</p>

## Opening Studio and Switching User

- [Starting Studio, page 25](#)
- [Starting Studio from the Command Line, page 26](#)
- [Changing the Connection Type, page 26](#)

### Starting Studio

Studio provides access to TDV and its resources. When you start Studio, you need to know the TDV Server instance to which you want to connect, the domain, and the port ID. For details, see the *TDV Installation and Upgrade Guide* or the *TDV Getting Started Guide*.

#### To start Studio

1. Select Start > All Programs > TIBCO > Studio <ver> > Start Studio <ver> from the Windows desktop. This command opens the Studio sign-in window.
2. Enter your user credentials and information for the TDV to which you are connecting. For details, see the *TDV Installation and Upgrade Guide* or the *TDV Getting Started Guide*.
3. Click Connect.

4. Click OK.

Studio opens on the Modeler tab (top tab along the left edge of the window).

See [About Studio, page 19](#) for information about how the Studio user interface is organized.

## Starting Studio from the Command Line

Studio provides access to the TDV Server and its resources. When you start Studio, you need to know the TDV Server instance to which you want to connect, the domain, and the port ID. For details, see the *TDV Installation and Upgrade Guide* or the *TDV Getting Started Guide*.

### To start Studio from the command line

1. Open a UNIX or Windows command line tool.
2. Type one of the following:

Command	Description
studio.bat	Starts Studio from a DOS prompt.
studio.sh	Starts Studio from a UNIX prompt.
studio.bat -server=hostname	Starts Studio from a DOS prompt for a specific TDV Server.
studio.sh -server=hostname	Starts Studio from a UNIX prompt for a specific TDV Server.

3. Enter your user credentials and information for the TDV to which you are connecting. For details, see the *TDV Installation and Upgrade Guide* or the *TDV Getting Started Guide*.
4. Click Connect.
5. Click OK.

Studio opens on the Modeler tab (top tab along the left edge of the window).

See [About Studio, page 19](#) for information about how the Studio user interface is organized.

## Changing the Connection Type

You can change users, domains, TDV Servers, ports, or connection security level. The TDV system administrator must set the Java Key Store for use in securing the SSL connection. For details, see the *TDV Administration Guide*.

### **To change the user, port, domain, or connection type, and then restart Studio**

1. On the File menu, choose Switch User.
2. In the dialog box that appears, confirm that you want to switch user by clicking Yes.
3. Supply your username and password, and enter the domain, server, and port information.
4. (optional) If the connection must be secured, check the Encrypt check box to initiate an SSL connection between Studio and TDV.
5. Click Connect. Studio reopens.

## **Customizing Studio**

This section contains topics that you can use to customize your Studio experience.

- [Customizing Studio Using the Studio Options Dialog, page 27](#)
- [Customizing Studio Result Panel XML Text, page 33](#)

## **Customizing Studio Using the Studio Options Dialog**

The Studio Options dialog lets you configure Studio behavior locally. You can customize:

- What information is displayed in the title bar.
- What toolbars are displayed.
- Whether logging is enabled.
- How warnings and confirmations are handled.
- How editors are displayed in the workspace.

Other Studio instances installed on different computers that log onto the same TDV Server are not affected by these local Studio options.

### **To customize Studio**

1. Open Studio and log in.
2. Select Edit > Options.

Studio opens the Options dialog box with the General tab displayed.

## 3. Edit the options as necessary.

Check box	Description
Display version, server host name, and port number in the title bar	Useful when the Studio user can connect with any one of several instances of TDV.
Display custom name in the title bar	Enter a string to display your text in the Studio application title bar.
Store execution parameters on disk and reuse when Studio runs again	Makes this Studio instance remember the procedure input parameters used during Studio test execution, so the test is easier to duplicate.
Copy privileges from parent folder when creating new resources	Sets the default privileges to apply creating new resources, making child resources accessible to the same groups and users.
Use a colored background in the View Model	Toggles the View Model background between blue and white.
Show the toolbar at top of main window	Toggles display of the Studio toolbar.
Show the status bar at bottom of the main window	Toggles display of the Studio status bar. This bar shows encryption status of the connection between the Studio and TDV, Studio memory usage, and introspection progress (when underway).
Show the navigation tree in main window	Toggles display of the Studio resource tree in Studio Modeler. This setting also toggles display of the Manager navigation panel.
Logging - Enable additional logging within Studio	Adds logged detail to assist with debugging. This can add a lot of information to the log file but has little affect on performance. Additional logging information is sent to the <TDV_install_dir>/logs/sc_studio.log file, which you can view using the View Studio Log button.
Data Source Introspection - Cache Loading Page Size	This value adjusts the page size to use for cache during introspection.
Session Heartbeat(millisecond)- Session Heartbeat Interval	This value adjusts the Studio session timeout. After a timeout, Studio prompts you to sign in again.



Check box	Description
Default Font	<p>This option lets the user select a general UI font for Studio. This selected font will be saved to studio.properties. After Studio is restarted, this user-selected font will be applied.</p> <p>For example, a Thai language user can select a Thai language-supported font such as Tahoma and apply the font throughout Studio.</p> <p><b>Note:</b> Since the Default Font for Studio and the Font used in Editor are treated separately, the user will need to change the font in both the places, as given below, to a Thai language-supported font (Tahoma) and restart Studio.</p> <p>Studio &gt; Edit &gt; Options &gt; Default Font &gt; Tahoma</p> <p>Studio &gt; Edit &gt; Editors &gt; Font &gt; Tahoma</p>

4. Select the Warnings tab and edit the options as necessary.

Warnings and confirmations check boxes can reset display of notifications and confirmation dialogs. These settings can be indirectly unchecked by dismissing a notification confirmation dialog after checking “Do not show me this warning again.”

Check Box	Description
Mark folders impacted when they contain descendants that are impacted.	Selected, by default, to show indications that folders contain resources that are impacted by changes or have error that might need correcting. Clear to remove the warning icon from Studio resource tree folder objects. The warning will continue to appear next to the impacted resource regardless of the selection made here.
Warn before execution when other editors are unsaved	When checked, warns that a procedure will return results based on the resource metadata definitions saved on the server, and not as-yet unsaved definitions in editors currently open on the Studio desktop.
Warn when canceling the execution of a query.	
Warn before data lineage calculation when current editor is unsaved	When checked, warns that the data lineage calculation will return results based on resource metadata definitions on the server, rather than metadata changed but not yet saved in an open editor.

Check Box	Description
Warn when an OLAP View member is selected on Where tab, but its dimension is not selected on Select tab	
Warn when OLAP View members from same dimension but different hierarchies are selected on Where tab	
Display confirmation prior to closing Studio.	Display Confirmation check boxes display warning prompts even if warnings have been marked as not to be displayed again.
Display confirmation prior to clearing all relationship discovery tasks.	Displays confirmation prior to removal.
Display confirmation prior to removing the view model.	
Display confirmation prior to removing the OLAP view model.	

5. Select and edit the options on the Editors tab as necessary.

Some Studio text editor formatting and font display options are configurable. Each of the groups has a Reset button on the right, and the Editors tab has an overall Restore Defaults button at the bottom.

Option	Description
Automatic Capitalization	Capitalizes and formats SQL keywords when they are typed or pasted. You can set font, color and size using the Studio Options dialog.

Option	Description
Automatic Indentation	<p>Automatically indents text based on the SQL keyword on the previous line. The following keywords have the same indentation, and the SQL Editor indent the line that follows a keyword in this list:</p> <p><code>SELECT, FROM, WHERE, GROUP BY, HAVING, ORDER BY, FULL OUTER JOIN, LEFT OUTER JOIN, RIGHT OUTER JOIN, INNER JOIN, UNION, UNION ALL, EXCEPT, EXCEPT ALL, INTERSECT, and INTERSECT ALL.</code></p> <p>Additionally newlines made with an Enter keystroke start with the indentation present on the preceding line, whether indentation is done with spaces or tabs. A single Backspace keystroke puts the cursor back at the far left position of the line.</p>
Indent with Spaces (not tabs)	<p>Allows insertion of spaces (ASCII character 32) for indentation instead of tabs (ASCII character 9). Both are handled as required for querying the underlying data sources. By default, tabs are used for indentation.</p> <p>Tab width lets you change to the default tab width as represented by spaces. Manually entered tabs can differ from the default SQL display of four spaces used as indentation.</p>
Tab Width	<p>Lets you change tab spacing from four (default) character widths to any value between 1 and 32.</p>
Reset Format Defaults	<p>Restores formatting options to their default values.</p>
Comment, Keyword, Literal, Label, Operator, Invalid	<p>Offers you a palette of colors to apply to categories of text in SQL statements. You can select each color from a group of swatches, from a hue-saturation-brightness (HSB) model, or (using sliders) from a red-green-blue (RGB) model.</p>
Reset Color Defaults	<p>Restores formatting options to their default values.</p>
Font list	<p>Lets you select a font family from the scroll list.</p>
Font size list	<p>Lets you select the font size from the scroll lists.</p>
Bold	<p>Check box that lets you select or unselect bold font.</p>
Italic	<p>Check box that lets you select or unselect italic font.</p>
Reset Font Defaults	<p>Restores font options to their default values.</p>
scrollable field	<p>Lets you preview what the SQL text looks like with your font family, size, and bold or italic choices.</p>

**Note:** Oracle JDK no longer ships any fonts and relies entirely on fonts installed on the operating system.

For more information about Fonts refer to following documentation:

- [Supported Fonts.](#)
  - [Removal of Lucida Fonts from Oracle JDK](#)
6. Select and edit the options on the SQL Scratchpad tab as necessary.

Some Studio SQL Scratchpad editor options are configurable in the SQL Scratchpad tab of the Studio Options panel. See [Views and Table Resources, page 133](#) for more information about how to use the SQL Scratchpad. Each group has a Reset Settings button on the right, and the SQL Scratchpad tab has an overall Restore Defaults button.

Item	Description
Open SQL Scratchpad Editor when Studio starts if it was open at exit check box	When checked, causes the SQL Scratchpad editor to open automatically when Studio restarts in cases where it was open when Studio was last exited. Default: checked.
Automatically save content when the editor is deactivated check box	When checked, causes Studio to save the SQL query currently being displayed in the SQL Scratchpad editor, as well as all queries in the History list, when you close the SQL Scratchpad editor. Default: checked.
Maximum History Size drop-down list	Lets you retain between 2 and 50 of the most recent SQL queries you have created in the SQL Scratchpad editor. Locked queries in the History list do not count toward this maximum. Default: 12.

7. Select and edit the options on the Transformation Editor tab as necessary.

Item	Description
Maximum Operation Width	Set the maximum width of the operations shown on the Transformation Editor model page.
Error Level to Show in the Editor	Defining a transform can be complicated, you can configure the level of error reporting displayed by Studio while you are defining your transform.

Item	Description
Show Insert Cast Dialog	When adding a cast function to your transform, you are shown a dialog to help you define the details of the cast.  Prefixes are also used when defining namespaces. Seeing the namespace can help you avoid namespace conflicts.
Show Prefixes in Type Names	The prefix values are used to indicate function type. They can be used to identify if a function is SQL or custom.
Show Operation Annotations	For the operations shown on the Transformation Editor, display any annotations in the heading portion of the operations.

8. Save your changes.

## Customizing Studio Result Panel XML Text

Many of the resources that you execute within Studio produce XML result sets that can be viewed in the Studio Result panel. Occasionally the XML displayed in the Result panel does not format well. If your XML isn't formatting well in the Result panel, it means that you are not retrieving the full result set. Studio has a configuration parameter that can be used to manipulate the total number of characters retrieved in XML results.

### To customize the Result panel XML text

1. Validate that your XML for a resource is not formatting well in the Result panel. For example, lines are run together.
2. Select Administration > Configuration.
3. In the Configuration window, navigate to Studio > Data > XML Text Size.
4. Increase the value of the total number of characters to retrieve in the XML result.
5. Click OK.
6. Execute the resource that previously had XML formatting problems.
7. Validate that the XML file is formatting correctly.

If your XML is still not formatting, continue to increase the value of the XML Text Size parameter until the XML formats as expected.

## Modifying Studio Memory Usage

You can change the extended memory and maximum memory allocation pool values for Studio.

### To change your Studio memory settings

1. Select Edit > Options.
2. On the Memory tab, type values for the following:

Field label	Description
Xms	The initial memory allocation pool or eXtended Memory Specification for a Java Virtual Machine (JVM).
Xmx	The maximum memory allocation pool for a Java Virtual Machine (JVM).

3. Optionally, choose to have Studio restart.
4. Optionally, choose to have Studio stop showing memory is low messages.
5. Click OK.
6. Make sure that Studio restarts and that your new settings are applied.

## Changing Your TDV Password

You can change your password using Studio's File menu, if you have the Access Tools right.

Changes made to the user rights profile take effect nearly immediately because TDV checks for appropriate rights every time feature access is attempted.

### To change your own password using Studio

1. Select File > Change Password.
2. In the Change Password window:
  - a. Type the old password in the Old Password field.
  - b. Type the new password in the New Password field.
  - c. Type the new password again in the Confirm Password field.
3. Click OK.

**Note:** "\*\*\*\*\*NOT\_UNKNOWN\*\*\*\*\*" is a reserved token string. Do not use it in any TDV password fields.

## Using the Code Editor Text Editing Commands

Editors within Studio including View, procedure, XML, and transformation editor dialogs come with a set of shortcut keys that enhance code editing.

The enhanced editing capabilities are enabled by default.

### To use the primary enhanced capabilities:

- For a list of shortcut keys and capabilities, see [Editor Text Editing Command Reference, page 36](#).
- In some editors, Ctrl-Space provides a list of potentially useful words from which you can select. For example in the SQL and procedure editors you can get a list of reserved words or function names.
  - You can start typing the word you are looking for to narrow the list results.

### To turn off these editing capabilities:

1. Select Edit > Options.
2. In the Options dialog, select the Editors tab.
3. Clear the Auto Complete check box.
4. Restart the TDV Server.

## Editor Text Editing Command Reference

Name	Shortcut Key	Description
Backspace	BACK_SPACE	Delete the previous character at the cursor position.
Delete to Word Start	Ctrl+ BACK_SPACE	Delete previous characters until encountering a non-word character.
Delete	DELETE	Delete the next character at the cursor position.
Delete to Word End	Ctrl+ DELETE	Delete the next characters until encountering a non-word character.
Delete Line	Shift+ DELETE	Delete the current line.
Insert Line Break	ENTER	Insert a line break at the cursor position.
Split Line	Ctrl+ ENTER	Insert a line break at the cursor position and keep current cursor position.
New Line	Shift+ ENTER	Start a new line next to the cursor and put cursor at the beginning of the new line.
Indent Selection	TAB	If there is no text selected, indent the line where the cursor is located, If there are selected lines of text, indent all selected lines.
Unindent Selection	Shift+ TAB	Unindent the line where the cursor is. If text is selected, unindent all selected text.
Join Lines	Ctrl+ Shift+ J	If no specific text is selected, join the current line with the next.  If there are selected lines of text, join all the selected lines.
Toggle Insert/Overwrite	INSERT	Toggle between the override and insert state.
Toggle Rectangular Selection	Ctrl+\ \	Toggle from regular selection and rectangular selection.
Toggle Case	Ctrl+ Shift+ U	Toggle the case of the selection.
Undo	Ctrl+ Z	Undo the last editing operation.



Name	Shortcut Key	Description
Redo	Ctrl+ Shift+ Z	Redo the last undone editing operation.
Cut	Ctrl+ X or Shift+DELETE	Cut the currently selected text. If nothing is selected, cut the current line.
Copy	Ctrl+ C or Ctrl+ INSERT	Copy the currently selected text. If nothing is select, copy the current line.
Paste	Ctrl+ V or Shift+ INSERT	Paste the clipboard contents to the current cursor position.
Paste from History	Ctrl+ Shift+ V or Ctrl+ Shift+ INSERT	Provides a selection dialog so that you can choose historical clipboard content and paste it into the new location.
Find	Ctrl+ F	Provides an editing dialog so that you can type text for which to search.
Find Next	F3	Find the next occurrence of the searching text.
Find Previous	Shift+ F3	Find the previous occurrence of the searching text.
Replace	Ctrl+ R	Provides an editing dialog so that you can type replacement text.
Select All	Ctrl+ A	Select all the text in the editor.
Move to Line Start	HOME	Move the cursor to the start of the current line.
Move to Line End	END	Move the cursor to the end of the current line.
select to Line Start	Shift+ HOME	Select from the current cursor position all the way to the line start.
select to Line End	Shift+ END	Select from the current cursor position all the way to the line end.
Move to Document Start	Ctrl+ Home	Moves the cursor to the start of the code editor.
Move to Document End	Ctrl+ End	Moves the cursor to the end of the code editor
Select to Document Start	Ctrl+ Shift+ Home	Select from the current cursor position all the way to the document start.

Name	Shortcut Key	Description
Select to Document End	Ctrl+ Shift+ End	Select from the current cursor position all the way to the document end.
Page Up	PAGE_UP	Move the cursor one page up
Page Down	PAGE_DOWN	Move the cursor one page down
Select to Previous Page	Shift+ PAGE_UP	Select from the current cursor position up by one page.
Select to Next Page	Shift+ PAGE_DOWN	Select from the current cursor position down by one page.
Move to Previous character	Left_arrow	Move the cursor one character to the left.
Move to Next character	Right_arrow	Move the cursor one character to the right.
Select Previous character	Shift+ Left_arrow	Select the previous character from the current cursor position.
Select Next character	Shift+ Right_arrow	Select the character after the current cursor position.
Move to Previous Word	Ctrl+ Left_arrow	Move the cursor to the previous word â?the first space character before the current cursor position
Move to Next Word	Ctrl+ Right_arrow	Move the cursor to the next word â?the first space character after the current cursor position
Select Previous Word	Ctrl+ Shift+ Left_arrow	Select the current cursor position to the first space character before it.
Select Next Word	Ctrl+ Shift+ Right_arrow	Select the current cursor position to the first space character after it.
Move to Previous Line	UP	Move the cursor up by one line.
Move to Next Line	DOWN	Move the cursor down by one line.
Select Previous Line	Shift+ UP	Select from the cursor position up by one line.
Select Next Line	Shift+ DOWN	Select from the cursor position down by one line.

Name	Shortcut Key	Description
Goto Line	Ctrl+ G	Provide a line index selector so that you can scroll to a particular line in the editor.
Select Word at Caret	Ctrl+ W	Select the current word.
Select to Matching Bracket	Ctrl+ B	Select the current block that starts and ends with two matching brackets.
Duplicate Selection	Ctrl+ D	Duplicate the selection. If there is no selection, the line where the cursor is located is duplicated.
Comments	Ctrl+Hyphen (-)	Comment a line or selected lines for SQL, XML, and XQuery editors.
Manual Fold Section	Ctrl+Period (.)	Folds the selected text to hide it from view. Works for the current session.
Expand Folding	Ctrl+ Equal_Sign	Expands the currently folded text selection.
Expand All Foldings	Ctrl+ Shift+ Equal_Sign	Expand all the folded text in the current editor.

## Security Features

Security features are discussed throughout this guide, but especially in these topics and sections:

- **HTTPS**  
Publishing resources ([Publishing Resources, page 325](#))
- **Kerberos**  
Configuring and connecting data sources ([Configuring Relational Data Sources, page 87](#), [Configuring Web-Based Data Sources, page 97](#), [Configuring File Data Sources, page 161](#))  
Publishing resources ([Publishing Resources, page 325](#))
- **Passwords**  
In studio ([Changing Your TDV Password, page 34](#))  
Working with data sources ([Working with Data Sources, page 67](#))  
Working with views ([Views and Table Resources, page 133](#))

Publishing resources ([Publishing Resources](#), page 325)

Setting up and using caching ([TDV Caching](#), page 391)

Setting up and using data ship ([Data Ship Performance Optimization](#), page 519)

- SSL

In Studio ([Customizing Studio](#), page 27)

Working with data sources ([Working with Data Sources](#), page 67)

Publishing to a database service ([Publishing Resources to a Database Service](#), page 340)

# Studio Resource Management Overview

---

This topic describes how to create and work with TDV resources in Studio.

- [About Resource Management, page 41](#)
- [Creating a TDV Resource, page 42](#)
- [Opening a Resource, page 44](#)
- [Getting Information about a Resource, page 44](#)
- [Annotating a Resource, page 46](#)
- [Moving, Copying, Deleting, or Renaming a Resource, page 46](#)
- [Searching for Resources in the Server, page 48](#)
- [Impacted Resources, page 49](#)
- [Exporting \(Archiving\) and Importing Resources, page 52](#)
- [Using Studio for a Full Server Backup, page 62](#)
- [Annotating a Resource, page 46](#)

## About Resource Management

Resource management involves creating and manipulating containers and resources in the TDV system. TDV resources are defined as the objects that are created, stored, and accessible in Studio including data sources, views, procedures, models, and the containers in which resources are organized. The containers are often referred to as folders.

The management of TDV resources includes such actions as creating, editing, copying, exporting, deleting, renaming, and moving the resources in the Studio resource tree.

Consider the following:

- To make a resource available to client programs, you must publish that resource. See [Publishing Resources, page 325](#).
- APIs are available (in `/services/webservices/system/admin/resource/operations`) for resource management. See the *TDV Application Programmer Interface Guide* for details.

- Built-in procedures are available in the TDV system library (in `/lib/resource`) for managing resources. Refer to the *TDV Reference Guide* and the *TDV Application Programmer Interface Guide* for details.

## Creating a TDV Resource

When you create a resource, you are adding an instance of the resource to the metadata repository. For a description of the hierarchy of user-created resources, refer to [Modeler Resource Tree, page 21](#).

The process you follow and the resource access rights depend on the type of resource, as described in these sections:

- [Locating a Container for a TDV Resource, page 42](#)
- [Creating a Resource, page 43](#)
- [Copying Privileges to Another Resource, page 43](#)

You must grant access and use privileges explicitly to other users and groups before they can use the resource you create. For details on access privileges, see the *TDV Administration Guide*.

## Locating a Container for a TDV Resource

You can create a TDV resource in your home folder (My Home), the Shared node, or in someone else's home folder, as long as you have the Write privilege on that container.

### To find a container for a TDV resource

1. Right-click the container to open the context menu.
2. If `New <resource_type>` is listed for the resource-type in the menu that you want, you can create the resource in that container. Select that item and follow the procedure in [Creating a Resource, page 43](#).

Or

1. Select a container.
2. Select `File > New`. If `<resource_type>` is listed in the submenu, you can create the resource in that container. Select that resource type and follow the procedure in [Creating a Resource, page 43](#).

## Creating a Resource

This section describes the common procedure for creating TDV resources. Several basic resource types are created in the same way. These resource types include:

- Definition sets (SQL, XML, or WSDL)
- Folders
- Models
- Parameterized queries
- SQL scripts
- Triggers
- Views
- XQuery procedures

Creation and configuration of other resource types are described elsewhere:

- Data sources are discussed in [Working with Data Sources, page 67](#) through [Configuring File Data Sources, page 161](#).
- Packaged queries are discussed in [Procedures, page 185](#).
- Transformations are discussed in [Using Transformations, page 231](#).

### To create a basic TDV resource

1. Right-click the container where you want to add the resource, and select New <resource\_type>; or select the container and then File > New > <resource\_type>. [Locating a Container for a TDV Resource, page 42](#)
2. Type a name for the resource in the input field, and click OK.
3. To apply the privilege settings of the selected parent folder to the new resource object, check the Copy privileges from parent folder check box.

By default, only you and administrators with Modify and Read All Resources rights can use the resource you create. If you do not elect to copy privileges from the parent folder, you need to modify resource privileges directly to let others share or use that resource.

4. Click OK.

## Copying Privileges to Another Resource

You can set privileges on a resource in several ways. One way, described here, is to copy privileges from an existing container or resource to another container or resource.

### To model privilege settings on the settings of an existing resource

1. Right-click select the container or resource that has the privileges you want to apply.
2. Select the Copy Privileges function. A window for selecting the target resource opens.
3. Select the container or resource that is to receive the copied privileges.

**Note:** The target container or resource receives new settings only for privileges common to the source and target. For example, privileges for a table are a subset of privileges for a container, so only table-level privileges are changed.

If you want all the resources contained in the selected target to have the same privileges, check the Copy Privileges into Target Descendants check box.

If you do not copy permissions from the parent folder into the target descendants, you or the administrator must modify the descendants' privileges directly.

## Opening a Resource

### To open a resource

- Double-click the resource name in the resource tree.
- Right-click and select Open from the popup menu.
- Select the resource and from the File menu, choose Open <resource name>.
- Select the resource and type Ctrl-O.

## Getting Information about a Resource

You can get information about a resource like who owns it, who created it, and when it was created as well as any annotations about the resource that might have been added.

The data source tabs display the following information about the resource.

Field	Description
Name	User-provided name and location.
Type	Resource type.



Field	Description
Owner	Name of the owner.
Orig Creation Date	Date the resource was created. If created in a release prior to TDV 6.2, this field contains Not Recorded.
Orig Owner	Name of the owner who created this resource. If created in a release prior to TDV 6.2, this field contains Not Recorded.
Last Modified Date	Date when the resource was last edited.
Last Modified User	Name of the user who last edited the resource.
Lock	Owner of the lock on the resource; or Not Locked.
Annotation	User-editable notes about the procedure.
Maximum Number In Queue	<p>(All triggers except JMS triggers; in the Queue Properties section) Displays and lets you set the number of times a trigger can be queued simultaneously before duplicates are dropped.</p> <p>A value of 1 (default) means that the queue for this trigger can contain only the trigger currently being processed. If the trigger repeats before the previous one finishes its task, it is lost.</p> <p>When the value is set to 2 or greater, additional triggers start execution as soon as the current trigger finishes. Each refresh failure results in an email notification. A larger number of queues for a trigger reduces event loss but might use more memory.</p> <p>(JMS triggers; in the Queue Properties section) TDV sets this field to 0. You cannot change it, because no message queueing is done inside TDV.</p>
Target Definition Set	(XQuery transforms) The path to the definition set containing the schema.
Target Schema	(XQuery transforms) The fully qualified name space for the schema.
Execute only once per transaction for each unique set of input values	(XQuery procedures) If other procedures are called multiple times with the same parameter and values from within a procedure, it is invoked only once and the original results are reused. This ensures that the execution results of a procedure are kept intact for the transaction, as long as the procedure's input parameter values remain the same. For details, see <a href="#">Setting Transaction Options for a Procedure</a> , page 223.


### To get information about a resource

1. Open the resource.
2. Select the Info or Configuration tab at the bottom of the resource editor.

## Annotating a Resource

You can edit any resource that you own or for which you have editing privileges.

Whenever a resource has been edited or changed, Studio indicates this by enabling the Save button on the Studio toolbar, displaying the name on the tab editor in blue italic type with an asterisk, and displaying the editor tab in which the change was made in blue type with an asterisk.



Saving the resource removes the asterisk and displays the tab text in black type.

### To annotate a resource

1. Verify that you have Read Access and Write privilege on the specific resource.
2. Open the resource.
3. Select the Info tab to view and modify annotations.

## Moving, Copying, Deleting, or Renaming a Resource

You can move a resource by cutting a resource and pasting it into another location, or by renaming it, subject to the following rules:

- You cannot move an unpublished resource into Data Services, which only stores resources that have been published. See [About Publishing Resources](#), page 326.
- You cannot move a published resource out of a Data Services container. You must delete it, and then, if you want, republish it.
- The only way to move the children of a data source is to move the entire data source.

- You can move a container (except a system-created container). When you do, all of the resources it contains are moved.
- You can move a leaf, such as a view or a procedure.
- As with any cut and paste sequence, if you cut a resource and do not paste it in its new location before you cut or copy another resource, the original resource is lost.

You can rename any resource in the resource tree. All references to the original filename in the SQL within resources in Studio are also changed to the new name. Resources with dependencies that are currently opened are closed to update and accommodate the changed dependency name.

**Note:** If the configuration option “Require Grant Privilege” is tuned to be True, then a user performing the copy-paste operation should have GRANT privilege on the source, in order to copy all sensitive information from the source. By default this is set to False. To change this setting, follow these steps:

1. Go to Administration > Configuration
2. Locate the Require Grant Privilege option. It can be found in Server > Configuration > Metadata
3. Change the value to True.
4. Click Ok.

### **To move a resource**

1. Right-click the name of the resource and select Cut, or select the resource name and click the Cut toolbar button.
2. Right-click the name of the container in which to place the resource, and select Paste into; or select the container name and select the Paste into button on the toolbar.

### **To copy a resource**

1. Right-click the name of the resource and select Copy; or select the resource name and click the Copy toolbar button.
2. Right-click the name of the destination container and select Paste into; or select the container name and select the Paste into button on the toolbar.

**To delete a resource**

1. Right-click the resource, and select Delete; or select the resource and click the Delete button.

To select multiple resources for deleting, hold down Ctrl while selecting the resources one by one, or hold down Shift while selecting a set of adjacent resources.

2. In the Confirmation window, click Yes.

**To rename a resource**

1. Right-click the resource, and select Rename; or select the resource and then the Edit > Rename option.
2. Place the cursor anywhere on the resource name, type a new name, and press Enter.

## Searching for Resources in the Server

You can search for any resource in the server using the Studio search feature.

The search field includes a timer that starts and waits about 0.3 seconds for you to stop typing. Each time you type a character, the timer restarts. When you stop typing, the server is queried for any resources whose name begins with the text you have typed, and resource references containing the resource name, path, and type are returned.

**To search for a resource in the server**

1. Select the Resource > Find Resource menu option.

If you want to close the search window, click anywhere outside the window, or press the Escape key. Clicking the search window's title bar does not close the window.

2. In the text field, type the name of the resource you want to find.


You can use a period to match a single character, and an asterisk or a percent sign to match any number of characters.

3. Use the up- and down-arrow keys to navigate through the list of resources.
4. Select the resource by clicking its name or by clicking the Enter key.

The resource opens on the right, and on the left the resource tree expands to display the location of the resource.

## Impacted Resources

An impacted resource in TDV is displayed with a red impacted icon in the Studio resource tree, because the resource definition is no longer valid. For example, if a composite view includes tables from a data source that is later deleted, the resource becomes impacted. The resource itself, any resource that depends upon it, and its containers display a red circle with an exclamation point in it.



This section contains:

- [Managing the Display of Impacted Resources, page 49](#)
- [Investigating Impacted Resources, page 50](#)
- [Repairing Impacted Resources, page 51](#)

## Managing the Display of Impacted Resources

The name of an impacted resource always displays the impacted icon next to it. However, you can configure the parent folders of impacted resources to display or not display the impacted icon.

### To manage the display of the impacted resource icon on folders

1. Open Studio.
2. Select Edit > Options.
3. Select the Warnings tab.
4. Select or clear Mark folders impacted when they contain descendants that are impacted.

5. Click OK.

For more information, see [Customizing Studio, page 27](#).

## Investigating Impacted Resources

There are multiple ways you can get the specifics about why a resource is impacted.

### To discover the reason a resource is impacted

1. Discover the reason a resource is impacted in one of these ways:
  - Hover your cursor over the impacted resource name in the Studio resource tree. Studio displays an error message in a popup.
  - From the Resource menu, choose Impacted Resources. Studio opens an Impacted Resources dialog. If you expand the nodes, you can see all currently impacted resources marked with exclamation points in red circles.

The Impacted Resources dialog helps you locate and investigate impacted resources:

- Use the Expand All button to view all impacted containers and resources in the resource list.
- Enter a search string in the Find field then click the Search button to view all resources with the search string in their name. If necessary, click the Expand All button to view the impacted containers and resources that match the search string.
- Select or clear the radio button to display or clear the tree from the view of impacted resources.
- Hover over any resource to get the explanation for why the resource is impacted as shown above.
- Double-click any resource to open its editor.
- Open the resource editor and click the tab for the type of resource:

SQL view—Click the SQL tab.

SQL script—Click the SQL Script tab.

XQuery transformation—Click the XQuery tab.

At the bottom of the panel, TDV displays an error message. You can see the entire error message by hovering your cursor over the error text box.

2. See [Repairing Impacted Resources, page 51](#) to learn about the possible causes of the impact condition.

## Repairing Impacted Resources

You can fix an impacted resource by correcting its definition. For example, if a dependent resource is missing, make it available. If there is a mismatch, make the resources match.

### To repair an impacted resource

1. Locate the impacted resource and display its error message as described in [Investigating Impacted Resources, page 50](#).
2. Review the table below to find the cause of the impaction.

Impact Condition	Cause
Configuration Error	The configuration of the resource is no longer valid, or its validity is uncertain. For example, when you import a data source, it might be impacted if it is unclear that the resources within the data source still exist. A reintrospection can resolve that uncertainty.
Missing Resource	A resource depends on another resource that no longer exists or is unavailable. For example, if a view references a table that was deleted, the view becomes impacted.
Mismatched Resources	A resource depends on another resource that has changed and no longer matches—for example, if the number of input variables changes for a procedure referenced in a view.
Mismatched Implementation vs. Interface	If the interface and implementation do not match, the resource is impacted—for example, if you design an interface using Design Mode in the view editor Columns panel and you add or delete columns.
Security Issue	A resource refers to another resource that you no longer have permission to access—for example, if the permission on a referenced data source is made more restrictive and you no longer have the required level of permission.
Syntax Error	A syntax error is introduced in the resource—for example, if you type an invalid SQL statement and save it.

## Exporting (Archiving) and Importing Resources

You can save selected resources—or an entire TDV Server instance—to a TDV archive (CAR) file so that you can port the resources to another TDV instance or preserve a snapshot of TDV.

Archiving a resource is called *exporting*; deploying it to the same or another location is called *importing*. When you export a resource, a copy of the resource is archived into a CAR file and saved in a specified location, while the original repository configuration for the resource tree remains intact. Archived resources can be redeployed by importing this CAR file. This file is referred to as the export file or import file.

If you want to archive an entire TDV Server instance, it is best to first perform a full server backup. You can retain the resulting CAR file as backup, or use it to restore the TDV Server to a known state. See [Using Studio for a Full Server Backup](#), page 62, for more information.

You can export and import resources using Studio or using TDV command-line utilities. See the *TDV Administration Guide* for information about using `backup_export`, `backup_import`, `pkg_export`, and `pkg_import`. With appropriate access rights, you can export a single resource, a group of resources, or the entire TDV configuration (except for local machine settings).

By default, importing adds CAR file resources to existing resources in identical container paths. Whenever both the resource path and name in the CAR file match the resource path and name on the target server, the CAR file version overwrites the target resource.

- [Access Rights for Export and Import](#), page 52
- [Exporting Resources](#), page 53
- [Export and Import Locked Resources](#), page 55
- [Marking Rebindables](#), page 55
- [Rules for Importing Resources](#), page 56
- [Importing a Resource](#), page 57
- [Rebinding an Imported Resource](#), page 61

### Access Rights for Export and Import

All objects can be exported by an administrator with all rights, or by an operations administrator with Backup (or Backup & Restore) rights who has Access Tools, Read All Config, Read All Resources, Read All Status, and Read All Users rights. Import requires all of the corresponding Modify rights.



- If encrypting resources when performing an export or import, you must communicate and share the encryption key that you used with others that are authorized to access those resources. There is currently no automatic way to securely share encryption keys between different TDV users.

When exporting:

- The user performing the export must have Read privileges on the selected objects and other associated rights.
- If the user performing the export has the Read All Users right, user profile definitions can be included (as in the `pkg_export` option `-includeusers`) in the export archive file. These items are disabled if the user does not have this right.
- A password for the CAR must be specified.

When importing:

- Resources captured in a CAR file can be imported to a TDV instance if the user has Write privileges on the target folders.
- Privileges are included among the items imported from a CAR file if the user performing the import has both the Modify All Resources and the Modify All Users rights.
- The password used to create the CAR file must be specified to import the CAR file. Or, if the CAR was created without a password, you can leave the password value blank.

See [Rules for Importing Resources, page 56](#) for more information.

## Exporting Resources

You can export selected nodes and resources in the Studio resource tree to a CAR file that contains the relevant resource definition metadata. Resources selected are exported with all of their child objects.

Exported CAR files can include caching configurations and the cached data, data source connections, access privileges, custom JAR files, dependencies, cardinality statistics, Discovery files, and the owners of the exported resources (called “required users”).

### To export resources using Studio

1. Select one or more resources in the Studio resource tree.

To select multiple resources for exporting, hold down Ctrl while selecting the resources one by one, or hold down Shift while selecting a set of adjacent resources.

2. Right-click and select Export, or choose File > Export <resource>. Studio displays the Export dialog.
3. For Name, type a name for the CAR file, or use the Browse button to locate a file in which to store the exported resources.
4. In the Include Resource Information section of the Export <resource> dialog box, select and uncheck export options as required.

Each export option is enabled only if the user has the appropriate rights for it.

Export Option	Description
Caching	Resource caching configurations: storage type and location, scheduling information, materialized view data.
Privileges	Resource group and user privilege information. User privilege information for exported resources is imported into the target TDV installation only for matching user, group, and domains on the target, and only if the user performing the import has the Modify All Users right or the Modify All Resources right.
Dependencies	Any dependency resources in the exported CAR file. To view dependencies that have been exported, open the resource and select the dependency panel.
Required Users	Owners of the exported resources.
Data Source Connections	Resource-specific connection profiles and configurations, including host, port, sign-in, and password. This option requires the Read All Resources right.
Custom Jars	JAR files created to support new data sources. JAR drivers in the conf\adapters\system folder are exported, but JAR files in the apps\dml\<DATASOURCE>\lib folder are not exported, regardless of this setting.  Custom JAR settings overwrite system JAR settings, which in turn overwrite DLM JAR settings.
Cardinality Statistics	Includes data source statistics, and configurations such as refresh mode, refresh timeframe, manual cardinality overwrites, and specific column settings.
Discovery Files	Be sure to include Discovery files, such as indexes and relationship files.

Export Option	Description
Parent Resources	Check this option to include the parent resources while exporting the datasource metadata.

Choosing check-box options in this section is equivalent to enabling options using the command line in the `pkg_export` utility. For more information on the `pkg_export` utility, see the *TDV Administration Guide*.

5. Type a password to encrypt the CAR file. Type the same password to confirm it.

A password is required to export resource data.

6. Optionally enter a description of the export file in the Description box.
7. Click OK.

## Export and Import Locked Resources

When you export resources using Studio, the selected resource definitions and containers are exported regardless of whether they are locked or not. However, an export using Studio excludes the locking information in the exported CAR file metadata. If you want to preserve the lock status and ownership, you must export your resources using one of these methods:

- Perform a full server backup. See [Using Studio for a Full Server Backup, page 62](#).
- Use the `backup_export` command-line utility. See the *TDV Administration Guide* for more information.

The export CAR file contains all pertinent lock metadata. If you use the `backup_import` utility to import resources, and the CAR file contains lock metadata (evidenced by the presence of a file named `resourcelocks.xml`), the resources are restored with the locks intact. Importing from Studio menus brings in the resources but not the lock metadata.

## Marking Rebindables

Many resources, such as views, procedures, and Web services, are dependent on one or more underlying resources. Dependent resources are considered 'bound' to the underlying resources. Imported resources often need to be bound again in their new location.

Binding a resource to its dependencies is also often necessary in the import process. For example, a procedure P1 might retrieve data from table T1 in the development data source DS1, and refer to it accordingly in its FROM clause. In this case, P1 is said to depend on T1, and P1 and T1 are said to be bound. When importing P1, the user must ensure that the connection to T1 is fed from either DS1 or another data source—for example, a live production data source rather than a QA or development data source.

For additional information, see [Rebinding a View, page 165](#) and [Rebinding a Procedure, page 222](#).

Exported resources are often bound to underlying sources, and the binding should be reestablished (or changed) when the resources are imported.

When a resource is marked as rebindable in the CAR file, Studio import of this resource displays the path and description in a dialog box that lets the user specify a new path for the dependency resource.

### To mark rebindables with a command-line program

1. Use the command-line `pkg_export` program.
2. Specify the option to mark the underlying source as rebindable:  
`-rebindable <SourcePath/.../ResourceName> <Description>`

Or

1. Use the command-line `pkg_import` program.
2. Specify the following command:  
`-rebind <OldPath> <NewPath>`

## Rules for Importing Resources

Importing follows certain rules to resolve conflicts during import. These rules are:

- If an imported resource does not exist, it is created. The person performing the import is granted privileges as the creator (such as Read | Write for a folder or Read | Write | Execute for a procedure). If the user is in the admin group and has requested include access, the resource reverts to its prior owner, and any privileges in the import are also put in place.
- If a resource is imported to a nonexistent folder, the folder and any parent folder that does not yet exist are created, and the user performing the import is assigned Read | Write privileges on and ownership of these folders.

**Note:** Missing folders are not auto-created in the Data Services folder.

- Importing a pre-existing resource overwrites the older version (assuming the required Write privileges), except that:
  - The owner is not changed.
  - User privileges are not overwritten unless explicitly changed by the import. For example, if Jean has Read | Write permissions and Sue has Read | Write permissions, and the import file lists Jean as having Read permission but not Sue, Jean's privileges are updated to just Read, but Sue's are left intact.
  - If the resource is a folder or data source, its child resources are not removed.

### Restrictions when importing resources

- Configuration settings are not carried over when you export or import a resource using Studio.
- Resource creation in a folder requires Write privilege on the folder path leading to that folder.
- A resource cannot be overwritten without Write privilege on that resource.
- You cannot export just part of a physical data source; you must export all of it or none of it.
- You cannot import just part of a physical data source; you must include the source definition itself.
- The Data Services folder enforces strict structure rules.
- You cannot import anything that was exported from the Data Services folder to a location outside of that folder.
- You cannot import anything that was exported from outside the Data Services folder into that folder.

## Importing a Resource

You import CAR files to replicate TDV resources and resource configurations. CAR files are created by exporting TDV resources, and they usually contain many object resources—possibly even a full server backup. For details on creating a CAR file, see [Exporting Resources, page 53](#) and [Using Studio for a Full Server Backup, page 62](#).

During the import process, you can choose to import or not import caching information, privileges, custom adapter JARS, and data source connections. You can also override locks, overwrite resources, merge folders, and create caching tables.

Resources imported from an archive using Studio are placed in the selected folder in Studio's resource tree. Import performs a path relocation on all folder path roots in the archive. See [Rules for Importing Resources, page 56](#) for details about the rights and privileges related to importing resources.

Prior to performing the import, you can view information about the archive file to make sure it is the one you want. You can also preview the messages generated during the import without actually performing the import.

### To import a resource

1. Right-click the container into which you want to import a resource, and select Import; or select the resource and then the option File > Import Into <container>.

The Import into window opens.

2. Use the Browse button to locate and upload the CAR file, or type the full path to the import file in the File field.
3. Optionally, type a password. If the CAR was created using a password, you must type that password here. If the CAR was created without using a password, you can leave this field blank.
4. Optionally, check the Ignore Encryption Errors check box to ignore any encryption errors.

**Note:** If this option is used, then all backup data will be imported regardless of whether a valid encryption key was provided. This means that the import will not fail. This option can be used to allow partially importing any backed up data. However, the import process will only import data that is not encrypted or can be decrypted using the provided encryption key. All encrypted portions of the backup data that cannot be decrypted will be imported as empty values and the import will otherwise succeed.

This affects all encrypted values in the backup data, which includes, but is not limited to data source and LDAP domain connection passwords.

5. Clear items in the Include Resource Information section that you do not want to import.

**Note:** A resource information box is checked only if that resource is present in the CAR file *and* you have appropriate user rights. For example, the Privileges check box is enabled only for users with the Read All Users right.

Option	Description
Caching	Includes or excludes resource caching configurations, including storage type, location, scheduling information, and materialized view data.
Privileges	Includes or excludes resource group and user privilege information. User privilege information is imported into the target TDV installation only if matching username, group, and domains exist on the target and the user performing the import has the Modify All Users right or the Modify All Resources right.
Override Locks	Clears existing resources from the target and sets the TDV Server to the resource definitions present in the full server backup CAR file. The importing user must have the Unlock Resources right to use Override Locks.
Create Caching Tables	If selected, the cache status, tracking and target tables required by cached resources are created, if not already present in the database for your data source.
Overwrite	<p>Overwrites or stops import of resources that have identical names and folder paths. Owner and user privileges are not overwritten unless they are explicitly changed to new privilege setting.</p> <p>Use this option to guarantee that the new TDV workspace matches the folders and content present in the CAR file.</p> <p>This option clears target folders before copying the CAR file contents to them.</p>
Custom Jars	Includes or excludes any custom JAR created to support a new data source.
Merge Users Folder	Imports all users present in the CAR file who are not already present in the server target. This option takes precedence over the Include Users Folder option. This option's behavior might be altered by the Overwrite option.
Data Source Connections	Includes or excludes resource-specific connection profiles and configurations, including host, port, sign-in, and password. This option requires the Read All Resources right.

Option	Description
Include Users Folder	<p>Includes or excludes resource owners who might be present in the CAR file.</p> <p>Imports all users present in the exported CAR file unless Merge Users Folder is specified. By default, domain, group, and user information are not included in export or import packages. When users are not included, the importing user becomes the owner of the resource.</p>
Include Policies	<p>Includes or excludes policies (CBS, RBS, Cache and Security policies) that might be present in the CAR file.</p> <p>If your CAR file includes these policies, import the CAR from the Studio Desktop directory level. Policies must be saved and used from the /policy Studio directory.</p>
Discovery Files	<p>Check this option to include Discovery files (such as indexes and relationship files) in the import.</p>

Different combinations of Overwrite, Include Users Folder, and Merge Users import options can alter the user definitions, resource ownership, and usage privileges defined on the TDV target after the CAR-file import is complete.

This table shows all possible combinations of these options. Check marks on the left side of the table show the import options used, and check marks on the right side show the results on the TDV target after the import.

Import options used			Users imported into CIS target			
Overwrite	Include Users	Merge Users	From *.car file		CIS target	
			UserA	UserB (car)	UserB (CIS)	UserC
✓					✓	✓
✓	✓		✓	✓		
✓	✓	✓	✓	✓		✓
✓		✓	✓	✓		✓
	✓		✓	✓		✓
	✓	✓	✓		✓	✓
		✓	✓		✓	✓
					✓	✓

Where a checkmark indicates an option used or the users defined on the CIS target after the pkg-import with the given options is performed.

**Note:** If Overwrite and Include Users Folder are both checked, all existing user definitions are removed and replaced with the users present in the import CAR file. The user performing the import must have Read and Modify All Users rights to use this combination.

Choosing check box options in this section is equivalent to enabling options in the pkg\_import command-line utility. See the *TDV Administration Guide* for more information.



6. If you edit the entry in the File field, click Refresh to view the following information about the import file:
  - File Type—archive type (whether partial or the entire server)
  - Date—day, date, and time when the resource was exported
  - User—name of the user who exported the resource
  - Server—host machine and port from which the resource was exported
7. Select the Show Rebinding Options box to bind a resource to an underlying source for the first time. (For details about resource binding, see [Marking Rebindables](#), page 55.)
 

If you check the Show Rebinding Options box the Import Into rebinding window appears. See [Rebinding an Imported Resource](#), page 61.
8. Optionally, click Preview to view a list of the contents of the import file without actually performing any imports.
 

The Preview button works like the `-messagesonly` option to the `pkg_import` command-line utility. This option displays the messages generated in a package import without actually performing the import.
9. Optionally, type search criteria in Find, and click Search. Use the up or down arrow key to jump to the next instance of the search text. The text that you are searching for is highlighted in yellow.
10. Click Import to import the resources.
11. Click Done to complete the importing process.

## Rebinding an Imported Resource

A view depends on one or more underlying sources, and the view is considered bound to those underlying sources. A view can be bound to tabular data or a procedure. Rebinding is useful when:

- You create a view with its sources and later decide to rebind the view to different sources.
- An execution error has occurred for a view because a source with which the view was initially bound does not exist any more.

If you checked Always Show Rebinding Options in the Import window, the window shown below appears, listing the resources that need to be rebound.

### To rebind an imported resource

1. Follow the procedure to import a resource described in [Importing a Resource, page 57](#) through step 5.
2. Select the resource to rebind in the upper part of the window.
3. Use the Browse button or type the Current Path to the resource.
4. Use the Browse button or type the New Path to which to bind the resource.
5. Click Rebind to rebind the resource.

**Note:** If Hide rebound item is checked (default), each item disappears from the top part of the window as it is rebound.

6. When all resources have been rebound, click Next.

The Import Into window appears, the same as when no resources need to be rebound.

7. Click Done to close the Import Into window.

## Using Studio for a Full Server Backup

Studio can perform a full TDV Server backup. This capability is available for those with these administrative rights: Access Tools, Read All Resources, Read All Users, and Read All Config.

This option is equivalent to the backup\_export command-line utility.

### To perform a full server backup

1. Select the Administration > Full Server Backup menu option.

The Full Server Backup window opens. Check boxes in the Include Resource Information area are:

- Checked and dimmed if the information must be included for a full server backup.
- Unchecked and dimmed if the information cannot be included in the backup.
- Checked if the information is included by default but can be excluded.
- Unchecked if the information is omitted by default but can be included.

2. Check or uncheck the undimmed boxes as appropriate to this backup.
3. Use the **Browse** button to specify a file in which to store the exported resource.

The **Save** window appears for specifying and locating an export file. You can:

- Create a new export file by typing a name for it in the **File name** field. The filename extension (.CAR) is automatically added.
- Use an existing CAR file. Locate it using Browse, and click **Save**.

If you use an existing CAR file, its contents are overwritten when you complete the export process.

4. Type a password to encrypt the CAR file. Type the same password to confirm it.

A password is required to export resource data.

5. Optionally, type a description for the export file in the Description field.
6. Click **OK**.

## Working with Resource Locks

In Studio, a resource can be opened, locked, and modified starting with a right-click on the resource name in the Studio resource tree.

You can also lock and unlock all resources in TDV using a single configuration parameter. When Studio resource locking is enabled with this configuration parameter, resources must be unlocked before they can be edited. Studio resource locking is disabled by default. See the *TDV Administration Guide* for more information.

When a resource is locked, other developers working on the same TDV Server instance (or active cluster) can see that a lock has been placed on a resource or a resource tree node.

**Note:** Resource locking is not intended as a security feature. An administrator can protect defined resources by managing rights and privileges.

Administrators with the Modify All Users right, and resource owners, can revoke the Write privilege (modify) for specific resources, thereby preventing anyone from modifying those resource definitions.

Constraints on new resources in locked containers include the following:

- Only the user who locked a resource can modify that resource or save changes to it.
- Only the lock owner can create or destroy resources within a locked container.
- All resources within a locked container inherit the lock from the parent container, which in turn belongs to the original lock owner.

This section includes:

- [Locking and Unlocking a Resource, page 64](#)
- [Identifying Locked Resources, page 64](#)
- [Change History of a Lock, page 65](#)

## Locking and Unlocking a Resource

You can lock a resource in Studio to prevent other users from changing it. The resource owner or an administrator with the Unlock Resources right must unlock a resource before other users are allowed to save changes that resource. Unlocking a tree of resources also unlocks all objects in that tree.

If the user has the Unlock Resources right, all other locked objects for which the user has the Read privilege are shown and selected for unlocking.

### To lock a resource

1. Verify that you are the resource owner.
2. Select one or more resources or containers in the resource tree container, right-click, and select **Lock Resource**.

### To unlock a resource

1. Verify that you are the resource owner or that you have the Unlock Resources right.
2. Save the resource prior to unlocking it.
3. Right-click the locked resource and select **Unlock Resource**.


All resources that can be unlocked by the current user are shown.

## Identifying Locked Resources

You can identify locked resources in the resource tree by noticing the small lock icon next to the resource icon. All Studio instances connected to the same TDV Server or Active Cluster have the same set of locked icons for resources for which they have Read privilege access. In the Lock field on the Info tab, the type of lock (implicit or explicit), who created the lock, and when it was created is displayed. The lock type is explicit if the user set a lock on the specific resource or implicit if the resource inherited the lock from a parent container.

## To get detailed information on a locked resource

1. Hover the cursor over the resource name to see the lock status, for example.



- Lock Owner—User who set the lock
  - Lock Creation Time—Time when the lock was set
2. To learn about the lock type, open the resource and select the Info tab.

## Change History of a Lock

The server events log, `cs_server_events.log`, captures change history for resource locks. It contains the username and domain of the person who locked or unlocked the resource, the time stamp, the data resource, and any annotation entered at the time of unlocking.

You can monitor lock change events using a third-party SNMP utility. SNMP IDs 20805 (`csResourceLock`) and 20806 (`csResourceUnlock`) reveal locked resources and changed resources, with change descriptions entered when the highest-level resource node was unlocked.

For more information on SNMP monitoring, see the *TDV Administration Guide*.



# Working with Data Sources

---

TDV lets you work with a wide variety of industry data sources, including relational databases, file data sources, WSDL data sources, application data sources, and so on, by providing built-in data adapters that help you define and configure the data sources for TDV. This topic describes how to work with data sources in TDV.

- [About Data Sources and TDV, page 67](#)
- [Data Source Categories, page 69](#)
- [Adding a Data Source, page 70](#)
- [Editing or Reviewing Configuration Information for a Data Source, page 73](#)
- [Viewing Data Source Table Details, page 75](#)
- [Adding and Removing Data Source Resources, page 76](#)
- [Testing the Connection to Your Data Source, page 77](#)
- [TDV Configuration Parameters Common to Multiple Data Sources, page 78](#)

## About Data Sources and TDV

TDV integrates your data sources into a single virtual data layer that can be used to model rich information resources. You can add many types of data sources to the TDV platform using Studio, defining connection profiles, specific source capabilities, and detailed source introspection metadata. TDV views and procedures built on the data modeling layer can take advantage of capabilities unique to each data source, allowing you to integrate those disparate parts into a single virtual data layer.

Adding a data source means creating a metadata representation of the underlying native data source in the TDV repository. It does not mean replication of the data or replication of the source. The data source metadata for each data source type includes things like how the data source:

- Defines and stores data, including catalogs, schemas, tables, and columns.
- Accepts and responds to requests for data.
- Handles insert, update, and delete transactions.
- Executes stored procedures.

- Makes data-related comparisons.

A virtual layer of information about data source capabilities allows the TDV Server Query Engine to create efficient query execution plans that leverage data source strengths and inherent advantages of preprocessing data at the source.

The following sections elaborate on the preparation and use of data sources:

- [About TDV Adapters, page 68](#)
- [About Introspection, page 68](#)
- [About Federated Queries, page 68](#)

## About TDV Adapters

TDV Adapters simplify and accelerate high-performance access to a wide range of data sources including popular enterprise applications, relational and multidimensional data sources. TDV adapter features include interactive metadata mapping, integration of and resolution for most vendor-specific SQL, and statistical analysis of source tables to enable quick optimization of query execution plans. TDV adapters provide certified, vendor-specific connectivity that leverages data source APIs. TDV adapters for non-relational data sources let you create views that represent data as relational tables.

TDV adapters capture data source settings that are then recorded in the metadata modeling layer, for use when query execution plans are calculated. Refer to [Adding and Removing Data Source Resources, page 76](#), for more information.

TDV provides some data adapters that have default settings. If data source instances have been changed to handle data and SQL in a special way, you might need to modify the adapter for best performance.

## About Introspection

Introspection is the process of retrieving metadata and data from your data sources. For more information, see [About Introspection and Reintrospection, page 108](#).

## About Federated Queries

Data virtualization makes it possible to execute federated queries, which are queries against multiple data sources. Each of these data sources may be of a different type, or of the same type with different settings. In addition, TDV can execute any of almost 300 functions natively when required, making TDV itself a source of federated query results.



The following table lists where in the documentation you can find further information about such issues.

Federated-Query Topic	Where Discussed
Data source function support (push vs. no-push)	Listed by data source: “Function Support for Data Sources” section of the <i>TDV Reference Guide</i> .  Listed by function: “Function Support Summary” section of the <i>TDV Reference Guide</i> .
Suppressing push of SQL operators	The five DISABLE_PUSH sections of <i>TDV Query Engine Optimizations</i> , page 515.
Pushing custom functions	<a href="#">Pushing a Custom Function to the Native Data Source</a> , page 192.
TDV function support	“TDV Support for SQL Functions” section of the <i>TDV Reference Guide</i> .
Case-sensitivity and trailing spaces in comparisons	See the <i>TDV Administration Guide</i> .  “Case Sensitivity and Trailing Spaces” section, CASE_SENSITIVE and IGNORE_TRAILING_SPACES option sections, and Case sensitivity and Ignore Trailing Spaces configuration parameters in the <i>TDV Reference Guide</i> .
Miscellaneous function support issues, such as data precision, truncation vs. rounding, collation, time zones, and interval calculations	“Function Support Issues when Combining Data Sources” section of the <i>TDV Reference Guide</i> .

## Data Source Categories

TDV supports the following general types of data sources:

Type	Description
Relational Data Sources	See the <i>TDV Installation and Upgrade Guide</i> for supported data sources. Specific connection details, parameters, and settings are slightly different for each adapter.  For more information on using these, see <a href="#">Configuring Relational Data Sources</a> , page 87.

Type	Description
File Data Sources	<p>See the <i>TDV Installation and Upgrade Guide</i> for supported data sources.</p> <p>For more information on using these, see <a href="#">Configuring File Data Sources, page 161</a>.</p>
WSDL and Web Services Data Sources	<p>TDV supports Web Services Definition Language (WSDL), SOAP, and REST. Web services can be “bound” to any message format and protocol, but these bindings are the most popular: SOAP, REST, HTTP, and MIME. TDV supports several profiles for SOAP binding, including the following: SOAP over HTTP, SOAP over WSIF JMS, and SOAP over TIBCO JMS.</p> <p>See <a href="#">Configuring Web-Based Data Sources, page 97</a> for more information.</p>
LDAP Data Sources	<p>You can use LDAP sources as data sources or (in some cases) as authentication servers. The TDV LDAP basic adapter supports the LDAP v3 protocol, and it is used when you want to use an LDAP source as an introspected data source. Most LDAP sources that are LDAP v3 compliant can be used with the TDV LDAP driver to connect and introspect the selected resource nodes for use in the modeling layer. When you want to use an LDAP source as an authentication service, the TDV Web Manager &gt; Domain Management page is used to add and initially configure the LDAP domain. See the <i>TDV Installation and Upgrade Guide</i> for a list of compatible LDAP directory services. Refer to the <i>TDV Administration Guide</i> section on LDAP Domain Administration for more details on how to implement an LDAP domain for TDV user and group authentication.</p> <p>See <a href="#">Adding an LDAP Data Source, page 170</a>.</p>

## Adding a Data Source

This section is an overview of the process for adding a data source. It includes the following topics:

- [Custom Adapters, page 72](#)
- [Auto-Discovering Data Sources, page 73](#)

## To add a data source

1. In the Studio navigation tree, select the directory in which you want the new data source to reside.
2. Right-click and choose New Data Source from the popup menu, or choose the File > New > Data Source option.

Studio opens the New Physical Data Source dialog. This dialog displays currently supported and custom-defined data source adapters in the Select Data Source Adapter pane.

3. Optionally, if one of the built-in adapters do not fit your data source, you can create a new, custom adapter (see [Custom Adapters, page 72](#)).
4. Optionally, if you are unsure of the data sources you want to define or that are available to you on your network, you can auto-discover resources (see [Auto-Discovering Data Sources, page 73](#)).
5. Search for and select the adapter to use to connect to your data source, and click Next.

The configuration window that is displayed depends on which data source adapter you have selected.

6. Provide the data source connection information to configure your data source:
  - a. For Datasource Name, enter a unique user-defined name for the introspected data source. It can be any name that is valid in TDV. This name will be displayed in the resource tree when the data source is added to the TDV Server.
  - b. For Connection Information on the **Basic tab**, supply the required information. Required information will vary depending on the type of data source you are adding.
    - Username and Password—Valid username and password to your data source.
    - Save Password and Pass-through sign-in —These fields work together. Discussion for how they work is in the *TDV User Guide*.
  - c. Click the **Advanced tab**, specify details about the connection.

Some properties refer directly to the configuration of the data source Server and must be provided by an Administrator. Other properties are specific to TDV and how it interacts with the data source.

- Connection Pool Minimum Size, Maximum Size, Idle Timeout(s), and Maximum Connection Lifetime—These control the JDBC connections

made to the data source, specifying timeout in seconds, the minimum and maximum number of simultaneous connections in a connection pool.

- Connection Validation Query—A simple query to test whether the connection is valid or not. You can leave it empty, or use simple queries like “select \* from dual.”
- Organization Id Cache Timeout Seconds—Length of time to cache user security information. After this time the security information is refreshed from the data source. If a user's security information is changed before the cache is refreshed, the changes will not be available to the Suite data source until the cache is refreshed.

For the specific connection information needed to configure each data source see:

- [Configuring Relational Data Sources, page 87](#)
- [Configuring Web-Based Data Sources, page 97](#)
- [Configuring File Data Sources, page 161](#)

For information on configuring any of the Advanced Data Sources, see the additional adapter guides that are provided as online help or in PDF form.

7. Create the data source using one of these buttons:
  - Click Create & Close to create this data source which can be introspected later.
  - Click Create & Introspect to select the data resources and introspect them. See [Retrieving Data Source Metadata, page 107](#) for how to do this.

## Custom Adapters

You can create a new custom adapter with the New Adapter button on the right side of New Physical Data Source dialog. Both system adapters and custom adapters that were created earlier are listed in the Select Data Source Adapter list in the left panel. There are specific reasons why you might want to create a custom adapter. See the *TDV Data Source Toolkit Guide* for more information see [Adding and Removing Data Source Resources, page 76](#).

See the *TDV Data Source Toolkit Guide* to see what capability changes might require use of a custom adapter.

## Auto-Discovering Data Sources

TDV provides an auto-discovery feature that automatically discovers and displays relational data sources that are visible on the local area network. If a large number of relational data sources and servers are on the network, the scan results might take a long time to complete. It is usually more efficient to add data sources manually. See [Adding Relational Data Sources, page 90](#).

### To auto-discover data sources on your network

1. Choose the File > New > Data Source.
2. In the New Physical Data Source dialog, click Auto Discovery.

The dialog for scanning the network for data sources opens.

3. Accept the default name displayed in the Machine Name field or type the name of the computer from which to scan the network, and click Scan Network.

TDV searches for data sources (using data source default port settings) on the network and displays a list of host computers where specific data sources are visible to the machine specified in Machine Name.

4. Select a machine name (or IP address) and click Next.

Each scan allows for a single addition of a relational data source.

5. For further details, see [Adding Relational Data Sources, page 90](#).

## Editing or Reviewing Configuration Information for a Data Source

After a data source has been configured and introspected as a new physical data source, the configuration information can be reviewed by opening the data source in Studio. The tabs display details about the data source connection and other configuration information. The details differ depending on data source type (relational, web-based, file, and so on).

If you make changes, you need to save changes when you close the data source. You also need to reintrospect the data source to apply your changes. For more information, see [Reintrospecting Data Sources, page 124](#).

**To edit or review data source configuration details**

1. Right-click the data source name in the Studio resource tree and select Open.
2. On the Configuration tab, depending on your data source type, you can review and modify the following information:
  - General Options

General Options	Description
Enable Data Source	Check box to enable or disable the data source for use.
Add/Remove Resources	Provides access to the re-introspection dialog.
Test Connection	Provides a way to validate the connection definition for the data source.

## — Caching

Caching Options	Description
Status Table	Tracks which views and procedures currently have cached data stored, when they were last refreshed, and so on.
Tracking Table	Tracks which views and procedures are currently using the data source for caching, and what tables in the data source are in use.

## — Connection information Option

Connection Information	Description
Basic Tab	Displays the basic connection details TDV uses to connect and sign in to the data source.
Advanced Tab	Displays the advanced connection details TDV uses to connect and sign in to the data source.

3. Review or edit the following information on the Info tab:

Field	Description
Name	User-defined name given to the data source during introspection.
Type	Type of the resource, which is Data Source in this case.

Field	Description
Owner	Domain to which the owner of the data source belongs, or the sign-in name of the user who created the data source.
Orig Creation Date	Date the data source was originally created.
Orig Owner	Name of the owner who originally created this data source.
Last Modified Date	Date when the resource was last edited.
Last Modified User	Name of the user who last edited the resource.
Lock	Owner of the lock on the resource, or Not Locked. TDV resources can be locked by a user to prevent concurrent and conflicting changes. See the <a href="#">Annotating a Resource, page 46</a> .
Cluster Health Monitor Table	Displays the table used to monitor the health of an Active Cluster. It contains the heartbeat messages from all nodes. Its purpose is to help caching determine the health of other nodes in the cluster in case of a cluster split. Refer to the <i>Active Cluster Guide</i> for more information.
Refresh Capability Information	Use to refresh the capability information for this data source.
Case Sensitivity	Reports whether the case sensitivity and trailing spaces settings do or do not match between TDV and the data source capability file. A mismatch does not necessarily reduce performance unless it results in a full-table scan performed locally by TDV. See the “Configuring Case and Space Settings” topic in the <i>TDV Administration Guide</i> .
Trailing Spaces	
Annotation	Area at the bottom of the panel that displays notes about the data source. Any user with Write permission can edit the annotation.

4. Save any changes.
5. If changes were made, perform a re-introspection.

## Viewing Data Source Table Details

Data source tables introspected in TDV can be opened to view the table’s metadata attributes.

**To view an introspected data source table**

1. In the Studio resource tree, navigate to a data source table and open it.  
Studio displays the Columns panel for the table that is open in the workspace.
2. The first three columns in the table are provided for every introspected data source table.

Column	Description
Name	Column name. A key icon to the left of the name indicates that this column is a primary key in this table.
Type/Reference	Displays the data type applied to this column by TDV.
Native Type	Displays the native data type of this column in the original data source.

3. See the *Discovery User Guide* for information about the additional columns.

**Adding and Removing Data Source Resources**

You can add or remove data resources at any time. Adding resources requires introspection of the data source to obtain the metadata about the new resources.

When you remove resources from TDV, you are deleting the TDV metadata about the resource and not the actual resource. If you remove a resource that had dependencies, the dependent resource names in the Studio resource tree turn red, alerting you to resource problems.

**To add or remove data source resources**

1. Right-click the data source in the resource tree, and select Add/Remove Resources, or open the data source's Configuration tab and click Add/Remove Resources. See [Editing or Reviewing Configuration Information for a Data Source, page 73](#).

The Enter Password window opens if the password to access the data source was not saved when the data source was originally added to the server. For further details, see the descriptions for the Save Password and Pass-through sign-in fields under [Adding Relational Data Sources, page 90](#).

2. If requested, supply the password that is required to access the data source, and click OK.



3. In the Add/Remove Resources window, do one of the following:
  - To add a resource, select the corresponding check box.
  - To remove a resource, clear the corresponding check box.
  - To change the settings for adding new resources during reintrospection, check the Detect New Resources During Re-Introspection box. For details, see the section [Setting Introspection Filters on a Resource, page 121](#).
4. Click **Next** to review the Introspection Report and if satisfied begin the introspection.
  - This window can be dismissed at any time to continue running in the background. The re-introspection process also runs independently of the Studio session.
  - Those resources that do not have a change in the metadata used by TDV contribute to the Skipped count.
  - Use the Show pull-down filter to quickly show any errors or warnings.
  - The introspection (re-introspection) status report can be exported as a text file.

## Testing the Connection to Your Data Source

After adding a data source, you can test whether the connection details you supplied are working.

### To test the connection

1. Right-click the data source in the resource tree, and select Open.
2. In the editor that opens on the right, select the Configuration tab, and click Test Connection.

The Connection OK message appears if you have a successful connection.

If the connection fails, examine the error message and review the following common remedies.

Common Problem	Suggested Remedy
Connection failure.	Verify that the TDV host has access to the Internet through HTTP (port 443, 80). If a Web browser can be used to reach the data source but TDV cannot, check the Web browser's configuration for Web proxy settings and enter them into the Advanced Properties of the data source.
Connection OK.	The connection was successful.
Password expired.	Login to the data source through its Web site and reset your password. If your organization's password policy forces users to change their passwords every certain number of days, you should enable the Password Never Expires option on your profile.
The SAP account is not authorized for API access.	Contact SAP or your organization's SAP administrator for assistance in enabling your organization's account for API access.
The Siebel account is not authorized for API access.	Contact Siebel or your organization's Siebel administrator to have your organization's account enabled for API access.
Username and password are invalid or locked out.	Verify that you have provided the correct user name and password by logging into the data source's Web site itself. Contact your organization's Administrator for assistance.

## TDV Configuration Parameters Common to Multiple Data Sources

Following are the configuration parameters that are common to multiple data sources. To access these parameters from Studio, choose Administration -> Configuration -> Data Sources -> Common to Multiple Source Types.

- [Data Source Connection Pool Checkout Timeout, page 79](#)
- [Buffer Flush Threshold, page 79](#)
- [Column Delimiter, page 80](#)
- [Enable String Data Normalization, page 80](#)
- [Escape Character, page 80](#)
- [Row Delimiter, page 81](#)

- [Default Commit Row Limit, page 81](#)
- [Default Execution Timeout, page 81](#)
- [Delayed Connection Commit/Rollback Timeout, page 82](#)
- [Delayed Statement Close Timeout, page 82](#)
- [Enable Data Source Connection Pool Checkout Timeout, page 83](#)
- [Introspectable Resource Id Cache Expiration Period, page 83](#)
- [Introspectable Resource Id Cache Cache Purge Frequency, page 83](#)
- [Introspection Full Report Size Threshold, page 84](#)
- [Default OAuth Page Execution Timeout, page 84](#)
- [Push Oracle/Vertica query hints, page 85](#)
- [Suppress Data Source Properties Validation Errors, page 85](#)
- [Trace level, page 85](#)

## Data Source Connection Pool Checkout Timeout

This timeout controls how long the server should wait to checkout a connection from a data source connection pool. If the timeout is 0, the server will wait until it obtains a connection from the pool.

### Data Type

Number

### Default

30

### Remarks

This value is locally defined. It will not be altered when restoring a backup and will not be replicated in a cluster.

## Buffer Flush Threshold

Certain types of data ship SQL executions might buffer very large tables before delivery to the data ship target. This configuration parameter can be used to limit the size of the buffer.

**Data Type**

Number

**Default**

10000

**Remarks**

The buffer is flushed when this limit is reached.

**Column Delimiter**

The column delimiter character to be used while exporting/importing the contents to/from a flat file.

**Data Type**

Text

**Default**

“|”

**Enable String Data Normalization**

If true, String data is normalized to NFC form if needed

**Data Type**

Boolean

**Default**

True

**Escape Character**

The escape character to be used while exporting/importing the contents to/from a flat file.

**Data Type**

Text

**Default**

“\”

**Row Delimiter**

The row delimiter character to be used while exporting/importing the contents to/from a flat file.

**Data Type**

Text

**Default**

“\n”

**Default Commit Row Limit**

When a cache to database table is processing, this value specifies a row count for a commit to occur while inserting cache data. The transaction will be committed every time after the number of rows that the cache data is inserted has reached this limit.

**Data Type**

Number

**Default**

2000

**Default Execution Timeout**

Sets the number of seconds the data source will wait for an execution to occur. If the limit has exceeded, a timeout will occur.

**Data Type**

Number

**Default**

0

**Remarks**

If this value is zero, it means that there is no limit. If it is greater than 0, the execution will wait at most the given number of seconds.

**Delayed Connection Commit/Rollback Timeout**

When the Server is asked to rollback or commit a JDBC connection on a data source, it will wait until all the result sets are closed. This timeout controls how long the server will wait. After the timeout, if there are still open result sets, the connection is forcibly closed.

**Data Type**

Number

**Default**

300

**Remarks**

If the timeout value is 0, the server will not timeout.

**Delayed Statement Close Timeout**

This timeout controls how long the TDV query engine should wait until it forcibly closing lingering data source connections

**Data Type**

Number

**Default**

60

**Remarks**

If the timeout is 0, the engine will never forcibly call close.

**Enable Data Source Connection Pool Checkout Timeout**

This timeout controls how long the server should wait to checkout a connection from a data source connection pool.

If true, global data source connection pool checkout timeout is used by the server.

**Data Type**

Boolean

**Default**

False

**Remarks**

This value is locally defined. It will not be altered when restoring a backup and will not be replicated in a cluster.

**Introspectable Resource Id Cache Expiration Period**

This is the retention period after which the introspectable resource id cache (on a per-user, per-data source basis) will be deleted.

**Data Type**

Number

**Default**

7

**Introspectable Resource Id Cache Cache Purge Frequency**

The frequency that the introspectable resource id cache will be purged of expired entries.

**Data Type**

Number

**Default**

1

**Introspection Full Report Size Threshold**

The maximum size a full introspection report can be before filtering out messages that are not warnings or errors. If the full report size is less than or equal to this value, then nothing will be filtered. Otherwise, the report will only contain a list of the resources affected by the introspection and any warnings or errors that were generated.

**Data Type**

Number

**Default**

10000

**Remarks**

Note that the resulting report can still end up being larger than the specified threshold even with message filtering if there are a large number of resources involved in the introspection.

**Default OAuth Page Execution Timeout**

Sets the number of seconds the data source will wait for a web page execution to occur. If the limit has exceeded, a timeout will occur. If this value is zero, it means there is no wait time. If it is greater than 0, the execution will wait at most the given number of seconds.

**Data Type**

Number

**Default**

5



## Push Oracle/Vertica query hints

This setting controls whether to push Oracle style query hints to Oracle/Vertica data sources. Query hints occur immediately after the SELECT keyword, and must begin with `--+` or `/*+`. Regular comments will be dropped.

### Data Type

Boolean

### Default

False

### Remarks

TDV will not validate the query hints, and Oracle/Vertica ignores invalid query hints. TDV does not guarantee that the query hint will be pushed, as plan optimizations may cause the hint to be dropped.

## Suppress Data Source Properties Validation Errors

If false, validation errors will cause the operation to fail. If true, any validation errors will be written to the log and the operation will go through.

### Data Type

Boolean

### Default

False

## Trace level

This option controls the Log Functionality.

### Data Type

Number

### Default

0

### Remarks

The valid values are:

- 0 - No Log
- 1 - Connection
- 2 - Requests
- 3 - Data

# Configuring Relational Data Sources

---

This topic describes the configuration options that apply generally to relational data sources for connection with TDV. Follow the steps in [Adding Relational Data Sources, page 90](#) for every relational data source.

Data type and function support are described in the *TDV Reference Guide*.

For details on versions supported for each type of data source, see the *TDV Installation and Upgrade Guide*.

The following topics are covered:

- [About Pass-Through Login, page 87](#)
- [About Data Source Native Load Performance Options, page 89](#)
- [Adding Relational Data Sources, page 90](#)
- [Enabling Bulk Loading for SELECT and INSERT Statements, page 92](#)

## About Pass-Through Login

Simple implementations of pass-through do not support multiple pass-through passwords for a single user. Each user session may use only one user sign-in and password to create new connections that have data sources enabled with pass-through login. If pass-through login is enabled on multiple data sources, connection authorization must be based on a single user login-password pair for each user, or the connection to the data source fails for federated queries.

TDV Server and JDBC clients can support pass-through login for multiple data sources, but the data source credentials passed from the end-user JDBC client must be set explicitly for those data sources. See [“Setting Pass-Through Credentials for JDBC Clients”](#) in the *TDV Client Interfaces Guide*. The JDBC `setDataSourceCredentials` method is used to register the data source pass-through credentials for each data source to be so used.

Each client making a request for data from pass-through-enabled data sources has to establish a connection, which requires significant processing time.

In pass-through mode:

- If you save the password, you can introspect without resupplying the password.

- You can perform the following operations even if you did not save the password:
  - Query, update, insert and delete operations (but you need to resupply the original login credentials for the current session).
  - Reintrospect, add, or remove data source resources. You are prompted to resupply the password that was used when the data source was originally introspected.
- You cannot perform the following operations if you do not save the password:
  - Schedule reintrospection
  - Gather statistics using the query optimizer
  - Perform scheduled automated cache updates

**Note:** Pass-through authentication is not allowed for TDV-built system-level accounts.

When using scheduled cache refreshes, you must specify a login-password pair in the data source, and the pair must be the same for the resource owner (or creator) who is accessing TDV and the target data source. If this is not the case, the cache refresh fails.

If a view uses a data source that was added to TDV Server using pass-through mode, and the password has not been saved, row-based security may affect the cache refresh. For example, a cached view named `CachedCommonView` uses the SQL statement `SELECT * FROM db2.T1`; user John is allowed to view only 10 rows; user Jane is allowed to scan 20 rows. Whenever Jane refreshes the view cache, both Jane and John are able to view 20 rows, but whenever John refreshes the view, Jane can view only 10 rows.

The operations you can and cannot perform in pass-through mode depend on if Save Password is checked as follows:

Save password?	Operations you can perform	Operations you cannot perform
Yes	Introspection. You do not have to re-supply the password.	N/A

Save password?	Operations you can perform	Operations you cannot perform
No	<ul style="list-style-type: none"> <li>Query/update/insert/delete operations. You need to resupply the original login credentials for the current session.</li> <li>Reintrospection, Add/Remove data source resources. You will be prompted to resupply the password that was used when the data source was originally introspected.</li> </ul>	<ul style="list-style-type: none"> <li>Schedule reintrospection.</li> <li>Statistics gathering, using the query optimizer.</li> </ul>

## About Data Source Native Load Performance Options

Most data sources have proprietary ways to optimize performance, and they are typically enabled by default. If TDV detects that your operation (for example, a direct SELECT or INSERT) can be made faster using a native loading option, TDV attempts to use it.

Depending on the data source type and the TDV feature you are using, native load performance options vary as follows.

Data Source Type	INSERT and SELECT	Caching and Data Ship Performance Options
DB2	Native load with INSERT and SELECT is supported.	<ul style="list-style-type: none"> <li>Native load with INSERT and SELECT</li> <li>Native and bulk load with LOAD utility</li> </ul>
Microsoft SQL Server		<ul style="list-style-type: none"> <li>Bulk loading using BCP</li> </ul>
Netezza	Native load with INSERT and SELECT is supported.	<ul style="list-style-type: none"> <li>Native load with INSERT and SELECT</li> <li>External tables</li> </ul>
Oracle		<ul style="list-style-type: none"> <li>(Version 9 and 10) Native load with INSERT and SELECT. (Native load with DB link is not supported.)</li> <li>(Version 11) Database links</li> </ul>
PostgreSQL (Greenplum)		<ul style="list-style-type: none"> <li>COPY</li> </ul>

Data Source Type	INSERT and SELECT	Caching and Data Ship Performance Options
Sybase IQ		<ul style="list-style-type: none"> <li>• Location</li> <li>• iAnywhere JDBC driver</li> </ul>
Teradata	Native load with INSERT and SELECT INTO is supported.	<ul style="list-style-type: none"> <li>• Native load with INSERT and SELECT</li> <li>• FastLoad/FastExport</li> </ul>
Vertica		<ul style="list-style-type: none"> <li>• Bulk load utility</li> <li>• Export to another Vertica database</li> <li>• Native load with INSERT and SELECT</li> </ul>

## Adding Relational Data Sources

The process of adding relational data sources for use with TDV is fundamentally the same for all types.

In the New Physical Data Source dialog, you need to provide the connection details that are used each time TDV accesses the data source. You can edit this information later if necessary when you open this data source in Studio. TDV automatically populates some fields for each data source type.

Refer to the corresponding Adapter guides for a description of the fields on the two data source configuration tabs.

### To add a relation data source

1. Make sure that any required drivers are installed and configured for use with Studio. For details on obtaining the adapter and for proper placement of the JDBC JAR files, see the corresponding *TDV Adapter Guide*.
2. For Netezza, go to Administration > Configuration and set the “Check if nested aggregates is supported by datasource” configuration parameter to True if that is the case.
3. For Hive 1.1.0, create a view of the table and use Show Contents from the view.
4. Right-click at an appropriate location in the resource tree, and select New Data Source.

Studio displays the first frame of the New Physical Data Source dialog, which lists the available data source adapters, including custom adapters that may have been configured and added to TDV.

5. Search for and select the data source adapter type, and click Next.
  - For Cloudera CDH4, select Hive 1.1.0 (HiveServer2) as the data source adapter.
  - For DB2 v9.5, select one of the DB2 v9 adapters.
  - For Microsoft Access data sources on non-windows platforms, select the Non ODBC Microsoft Access adapter.
  - For Oracle 11g using the type 2 native client (OCI), select Oracle 11g (OCI Driver) as the data source adapter.
  - For Oracle 11g using the Type 4 Java-only client (thin driver), select Oracle 11g (Thin Driver) as the data source adapter.
  - Select the Sybase option that matches your version of the data source adapter.

If You Are Using Sybase Version	Use Sybase Option	Driver Required
Sybase v12.x	Sybase 12	jConnect for JDBC 16
Sybase v15.x	Sybase 15	jConnect for JDBC 16
Sybase IQ v15 using JDBC Type 4 driver	Sybase IQ	jConnect for JDBC 16
Sybase IQ v15 using JDBC Type 2 driver	Sybase IQ (Type 2)	SQL Anywhere Database Client v12.0.1

**Note:** If none of the data source types are appropriate, see [Custom Adapters, page 72](#) for more information.

6. Enter the name for the data source as you want it to appear in Studio resource tree.
7. Enter the basic connection information for the data source. See the *Adapter Guide* for the specific datasource, for a description of the basic settings.
8. To enable Kerberos security through keytab files, select the Kerberos option on the Basic tab. You can then type values for the Keytab File and the Service Principal Name fields.
9. Enter the connection values and related fields. See the *Adapter Guide* for the specific datasource, for an overall description of the advanced settings.

**Note:** Many of these fields control connection pools. Connection pool configuration uses the standard settings that you can find on the internet.

10. Scroll down to make sure that you have specified all necessary information.

For additional fields and options, see the section about the specific data source you are adding.

11. Click one of these options:

- Create & Introspect—Introspect the data source immediately. See [Introspecting a Data Source, page 110](#).
- Create & Close—Save the data source definition but do not introspect now.

## Enabling Bulk Loading for SELECT and INSERT Statements

Optionally, enable bulk loading for SELECT and INSERT statements. Netezza, Teradata, and SQL Server require extra steps to use this feature. Other data sources might support this feature, but they require no extra configuration.

### To enable bulk loading for SELECT and INSERT statements

1. Open Studio.
2. Select Administration > Configuration.
3. Locate the Enable Bulk Data Loading configuration parameter.
4. Set the value to True.
5. Click Apply.
6. Click OK.

### To complete configuration of Teradata bulk loading for SELECT and INSERT statements

1. Right-click the data source name in the Studio resource tree and select Open.
2. Select the Advanced tab.
3. Set values on the Advanced tab for Enable FastLoad/FastExport for large tables, FastExport Session Count, and FastLoad Session Count.
4. Save your settings.



# Configuring Advanced Adapters

---

This topic describes the configuration of optional TDV adapters. These topics are covered in this topic:

- [Adapter Data Type Limitation, page 93](#)
- [Dynamics CRM Adapter ID Ordering, page 93](#)
- [Upgrading the ADO.NET Driver for Sharepoint Adapters, page 94](#)
- [Configuring OAuth 2.0 for TDV Advanced Adapters, page 94](#)
- [Installing the Siebel Data Bean JARs, page 99](#)
- [Registering with the SAP System Landscape Directory, page 99](#)
- [Installing the SAP Java Connector Library, page 100](#)
- [Verifying a Successful Activation of an Adapter, page 104](#)
- [Increasing the Maximum Size of Excel Sheets for SharePoint, page 105](#)

## Adapter Data Type Limitation

There are several data source types that have two or more adapters that can be used to interpret the data coming into TDV. If you have designed some views based on objects imported with one adapter and you switch adapter types, say Salesfore for Salesforce SSO, your introspected data might be assigned to different data types. For example, data that was previously introspected as DOUBLE might now be assigned to the DECIMAL data type.

## Dynamics CRM Adapter ID Ordering

Id's in Dynamics CRM have special ordering and when you do ORDER BY ASC or DESC based on the ID, the data might not order the way you expect until you get used to the way Dynamics CRM organizes itself.

## Upgrading the ADO.NET Driver for Sharepoint Adapters

### To upgrade the ADO.NET driver for Sharepoint Adapters

1. Read any README files included with or associated with the download file.
2. Locate and extract the drivers zip file.
3. Make sure there is no application using or the holding ADO.NET driver.
4. Uninstall the old ADO.NET driver.
5. Install the new ADO.NET driver.
6. Update connection settings in the client and development tools.
7. Refer to the TDV Client Interfaces Guide for details on complete configuration of the ADO.NET driver.
8. Restart any application that's using the ADO.NET driver.]

## Configuring OAuth 2.0 for TDV Advanced Adapters

If your Advanced Data Source Adapters will make use of OAuth authentication, then there is extra configuration that you must perform. The OAuth 2.0 authorization framework enables a third-party application to obtain limited access to an HTTP service for:

- A resource owner by authorizing the resource owner and the HTTP service
- A third-party application to manage authorization separately

This section includes:

- [OAuth Options Provided by TDV Advanced Adapters, page 95](#)
- [Preparing Eloqua for OAuth Access through TDV, page 95](#)
- [Configuring GETANDREFRESH OAuth access for Advanced Data Source Adapters, page 96](#)
- [Replicating your OAuth Configuration on Other Machines, page 98](#)

## OAuth Options Provided by TDV Advanced Adapters

TDV provides the following OAuth options:

Initiate OAuth field options	Description
GETANDREFRESH	<p>Typically, this option can be established quickly by most users.</p> <p>The Get and Refresh option uses the client id and client secret to initiate the OAuth as described in the OAuth 2 RFC and requires interaction between client, resource owner, and the Authorization and Resource Servers. A browser must be launched on the local machine to enable the granting of permissions. The OAuth settings file must point to a location on the TDV Server machine.</p> <p>Required field: Client Id, Client Secret, OAuth Settings file Location</p>
OFF	<p>This configuration uses an OAuth Access Token to authorize to the back end; it doesn't initiate any OAuth flow. The OAuth access token needs to be provided as part of configuration. This method is recommended if the access token is already obtained using other means. Most OAuth providers have a way to generate access tokens, with the help of developer consoles or APIs. Access tokens do expire and it is your responsibility to provide a new access token, when the previous one expires. This makes it suitable for one time use or when the access tokens have long life.</p> <p>Required Field: OAuth Access Token</p>
REFRESH	<p>This option refreshes the access token using a refresh token, client id, and client secret, when the current access token is expired and the refresh is transparent to the user. It stores the new access token in the OAuth settings file. Typically, users do not need to enter anything. This option is best where the Studio and the TDV Server cannot be run on the same machine. It does require that a refresh token be obtained out side of TDV using OAuth provider tools.</p> <p>Required fields: OAuth Refresh Token, Client Id, Client Secret, OAuth Settings file Location</p>

### Preparing Eloqua for OAuth Access through TDV

The Eloqua data source adapter does not permit the use of the loopback address "localhost" or "127.0.0.1" in the callback URL. To use Eloqua with TDV and OAuth, you must configure your system resolver to resolve the new hostname you choose for this purpose to the loopback address 127.0.0.1, and use that new hostname in the callback URL. You must also identify an unused port.

### To prepare Eloqua for OAuth access

1. On your TDV Server host, add a new hosts file entry that maps the loopback address 127.0.0.1 to a fully qualified hostname not actually used on your network, such as "eloqualoopback.mycisserver.com."

For example, on Windows add the following entry to your  
c:\windows\system32\drivers\etc\hosts file:

```
127.0.0.1 eloqualoopback.mycisserver.com # the fully qualified  
hostname for the Eloqua Callback URL
```

2. Choose an available port on the host running TDV for use in the Callback URL. For example: 12481.
3. Log into Eloqua and configure your app's AppCloud Developer Settings to reference that hostname and port in the Callback URL. For example:

```
https://eloqualoopback.mycisserver.com:12481/
```

The https protocol is required.

### Configuring GETANDREFRESH OAuth access for Advanced Data Source Adapters

The GETANDREFRESH option is the most typical configuration method for configuring OAuth access for your TDV Advanced Data Source adapters.

### To configure GETANDREFRESH OAuth access for Advanced Data Source Adapters

1. Start the TDV from the UNIX or Windows command line.
2. Start Studio on the machine where you are running the TDV Server.
3. Add a new data source for one of your Advanced Data Source Adapters.
4. Provide a unique name for your data source.
5. On the Basic tab, type your company name (or account identifier).

6. On the Advanced tab, enter values for the following fields:

Field	Description of Value
Initiate OAuth	Typically, set this to GETANDREFRESH.  Or a refresh token can be obtained from the OAuth provider and provided along with the client id and client secret. Getting a Refresh token requires experience in using the developer APIs and console of the OAuth provider. Also, the token has to be obtained using the same client id and client secret that is configured in the data source.
OAuth Client Id App ID	Set this to the client Id (app Id) of your data source.
OAuth Client Secret App Secret	Set this to the client secret of your data source.
Other	Set this to the value of your data sources callback URL.  For Eloqua, obtaining the callback URL requires some extra steps. <a href="https://eloqualoopback.mycisserver.com:12481/">https://eloqualoopback.mycisserver.com:12481/</a>

After the initial authentication is run and the tokens have been obtained, they are written into the configured OAuth settings file.

7. Save your new data source.
8. From the Studio resource tree, open the data source that you just added, and select Test Connection. Or introspect the data source.

The adapter opens the OAuth endpoint in your system default browser.

9. Using the browser, log in and grant TDV permission to the adapter application.

For example, Eloqua calls your specified callback URL, appending the access token and other needed values, such as:

```
https://eloqualoopback.mycisserver.com:12481/callback#access_token=2YotnFZFEjr1zCsicMWpAA&token_type=bearer&expires_in=86400&state=xyz
```

10. If or when the authentication certificates expire, you must perform this procedure again to allow TDV permission to the data in the data source.

## Replicating your OAuth Configuration on Other Machines

After initial testing and development work with your Advanced Data Source Adapters within TDV and Studio, it is typical that authorization settings will need to be migrated or replicated on other machines within your TDV environment. You can do this using CAR files and by migrating the OAuth settings file.

Occasionally, your usage focus might also require the replication of the authorization settings. Some of these usage focuses include:

Usage Focus	Description
Importing/Exporting Archives and Deployment Manager	When the archive contains a data source configured for OAuth and when it is imported or migrated to the target server, the OAuth settings file is not automatically imported or migrated. OAuth settings file needs to be externally migrated or the OAuth flow has to be reinitiated in the target server.
Clustered Environment	In a cluster, data source configuration is synced across the members of the cluster. For OAuth providers, who allow multiple valid tokens, configure OAuth settings location to be same path. If that is not possible, provide a path on the shared file system, which is accessible to all the members. Shared file system path is needed in case, where the OAuth provider does not support multiple valid tokens.

### To replicate your OAuth configuration on Other Machines

1. From the Studio resource tree open the data source for which you want to replicate OAuth configuration.
2. On the Advanced tab, locate and save the value of the following field:

OAuth Settings Location

The value of this field is the location where the adapter writes the authentication information.

If working in a clustered environment, make sure this location is central to all the nodes of the cluster, or replicate the OAuth settings file to each cluster

3. Create a CAR file export of the data source for which you want to replicate OAuth configuration.
4. Copy the OAuth settings file and the CAR file to the new host machine.
5. Copy the settings file to the same directory location as was specified in the OAuth Settings Location for the data source that you are replicating.

Doing this allows a data source imported from the source to be used in target without modifications.

6. Use Studio on the new host machine to import the CAR file of the data source you are migrating.
7. Test the connection of the data source. If necessary resolve any issues.

## Installing the Siebel Data Bean JARs

For the Siebel adapter, you must install the Siebel Data Bean JARs to enable connectivity to Siebel. Because these JARs are present on the Siebel Server itself, you might need assistance from your Siebel System Administrator. Follow the process below.

### To install Siebel Data Bean JARs

1. Create a directory for the Siebel Data Bean JARs in the following location; <version> is the Siebel version:  
 <TDV\_install\_dir>/apps/dlm/app\_ds\_siebel/lib/<version>
2. Copy Siebel.jar and SiebelJI\_enu.jar from directory below to the directory created in the previous step. <Siebel> is the root directory of your Siebel Server.  
 <Siebel>/eaiconn/CLASSES

## Registering with the SAP System Landscape Directory

After installing the TIBCO software, you must register the installation with the SAP System Landscape Directory if you are using this feature. The procedures for both Windows and UNIX are shown below.

### Registration Procedure for Windows

#### To register the installation with the SAP System Landscape Directory on Windows

1. Run the script sap\_sld\_register\_util.bat under <TDV\_install\_dir>/bin with command-line arguments <SLDHost> <Port> <Username> <Password>.
2. If connecting through a proxy, modify the script line set JAVA\_OPTS= to:  
 set JAVA\_OPTS=-Dhttp.proxyHost=<server> -Dhttp.proxyPort=<port>

## Registration Procedure for UNIX

### To register the installation with the SAP System Landscape Directory on UNIX

1. Run the script `sap_sld_register_util.sh` under `<TDV_install_dir>/bin` with command-line arguments `<SLDHost> <Port> <Username> <Password>`.
2. If connecting through proxy, modify the script line `JAVA_OPTS=` to:  
`JAVA_OPTS=-Dhttp.proxyHost=<server> -Dhttp.proxyPort=<port>`

## Installing the SAP Java Connector Library

You must install the SAP Java Connector Library (SAP JCo), version 3.0.9, on the same computer as TDV. SAP JCo is available through the SAP Service Marketplace at [www.service.sap.com](http://www.service.sap.com). You need to be a registered customer to download from there. After you sign in, navigate to SAP Java Connector > Tools & Services and download the JCo distribution for the platform running TDV, then refer to the next section to validate the installation.

**Note:** In SAP JCo version 2.1.5, passwords are no longer automatically converted to uppercase when they are sent to SAP; instead, case is preserved, which could lead to log on failure. The easiest way to address this is to change the data source to use an uppercase version of passwords. See SAP Notes 817880 and 792850 for more information.

It is best not to install the SAP Adapter on the same machine as the SAP GUI, to avoid a possible conflict between JCo versions.

- [SAP JCo and Large Volumes of Data, page 100](#)
- [Installing SAP JCo on Windows, page 101](#)
- [Testing the SAP JCo Installation on Windows, page 101](#)
- [Installing SAP JCo on UNIX, page 102](#)
- [Testing the SAP JCo Installation on UNIX, page 103](#)

### SAP JCo and Large Volumes of Data

JCo has known memory limitations when processing queries. Severe cases can affect the main TDV Java process. In such cases, we recommend that large queries be divided into small queries.



## Installing SAP JCo on Windows

You need to obtain the SAP Java Connector for your machine from SAP. TIBCO has tested version 3.0.9 of the SAP Java Connector.

### To install SAP JCo on Windows

1. Unzip the SAP JCo zip file into a temporary directory.
2. Execute the command to create jre folder under <TDV\_install\_dir>/jdk:
  - `./bin/jlink.exe --module-path jmods --add-modules java.desktop --output ../jre`
  - create a folder named as ext under <TDV\_install\_dir>\jre\lib
3. Copy sapjco3.jar to <TDV\_install\_dir>\jre\lib\ext.
4. Copy sapjco3.dll to one of these directories:
  - For Windows 32: <TDV\_install\_dir>\apps\common\lib
  - For Windows 64: <TDV\_install\_dir>\apps\common\lib\win64
5. Add a system PATH variable to point to the directory where you put your library files in the previous step.
6. Verify that the Windows system directory includes the files MSVCR71.DLL and MSVCP71.DLL.

These DLLs are the Shared C Runtime (CRT) Components required by SAP JCo but are not shipped with it. If these DLLs are missing, install the Microsoft .NET Framework SDK Version 1.1. Microsoft .NET Framework SDK is available from the Microsoft Developer Network (MSDN) download site.

### Testing the SAP JCo Installation on Windows

Be sure to test that the SAP JCo installation works correctly before using TDV.

## To test the installation of SAP JCo on Windows

1. Run the `sapjco3.jar` Java executable using one of these commands:

Platform	Command
32-bit	<code>&lt;TDV_install_dir&gt;\jdk\bin\java -Djava.library.path="&lt;TDV_install_dir&gt;\apps\common\lib" -jar "&lt;TDV_install_dir&gt;\jre\lib\ext\sapjco3.jar"</code>
64-bit	<code>&lt;TDV_install_dir&gt;/jdk/bin/java -Djava.library.path="&lt;TDV_install_dir&gt;\apps\common\lib\win64" -jar "&lt;TDV_install_dir&gt;\jre\lib\ext\sapjco3.jar"</code>

2. Verify that running `sapjco3.jar` results in a screen that looks like this.



If an error message appears instead, SAP JCo needs to be re-installed.

## Installing SAP JCo on UNIX

Follow the instructions to install SAP JCo based on the type of UNIX system you have. You need to obtain the SAP Java Connector for your machine from SAP. TIBCO has tested versions of the SAP Java Connectors up to 3.0.9.

### To install SAP JCo (Linux and AIX):

1. Unzip the SAP JCo tgz file for your machine into a temporary directory.
2. Execute the command to create jre folder under <TDV\_install\_dir>/jdk:
  - `./bin/jlink --module-path jmods --add-modules java.desktop --output ../jre`
  - create a folder named as ext under <TDV\_install\_dir>\jre\lib
3. Copy sapjco3.jar to <TDV\_install\_dir>/jre/lib/ext directory, where <TDV\_install\_dir> is the root directory of your TDV Server.
4. Copy libsapjco3.so into one of these directories:
  - Linux 32: <TDV\_install\_dir>/jre/lib/i386
  - Linux 64: <TDV\_install\_dir>/jre/lib/amd64
  - AIX 64: <TDV\_install\_dir>/jre/lib/ppc64

**Note:** Create the subfolders if they do not exist. In the Linux 64 platform for example, create the folder amd64 under <TDV\_install\_dir>/jre/lib if it does not exist.

5. (For Linux) Add a system LD\_LIBRARY\_PATH variable to point to the directory where you put your library files in the previous step.
6. (For AIX) Add a system LIBPATH variable to point to the directory where you put your library files in the previous step.

### Testing the SAP JCo Installation on UNIX

It is critical to verify that SAP JCo is working before you attempt to connect to SAP using TDV.

#### To test the UNIX installation

1. From the command line, run the following command:
 

```
<TDV_INSTALL_DIR>/jdk/bin/java -Djava.library.path= <LIBRARY_PATH>
-jar <TDV_INSTALL_DIR>/jre/lib/ext/sapjco3.jar
```

Where LIBRARY\_PATH is the path for your system:

- Linux: \$LD\_LIBRARY\_PATH
  - AIX: \$SHLIB\_PATH
2. Verify that your output resembles the text below. If this command runs without error and the JCo API, middleware, and libraries have version information listed, then SAP JCo is properly installed.

```

-----
-----
|                                     SAP Java Connector
|
|      Copyright (c) 2000-2012 SAP AG. All rights reserved.
|
|                                     Version Information
|
-----
-----
Java Runtime:
  Operating System:      AIX 5.3 for ppc64
  Java VM:               1.6.0 IBM Corporation
  Default charset:      ISO-8859-1
Versions:
  JCo API:               3.0.9 (2012-07-19)
  JCo middleware:        JavaRfc 2.2.8
  JCo library:           720.310
Library Paths:
  Path to JCo archive:   /opt/TDV/jre/lib/ext/sapjco3.jar
  Path to JCo library:   System-defined path to libsapjco3.a
-----
-----
|                                     Manifest
|
-----
-----
Manifest-Version: 1.0
Ant-Version: Apache Ant 1.6.4
Created-By: 1.5.0_14-b03 (Sun Microsystems Inc.)
Specification-Title: SAP Java Connector v3
Specification-Version: 3.0.9
Specification-Vendor: SAP AG, Walldorf
Implementation-Title: com.sap.conn.jco
Implementation-Version: 20120724 0023 [3.0.9 (2012-07-19)]
Implementation-Vendor-Id: com.sap
Implementation-Vendor: SAP AG, Walldorf
Main-Class: com.sap.conn.jco.rt.About
-----
-----

```

## Verifying a Successful Activation of an Adapter

Verification ensures that the adapter (which includes Advanced Data Source Adapters) was successfully installed and available as a data source.

**To verify a successful activation**

1. Start and log into Studio.
2. In the resource tree on the left, select a location to add a data source, right-click, and select New Data Source.

In the New Physical Data Source window that opens, your adapter should appear in the list of data source drivers, indicating a successful installation.

3. Click Cancel.

## Increasing the Maximum Size of Excel Sheets for SharePoint

Getting data from an Excel worksheet that exceeds the maximum allowable size in SharePoint, results in a "413 Request Entity Too Large" message.

To avoid the message, you must increase the size of workbook allowed to be opened by Excel Services and the default IIS request size.

**To increase the size of a workbook in Excel Services**

1. Open SharePoint Central Administration.
2. Navigate to Application Management > Manage Service Applications > ExcelServiceApp > Trusted File Locations.
3. Select the appropriate Address.
4. Under the Workbook Properties section, locate a Maximum Workbook Size option.
5. Set this value to the required file size in MB.
6. Click OK to save the setting.

To avoid error messages, make sure the value is higher than the largest workbook size in SharePoint.

**To increase the default IIS request size**

1. Open a command window.
2. Navigate to  
<drive>\Windows\System32\inetsrv
3. Type the following command:  
appcmd.exe set config "http://localhost/<rmft\_virtual\_dir>"  
-section:system.webServer/serverRuntime  
/uploadReadAheadSize:"request size in bytes" /commit:apphost

For example:

```
appcmd.exe set config  
"http://localhost/repliweb-mft"-section:system.webServer/serverRun  
time /uploadReadAheadSize:"100000000" /commit:apphost
```

**4. You can check the configuration using the following URL in your browser:**

```
https://<your site>.com/_vti_bin/ExcelRest.aspx/<document  
library>/<folder (optional)>/<file name>.xlsx/OData/<sheet name>
```

# Retrieving Data Source Metadata

---

To complete the data source creation process in Studio, the data source metadata must be introspected from the source. This topic describes how to introspect the data sources that you have configured, set filters for introspection, and reintrospect data sources.

The following topics are covered:

- [About Introspection and Reintrospection](#), page 108
- [Introspecting Data Sources](#), page 109
- [Tracking and Viewing the Introspection Process](#), page 118
  - [Tracking Introspection](#), page 118
  - [Viewing the Introspection Task Status Report](#), page 118
  - [Viewing the Introspection Report for a Data Source](#), page 119
- [Introspecting Data Source Table and Column Comment Metadata](#), page 120
- [Setting Introspection Filters on a Resource](#), page 121
- [Reintrospecting Data Sources](#), page 124
  - [Reintrospecting a Data Source Immediately](#), page 125
  - [Scheduling Reintrospection](#), page 125
  - [Triggering Reintrospection](#), page 126
- [Tips on Introspecting Multiple Files in a Network Share Folder](#), page 127
- [Tips on Introspecting Based on a CREATE TABLE Statement](#), page 128
- [Tips on Introspecting Large Data Sources](#), page 128

You can use the TDV API to set up introspection tasks and view the results. You can find the introspection API operations under:

`/Data Services/Web Services/system/admin/resource/operations/`

For instructions on how to use these operations, open the operation in Studio and click the Info tab, or see the *TDV Application Programming Interfaces Guide*.

## About Introspection and Reintrospection

*Introspection* is the process of collecting native data source metadata so that all selected resources—like catalogs, schemas, tables, and procedures—are represented in a standardized way in the TDV virtual data modeling layer. The representations include capabilities and connection profiles. Composite views and procedures can then be built on the data modeling layer.

Introspection can be performed any time after data source configuration. When setting up introspection, you can also set filter criteria so that any new resources of interest are automatically introspected.

Introspected resources are added to the Studio resource tree for use in the Studio modeling layer, where you can then create views, procedures, and other resources based on those data resources. The metadata layer can be further enhanced by definition of indexes and primary keys, by discovery of data relationships, and by gathering of statistics about the data. The TDV query engine uses introspection data to generate efficient queries with source-aware algorithms.

See [Retrieving Data Source Metadata, page 107](#) for more information.

After each data source instance is configured and introspected in Studio, you can use that instance with any other data source instance to create views and procedures that intermix them all.

**Note:** Privileges on objects in the Data Source are evaluated only at the time of introspection or later when a FETCH is called during statement execution. So if privileges on an object in the data source are lowered after introspection, the error will not be caught until actual statement execution.

*Reintrospection* is the process of updating the data modeling layer after a data source has changed. During reintrospection, new data resources can also be automatically introspected for the first time.

Reintrospection can be initiated in any of these ways:

- Immediately, at any time.
- Automatically, according to a schedule.
- Triggered by conditions that you specify.
- Invoked by a TDV API call.

You can set filters that automatically reintrospect based on criteria applied to a catalog, schema, node, or resource.



Introspection and reintrospection can be performed in the background. Studio provides status reports about the resources selected. Multiple introspection and reintrospection tasks can be initiated on many resources. After resources are introspected, reintrospection is needed only if resource metadata has changed.

The introspection steps are similar for all data sources. They fall into three phases, each of which affects performance:

- [Understanding the Resource ID Fetching Phase, page 129](#)
- [Understanding the Introspection Plan Creation Phase, page 130](#)
- [Understanding the Introspection Plan Implementation Phase, page 130](#)

## Introspecting Data Sources

For information about configuring TDV-supported data sources see:

- [Working with Data Sources, page 67](#)
- [Configuring Relational Data Sources, page 87](#)
- [Configuring Web-Based Data Sources, page 97](#)
- [Configuring File Data Sources, page 161](#)

Introspection steps are described in the following sections:

- [Invoking Data Source Introspection, page 109](#)
- [Introspecting a Data Source, page 110](#)

Various methods are available for working with introspection, including:

- [Tracking Introspection, page 118](#)
- [Tips on Introspecting Based on a CREATE TABLE Statement, page 128](#)

## Invoking Data Source Introspection

You can invoke data source introspection when you first create a connection to a data source or at any time after the data source has been created.

### **To invoke introspection when the data source is initially created**

- Click the Create and Introspect button on the New Physical Data Source panel.

### **To invoke data source introspection at any time after the data source has**

**been created**

Use any of these methods:

- Right-click the name of the data source in the Studio resource tree and select the Add/Remove Resources option.
- Select the data source in the Studio resource tree. Open the Resource menu and select Add/Remove Resources.
- Open the data source and click the Add/Remove Resources button.

If you request multiple introspection tasks for the same data source, the requests are queued and executed sequentially, with all but the current task listed as WAITING.

## Introspecting a Data Source

The introspection steps include three phases:

- Fetching the resource information from the data source.
- Creating an introspection plan based on rules and filters.
- Introspecting the data source.

All of these phases are accomplished using the Data Source Introspection window.

### To introspect a data source

1. Invoke the introspection process as described in [Invoking Data Source Introspection, page 109](#).

The Data Source Introspection window opens and loads a list of resources that it detects in the data source.

The process of loading resources can take significant time, depending on the size of the data source, connectivity, and whether the resource information is cached within TDV. See [Understanding the Resource ID Fetching Phase, page 129](#).

While resource information is loading, you can start selecting resources for introspection by checking the boxes next to resource names. You can even start an introspection task prior to loading all of the resource information.

**Note:** If you click a triangle to expand a container, TDV immediately makes an extra call to load the contents of that container. This allows you to prioritize the loading of resources.

2. Select the resources you want to introspect by checking the boxes next to them.

If you select a parent folder, all of the resources it contains are selected.

**Note:** If you select a catalog, schema, or parent node before the entire list of contained resources is loaded, only those child resources that were loaded at the time of selection are selected. In this case, you might want to recheck later that the entire list has been loaded.

When you select a resource, a Properties tab on the right displays the boxes that can be checked to control introspection of new resources in the future. See [Reintrospecting Data Sources, page 124](#).

3. Optionally, filter the display of detected resources as described below.

A count of the number of detected resources that are visible in the resource list versus the total number of resources is shown at the top of the resource list (for example, 5 Visible of 6 Total).

You can use the fields and buttons above the resource list to control what is displayed.

When searching with the Find field, type part or all of the name of a resource if you want to view only resources starting with this string. The Find field search pattern has the following rules:

- Search patterns are applied to the entire resource path and name.
- Only matches are shown.
- The characters in the search pattern do not need to be adjacent—only in the same order.
- The search pattern is not case-sensitive.
- You can use “/” (forward-slash) to control how containers match. Without a slash, the search pattern spans catalog, schema, and resource names. (For example: abc matches resource a/b/c.) With one or more slashes, matching characters must be found in the same positions relative to the slashes.
- No wildcards are supported.

When searching with the Show field, filter what is displayed in the resource list using one of the following options.

Option	What it shows
Introspectable	All resources that can be selected for introspection.

Option	What it shows
Introspected	The resources that have already been introspected.
Changes	Only the changes made since the dialog was opened, including new selections and clears.
Adds	Only resources that have been added since the dialog box was opened.
Removes	Only resources that have been selected for removal from TDV since the dialog was opened.

- When searching with the filter buttons, click any of the buttons to include or not include empty containers, check or clear all resources, or expand or collapse the list.
4. Optionally, click Refresh Resource List to refresh the list of resources that are available for introspection.

**Note:** Any currently selected resources are unchecked during the refresh process.

You must click Refresh Resource List if you have added new resources after caching metadata and you want to bring those new resources into TDV. Studio and the TDV Server cache the resource list, and this button forces both caches to be refreshed. By default, the list of resources is cached within Studio for the seven most recently introspected data sources during the current user session. This cache exists only in memory and is cleared when Studio is closed. Another cache exists within the TDV Server to improve resource load time. The cache within TDV Server persists across Server restarts.

5. Select how you want TDV to run introspection based on the resources it encounters using the check boxes at the bottom of the Data Source Introspection dialog.

Check Box	Description
Re-Introspect previously introspected resources	<p>Check to introspect all data sources, including those already introspected.</p> <p>If this check box is checked and dimmed then you are working with a data source adapter that has not yet been upgraded to the new introspection framework.</p> <p>Select this check box if you want to update existing TDV metadata for resources that might have changed at the source.</p> <p>Clear this check box for faster response when adding a new set of resources. You can work with new resources more quickly if you do not perform unnecessary full reintrospections of all existing resources.</p> <p>This check box setting does not apply to reintrospection initiated by API, scheduled reintrospection, trigger-initiated reintrospection, or manually initiated reintrospection.</p>
Allow partial introspection, omitting resources with errors	<p>Check to allow the metadata of those resources that are introspected to be committed to the TDV repository even if other resources fail to introspect.</p> <p>If this check box is checked and dimmed then you are working with a data source adapter that has not yet been upgraded to the new introspection framework.</p>
Stop introspection upon the first error	<p>Check only if the data source adapter does not yet support the new introspection framework. If unchecked, you can view all errors and warnings in the Introspection Status report without prematurely ending the introspection of other resources.</p> <p>If this check box is checked and dimmed, you are working with a data source adapter that has not yet been upgraded to the new introspection framework.</p>
Copy privileges from parent folder	<p>Check if you want the data source resources to inherit the access privileges accorded to the parent resource.</p>

6. Optionally, for SOAP data sources, expand and define properties for each of the nodes. Properties can include any of the following.

Property	Description
Detect New Resources During Re-Introspection	<p>If you select this option, child resources added to the current resource subsequent to this introspection will be detected during reintrospection.</p> <p>If the current resource is a catalog and you add a schema to it subsequent to this introspection, the added schema is detected during reintrospection. For details on reintrospection, see <a href="#">About Introspection and Reintrospection, page 108</a>.</p> <p>If you do not select this option, child resources added to the current resource subsequent to this introspection are <i>not</i> detected during reintrospection.</p> <p>If the current resource is a catalog and a schema is added to it subsequent to this introspection, that schema is <i>not</i> detected during reintrospection. For details on reintrospection, see <a href="#">Reintrospecting Data Sources, page 124</a>.</p>
Binding Profile Type	Allows specification of the HTTP transport protocol, literal encoding scheme, and document message style.
Use Endpoint URL	<p>Check box that allows you to configure the endpoint URL. If it is not checked, the URL defined in the WSDL is used.</p> <p>The Endpoint URL displays the real URL of the SOAP data source, which might be different than the WSDL URL.</p> <p>If the specified URL is invalid, the introspection process fails for the SOAP data source. The WSDL data source fails until the request is sent.</p>
Endpoint URL	<p>The Endpoint URL displays the URL where clients can access the SOAP data source, which might be different than the WSDL URL.</p> <p>You can use this field to edit the endpoint URL.</p>
Default Timeout (msec)	The number of milliseconds the connection waits before declaring a failure is the attempt is unsuccessful.
MTOM Enabled	Select to enable the use of Message Transmission Optimization Mechanism (MTOM), a method of sending binary data to and from Web services.

Property	Description
Fast Infoset Enabled	Select to allow conversion of XML files into XML Infoset. This option provides for more efficient serialization than the text-based XML format.
Timeout (msec)	The number of milliseconds the connection waits before declaring a failure is the attempt is unsuccessful.
Choose Input Envelope	Obsolete field for legacy WSDL data sources. If you do not to select this option, the Choose Top Level Child Elements appears.
Choose Top Level Child Elements	Select this option to map the operation's request and response to input and output parameters, respectively. This option is configurable for every message part separately.
JMS related	If the SOAP data source connects through JMS, your node might display several fields that allow you to enter JMS information such as: <ul style="list-style-type: none"> <li>• JMS Connector</li> <li>• JMS Destination</li> <li>• JMS Delivery Mode</li> <li>• JMS Expiry</li> <li>• JMS Priority</li> </ul>

- Optionally, expand and define introspection properties, which can include any of the following.

Property	Description
Detect New Resources During Re-Introspection	<p>Detect child resources added to the current resource after this introspection.</p> <p>If the current resource is a catalog and you add a schema to it after this introspection, the added schema is detected during reintrospection. See <a href="#">About Introspection and Reintrospection, page 108</a>.</p> <p>If you do not select this option, child resources added to the current resource subsequent to this introspection are <i>not</i> detected during reintrospection.</p> <p>If the current resource is a catalog, and a schema is added to it after this introspection, that schema is <i>not</i> detected during reintrospection. See <a href="#">Reintrospecting Data Sources, page 124</a>.</p>

Property	Description
Wildcard Symbol for Single Character Match	Defaults to an underscore.
Wildcard Symbol for Zero or More Character Match	Defaults to a percent symbol (%).
Escape Character for Wildcard Symbols	Defaults to a backslash (\).
Filter in Case Sensitive Mode	Check box that indicates your preference for running filters.
Separator for Each Filter	Defaults to a comma (,).
New Resource <Schema   Catalog   Procedure   Table> Name Filter(s)	Allows you to save the filter settings with a name that you specify.
Character Set	Character encoding type.
Schema Location	Enter the schema location using this syntax: <code>&lt;namespace&gt; &lt;location&gt; [&lt;namespace&gt; &lt;location&gt;]</code>  <namespace> is the target name space for the XML schema.  <location> is the absolute path (including the name of the file) to the .XSD file.
No Namespace Schema Location	The URL (one only) of a schema document that does not define a target name space.
Delimiter	Defaults to comma (,).
Text Qualifier	Defaults to asterisk (*).
Starting Row	Default to 1.
Has Header Row	Check box is selected by default.

8. Optionally, you can set up filters for the resources, but they are applied only if reintrospection is done. See [Setting Introspection Filters on a Resource, page 121](#), for more information.
9. Click Next.



Studio opens a Data Source introspection plan that lists the resources that are to be introspected, based on your selections. The Data Source Introspection plan lists all the introspection changes (additions, removals, and updates) that will occur when you click the Finish button.

- Resources in black will be introspected.
- Resources in green will be added. (Their parent resources are also shown in green.)
- Resources in gray will be removed.

10. Review the introspection summary, and if necessary, click Back to revise the introspection plan and how it is to be done.

11. Click Finish to introspect the resources.

TDV introspects the selected resources and adds the metadata about those resources to the TDV repository.

12. You can click OK to dismiss this window at any time; however, the introspection process continues running in the background. The introspection process continues even if you close the Studio session.

Panel	Shows
Running Tasks/Completed Tasks (left side)	The progress of introspection tasks and their status in the current user session.
Introspection Summary (upper right)	The status; introspection start and end times; number of warnings and errors; and the number of resources that were added, removed, updated, and skipped (plus an overall total).
Details (lower right)	<p>The specific resources that were added, updated, removed, and skipped in the selected introspection. Those resources with no changes in the metadata used by TDV are added to the Skipped count. You can:</p> <ul style="list-style-type: none"> <li>• Show options—Filter the details displayed to view all details, only warnings, or only errors.</li> <li>• Show Details—Select any added resource then click show details to get additional information about the resource.</li> <li>• Export—Click to save a text introspection report that lists the tables, columns, and indexes that were introspected. See <a href="#">Viewing the Introspection Report for a Data Source, page 119</a> for an example of this file.</li> </ul>

13. You can view the introspection information for a data source at a later time. See [Tracking and Viewing the Introspection Process, page 118](#).

## Tracking and Viewing the Introspection Process

- [Tracking Introspection, page 118](#)
- [Viewing the Introspection Task Status Report, page 118](#)
- [Viewing the Introspection Report for a Data Source, page 119](#)

### Tracking Introspection

You can track time usage by the introspection process with the support of log files. A configuration parameter controls debug logging.

#### To diagnose introspection

1. Select Administration > Configuration from the main Studio menu.
2. Locate the Debug Output Enabled for Data Sources configuration parameter.
3. Set the parameter value to True.
4. After introspection, open `cs_server_events.log` to see how much time the various introspection steps used.

### Viewing the Introspection Task Status Report

When you introspect a data source, TDV saves the introspection status information for all introspections done in the current user session so that it can be viewed at any time. The Introspection Task Status report displays the status of the data source introspections as well as the summary and details for the latest introspection that was performed.

You can view the introspection summary and details for any previously introspected data source at any time. See [Viewing the Introspection Report for a Data Source, page 119](#) for more information.

### To view the Introspection Task Status report

1. Open the introspection report:
  - From the Studio Resource menu, select Introspection Task Status.
  - If any introspection task is still running, you can click the introspection task progress bar at the bottom margin of the Studio application window to open this window.
2. Review the details of the introspection task status.

Panel	Shows
left	The status of all completed introspection tasks during this user session. A status of SUCCESS indicates that at least one resource was introspected. It does not mean that no errors or warnings were logged, but that the attempt was successfully committed to the data source.
right	The status summary and details for the most recent introspection.

### Viewing the Introspection Report for a Data Source

When you introspect a data source, TDV saves the introspection information for the data source so that it can be viewed at a later time. The Introspection Report displays the summary and details of the most recent successful introspection of this data source.

#### To view the introspection results for a data source

1. Open the data source in Studio.
2. Click the Introspection Report tab.

The Introspection Report tab displays the results of the latest introspection. It alerts you to any warnings or errors that might need your attention. It also indicates how many resources were introspected to synchronize changes with the data source.

3. Use the Show drop-down list to choose whether to display all warnings or errors. This selection filters the results to show any resources that had a problem.

Sometimes network latency or other data collisions can cause a problem with resource introspection; these problems can be cleared up by attempting to introspect those resources again. At other times, a data source type incompatibility might cause a table column to fail to load.

Refer to the *TDV Reference Guide* for details about the data source data types that are supported by TDV.

4. Optionally, select a message in the Details list and click Show Details.

TDV shows details about that message.

5. Optionally, click Export to export text file that contains a list of introspected resources.

## Introspecting Data Source Table and Column Comment Metadata

Data sources, such as Oracle and Teradata, include the ability to add annotations or comments for added understanding. During the introspection process, TDV can retrieve this information and add it to the annotations field for each resource. The annotation field can be viewed on the Info tab of each resource.

### Requirements

Requires one of the following data sources:

- Oracle
- DB2 LUW
- Teradata
- Netezza
- PostgreSQL
- DB2 mainframe
- Vertica, Composite
- SAP HANA
- HSQLDB
- Hbase

You can enable or disable the comments introspection for Oracle data sources.

### To enable comment introspection

For data sources other than Oracle, comment introspection is performed by default.

1. Open the Oracle data source for which you want table and column level metadata retrieved.
2. Select the Advanced tab.
3. Locate and select the Introspect comments check box.
4. Run the introspection process.
5. Review the comments by opening a resource editor and selecting the Info tab.

## Setting Introspection Filters on a Resource

When you introspect or reintrospect a data source, you can set filters to control how TDV runs the reintrospection process. You can set filters at the data source, catalog, or schema level to:

- Filter by catalog, schema, table, or procedure name.
- Use wildcard characters to filter names.
- Detect new resources during introspection.
- Filter in case-sensitive mode.

The filters are applied during reintrospection, whether invoked by API or trigger, at a scheduled time, or manually. Filters do not apply on *initial* introspection but are applied when during reintrospection.

**Note:** These filters are only available on relational data sources.

### To set introspection filters on a resource

1. Invoke Add/Remove Resources from the context menu for a data source.
2. In the Data Source Introspection window, select a resource in the list on the left.
3. Optionally, in the Properties tab on the right, check Detect New Resources During Re-Introspection.
  - If you select this option, child resources added to the current resource subsequent to this introspection will be detected during reintrospection.

If the current resource is a catalog and you add a schema to it subsequent to this introspection, the added schema is detected during reintrospection. For

details on reintrospection, see [About Introspection and Reintrospection, page 108](#).

- If you do not select this option, child resources added to the current resource subsequent to this introspection are *not* detected during reintrospection.

If the current resource is a catalog and a schema is added to it subsequent to this introspection, that schema is *not* detected during reintrospection. For details on reintrospection, see [Reintrospecting Data Sources, page 124](#).

4. Optionally, choose the filter settings for each resource.

The filters displayed in the Properties tab on the right depend on whether you have selected a data source, catalog, or schema. For example, if you selected a catalog in the resource list, you can supply the value for filtering the schemas in the catalog in the New Resource Schema Name Filter(s) field. To filter for all schemas that start with the string SYS, you would type SYS%.

For a data source, Studio displays the filters shown in the figure below. The Properties tab for a selected data source displays wildcard symbols you can use to filter the names of catalogs, schemas, tables, procedures, and folders. For a schema, Studio displays a smaller collection of filters.

The possible fields on the Properties tab are described below:

Field or button	Description
Wildcard Symbol for Single Character Match	Symbol that stands for a single character. The default symbol is the underscore ( <code>_</code> ) and this cannot be changed. For example, if you type <code>ab_</code> in the Schema Name Filter(s) field, it matches schema names such as <code>abc</code> and <code>abd</code> , where <code>c</code> or <code>d</code> occurs in place of the underscore.
Wildcard Symbol for Zero or More Characters Match	Symbol that stands for zero or more characters. The default symbol is the percentage sign ( <code>%</code> ) and this cannot be changed. For example, if you type <code>ab%</code> in the Schema Name Filter(s) field, it would match schema names such as <code>abc</code> , <code>abd</code> , <code>ab</code> , and any name with <code>ab</code> as prefix.
Escape Character for Wildcard Symbols	Character for escaping the symbols specified in the previous two fields (Wildcard Symbol for Single Character Match and Wildcard Symbol for Zero or More Characters Match). The default escape character is backslash ( <code>\</code> ) and this cannot be changed. For example, the sequence <code>ab\_c</code> would match the resource-name <code>ab_c</code> by escaping the underscore ( <code>_</code> ).

Field or button	Description
Filter in Case-Sensitive Mode	<p>Check to make the filter pattern case-sensitive.</p> <p>This option is not available for certain data sources. In such cases, the underlying physical data source determines the case-sensitive mode, and filters the names of its resources as well for introspection.</p>
Separator for Each Filter	<p>Symbol for separating filters. The default separator is a comma (.). For example, if you type orders, customers, it would match the table names orders and customers.</p>
New Resource <resource type> Name Filter(s)	<p>Where &lt;resource type&gt; can be a catalog, schema, procedure, or table depending on what is selected in the resource list. For example, if you select a data source that has no catalogs or schemas but does have procedures and tables, then only New Resource Table Name Filter(s) and New Resource Procedure Name Filter(s) are displayed on the Properties tab.</p> <p>Enter filters on the Properties tab to introspect only the resources that meet the filter criteria. See the preceding descriptions for wildcard symbols, escape character for wildcard symbols, and separator for filters.</p> <p>If no filter is specified, all new catalogs/schemas/procedures/tables (and their contents) are added during reintrospection. Existing resources that were not selected during the initial introspection or during a manual introspection are ignored during reintrospection, even if they match the New Resource Catalog &lt;resource type&gt; Name Filter(s) string. You can add previously ignored resources at any time using Add/Remove Resources.</p> <p>For example, if BZHANG is not selected for introspection and a reintrospection filter of B% is set for the data source, subsequent reintrospection finds any new schemas that begin with B but does not introspect BZHANG.</p> <p>The filters do not use the same serial character matching pattern as the Find field, which applies to the Introspectable list only. Strings are matched using the case sensitivity setting and the wildcard symbols specified.</p>

5. Click Next.

The Data Source Introspection summary page lists all the introspection changes (additions, removals, and updates) that will occur when you click the Finish button.

- Resources in black will be introspected.
- Resources in green will be added. (Their parent resources are also shown in green.)
- Resources in gray will be removed.

The summary also lists at the bottom the rules that are applied during introspection as a result of what you selected for the check boxes on the previous panel.

6. Click Finish to initiate the introspection.

## Reintrospecting Data Sources

*Reintrospection* is the process of synchronizing the TDV Server metadata representation of an introspected data source with the current state of the data source.

You can invoke reintrospection at any time, schedule it to occur periodically, use triggers, or call for it using a system API. Automated reintrospections can either just report on metadata differences or automatically reintrospect to synchronize TDV metadata to the current state of the resource.

Depending on the data source type (relational or file), all changes are detected, including the following:

- Changes in column data types
- Removed tables or columns
- Added tables or columns

Persistent reintrospection filters can be set to detect and incorporate new resources that meet the filter criteria during reintrospection. The filters are defined during introspection by the properties in the right side panel of the Data Source Introspection window.

Resources that were explicitly introspected remain introspected. Resources that were not selected during a previous introspection are not introspected, even if they happen to meet the criteria of a filter intended to find and introspect new resources.

The following sections describe the ways you can invoke reintrospection:

- [Reintrospecting a Data Source Immediately, page 125](#)



- [Scheduling Reintrospection, page 125](#)
- [Triggering Reintrospection, page 126](#)

If you are introspecting large data set, see this section for additional information:

- [Tips for Reintrospecting Large Data Sets, page 132](#)

If you are reintrospecting an SAP BW data set, see the *TDV SAP BW Adapter Guide*

## Reintrospecting a Data Source Immediately

You can reintrospect a data source immediately at any time.

### To reintrospect a data source immediately

1. You can reintrospect immediately in two ways:
  - Right-click a data source name in the resource tree, and select Re-Introspect Now.
  - Open the data source in Studio. Use this method if you want to review the data source definition or the scheduled reintrospection settings.
2. At the bottom of the Studio workspace for the open data source, click the Re-Introspection tab.
3. In the Immediate Reintrospection section, click Re-introspect Now.
 

The Enter Password window opens if the password to access the data source was not saved when the data source was originally added to the server. For further details, see the descriptions for the Save Password and Pass-through Login fields under [Adding Relational Data Sources, page 90](#).
4. If necessary, supply the password that is required to access the data source, and click OK.

TDV immediately reintrospects the data source and displays the Introspection Task Status window with the introspection status, summary, and detailed results. See [Viewing the Introspection Task Status Report, page 118](#) for more information.

## Scheduling Reintrospection

You can schedule reintrospection to occur at a specific time, date, or interval. The scheduled reintrospection option is available only if the password was saved when the data source was originally added to the server.

### To schedule reintrospection

1. Right-click a data source name in the resource tree, and select Open.
2. Click the Re-Introspection tab at the bottom of the Studio workspace for the open data source.
3. In the Scheduled Re-Introspection section, select the options for the schedule you want reintrospection to follow.
  - a. Select Save Detected Changes if you want the changes detected in the data source during reintrospection to persist (that is, be saved in the repository). Uncheck this box if you want to inspect the changes prior to accepting them and committing data source metadata changes to the TDV metadata.
  - b. Select the frequency with which you want reintrospection to repeat:
    - None (the default). Reintrospection is not scheduled.
    - Repeat Every < > minute(s), and type the number of minutes in the text field.
    - Repeat Hourly for the reintrospection to recur every hour.
    - Repeat Daily for the reintrospection to recur every day.
    - Repeat Weekly for the reintrospection to recur every week.
  - c. Specify the starting time and date for the introspection in the corresponding drop-down lists.  
  
 The date entered indicates the time at which the first occurrence of the reintrospection is to occur. For example, if a daily event is set for 11:55 a.m. three days in the future, it will run at 11:55 a.m. in three days and then every day thereafter.
  - d. To send a reintrospection report to one or more email addresses, type and confirm the email addresses of the recipients.  
  
 Separating multiple email addresses with commas (,) or semicolons (;).
4. Right-click on the resource panel's upper tab and select Save to save your settings.

### Triggering Reintrospection

You can set up a trigger to reintrospect based on a JMS event, a system event, timer event, or user-defined event. See [Triggers, page 309](#) for more information about triggers.

## To set up a reintrospection trigger

1. Create a new trigger:
  - a. Right-click in the Studio resource tree where you want the trigger to reside.
  - b. Type a name for the new trigger and click OK.
2. Specify the condition that is to invoke the trigger: JMS Event, System Event, Timer Event, or User Defined Event.
3. For Action Type, select Reintrospect Data Source.
4. Specify the data source in one of these ways:
  - Type the resource-tree path and data source name in the Data Source Path field.
  - Click Browse and in the Select a datasource dialog box navigate to the data source, highlight it, and click **OK**.
5. Optionally, specify email information (in the To, Cc, Bcc, Reply-To, Message Subject, and Message Body fields) to send email when the trigger fires.
6. Select one or both of these options:
  - Do Not Persist Detected Changes—If you do not want to persist detected changes.
  - Do Not Send If No Changes Detected—If you do not want email sent if no changes were detected.
7. Check Enable Trigger near the top of the panel to enable this trigger.
8. Use Studio Manager to track the status and history of when this trigger runs.

## Tips on Introspecting Multiple Files in a Network Share Folder

If the root path does not show the network mapped drives, the Root Path can be specified as UNC path without using the Browse button.

1. Define a new or edit an existing Microsoft Excel (non-ODBC) data source.
2. On the Basic tab for the Local File System value, if the Browse button does not allow you to navigate to the machine or root directory that contains your Excel data you can type the root directory location in the Root Path field. For example:

R:/<mymachinename>/work/users/mega/excel-ds

**Note:** The direction of the slashes in the root path are important. If you know your files are in a particular directory and they do not show in the introspection window, modify the direction of the slashes in your root pathname and save the data source.

3. Save the Microsoft Excel (non-ODBC) data source.
4. For an existing data source, on the Basic tab, scroll to and click the Add/Remove Resources button.
5. Multiple files in the network share folder should now be available for introspection.

## Tips on Introspecting Based on a CREATE TABLE Statement

Under some circumstances, you can significantly reduce introspection time by collecting metadata based on the issued CREATE TABLE DDL statement rather than by introspecting it from the database after the table has been created. A configuration parameter is available for doing this.

### To introspect a data source based on CREATE TABLE statement

1. Select Administration > Configuration from the main Studio menu.
2. Navigate to Server > Configuration > Debugging > DDL > Introspect newly created table using data source introspection.
3. Set the parameter value to True.
4. If you use the DDL statement to introspect, you can only examine table columns, primary keys, and indexes. Also, the results may be different from data source introspection.

## Tips on Introspecting Large Data Sources

Large data sources with complex schemas and big tables with lots of columns have a correspondingly large amount of metadata that can pose challenges for TDV. For TDV, it is not the amount of data stored, but rather the complexity and amount of metadata that defines the data source that is the most important factor for performance, particularly during introspection.

Introspection can be broken down into three phases.

- [Understanding the Resource ID Fetching Phase, page 129](#)

- [Understanding the Introspection Plan Creation Phase, page 130](#)
- [Understanding the Introspection Plan Implementation Phase, page 130](#)

Understanding these phases can improve introspection performance for large data sources:

- [Tips to Improve Performance of Resource ID Fetching, page 131](#)
- [Tips to Improve Performance of Introspection Implementation, page 131](#)
- [Tips for Reintrospecting Large Data Sets, page 132](#)

Each of these phases has independent performance considerations.

## Understanding the Resource ID Fetching Phase

So that TDV has complete metadata about all of the resources in your data set, do at least one full data source scan to retrieve all possible object names (resource identifiers) from within the data source. The initial fetch loads the resource list with basic metadata for all catalogs, schemas, tables, and procedures.

This phase corresponds to [Invoking Data Source Introspection, page 109](#). After you have invoked introspection, TDV begins populating the resource list in the Data Source Introspection dialog with the resources it detects.

When obtaining this resource ID list, keep these things in mind:

- The list of resource IDs is cached within the TDV so that future fetches will be faster unless the list is recreated.
- Retrieving this list is asynchronous so that after the resources you need are visible within Studio, you can choose those resources before the full scan finishes.
- See [Tips to Improve Performance of Resource ID Fetching, page 131](#) when introspecting large data sources.

The actual fetching of Resource ID from data sources is multithreaded to provide concurrency. One thread per container (data source root, schema, catalog, or other type of container) is created. The degree of parallelism (maximum number of threads) is either the number of processors, or half of the data source maximum connection pool size, whichever is less. Degree cannot be less than 1.

After the resource IDs are fetched and placed within a cache in the TDV, the resource IDs are directly fetched from the cache, unless the cache has been invalidated and needs to be recreated. This cache-based fetch is single-threaded but fast. The results of the fetch are streamed to Studio.

The resource identifiers are invalidated and the resource ID list is recreated when:

- You choose Refresh Resource List in the Data Source Introspection dialog when you choose Add/Remove Resources.
- Introspection (see [Understanding the Introspection Plan Implementation Phase, page 130](#)) is executed with an introspection plan that requests detection of new resources to be added.
- You invoke the deprecated or UpdateDataSourceChildInfosWithFilter (or the deprecated UpdateDataSourceChildInfos) Web services operation.

Reintrospecting existing resources does not recreate the cache unless the user has requested that new resources be detected for adding.

## Understanding the Introspection Plan Creation Phase

After you have fetched the complete list of resource IDs (see [Understanding the Resource ID Fetching Phase, page 129](#)), you are ready to select the resources to introspect; that is, create an introspection plan ([Introspecting a Data Source, page 110](#)).

Loading resource names for a large data source can take a long time, so TDV lets you choose resources to introspect and drill down into as soon as their names are visible.

For container resources selected in the Add/Remove Resource dialog box, check the Detect New Resources During Re-Introspection check box under Properties on the right.

Some resources (most commonly the container resources within relational data sources) provide filter property options: New Resource Table Name Filter(s) and New Resource Procedure Name Filter(s). These filters only limit resources newly found during reintrospection.

Resources can be added through recursion using the TDV API.

## Understanding the Introspection Plan Implementation Phase

After you select the resources to include and specify any filters for newly found resources, TDV displays a list of the resources in the introspection plan.

The introspection plan is displayed. You can change it by clicking Back and changing the filters and other settings as described in [Introspecting a Data Source, page 110](#).

After completing the list of resources to be introspected, click Finish and the introspection task is launched. The introspection task status is displayed, along with a summary of the actions taken.

If you close Studio before finishing, introspection continues to run in the background.

The following describes the introspection and performance considerations:

- Introspection happens concurrently, one thread per container.
- Batching is applied to further improve performance.
- For each container, TDV evaluates the contents and breaks it into chunks of resources that have a common parent container and resource type. These chunks are broken into pieces smaller than the maximum introspection batch size. If this size is not defined for the data source, the chunks are divided into several pieces equal to the number of processors, or half the data source maximum connection pool size, whichever is less. This parallelism degree can be overridden within the data source capabilities file using `introspect.override_parallelism_degree`.

**Note:** This override is only available for introspection, not resource ID fetching.

## Tips to Improve Performance of Resource ID Fetching

If you are introspecting a very large data source, you can improve the performance during resource ID fetching by:

- Putting the TDV Server on a machine with many CPUs.
- Increasing the Connection Pool Maximum Size setting in Studio. Open the data source, select the Configuration tab, and select the Advanced tab.

**Note:** The physical data source might be impacted if this number is too high.

- Allocating additional memory for both TDV Server and Studio if the data source you are introspecting has large amounts of metadata. (Large amounts of data do not matter.) To do this, increase the memory settings in these Studio configuration parameters: Privilege Cache Size (On Server Restart) and Metadata Cache Size (On Server Restart).

**Note:** Do not request that a second cache be built while the initial cache of resource IDs is being built. If you do this, TDV does not attempt to merge these requests; instead the work is duplicated in parallel.

## Tips to Improve Performance of Introspection Implementation

To improve introspection performance, you can:

- Put the TDV server on a machine with many CPUs.

- Increase the Connection Pool Maximum Size setting of the data source (be aware that the physical data source can get impacted if this number is too high). To change this setting, open the data source, and modify settings on the Advanced tab.
- Set the `introspect.override_parallelism_degree` in the data source capabilities file. The data source capabilities files for all supported data sources can be found at:

`<TDV_install_dir>\apps\dml`

Setting `introspect.override_parallelism_degree` in the data source capabilities file to a number higher than the number of CPUs might degrade performance. However, if there is network latency between the TDV and data source, setting this to a number higher than the number of CPUs might keep the TDV busy doing what it can while it waits for responses from the data source. This number cannot be higher than the maximum pool size of the data source. For example, this is a good option if you do not want to change the current connection pool size, but want to consume three-quarters of the pool instead of half of it.

- Specify `introspect.max_batch_size` in the data source capabilities file to tune introspection batching to match the batching capabilities of the data source. (Batching is supported for DB2, Oracle, PostgreSQL, Teradata, and Oracle E-Business Suite data sources. The default `max_batch_size` is 999.)

## Tips for Reintrospecting Large Data Sets

The process for reintrospecting data sources is described in [Reintrospecting Data Sources, page 124](#). When reintrospecting large data sets:

- If TDV has introspected a large number of resources for a given data source, introspecting this source again is an expensive operation.
- Reintrospection brings all new resources that have been added to the source after the most recent introspection, if the Detect New Resources During Re-Introspection is selected on the Data Source Introspection/Properties tab.
- If you want to add only a few new resources to the TDV, it might be better to newly introspect the resources rather than reintrospect them, because introspection only targets the selected resources.



# Views and Table Resources

---

This topic describes the Studio user interface that you use to create and work with composite views and table resources.

- [About Composite Views, page 133](#)
- [Creating a New View, page 134](#)
- [Setting Default Query Options, page 135](#)
- [Commenting SQL, page 136](#)
- [Adding Column Level Annotations, page 137](#)
- [SQL Request Annotation Pass-Through, page 137](#)
- [Designing a View and Table Resource, page 138](#)
- [Generating a Model from the SQL Panel, page 159](#)
- [Working with Views and JSON, page 160](#)
- [Designing Column Projections Using the Columns Panel, page 162](#)
- [Obtaining View Details, page 163](#)
- [Executing a View, page 163](#)
- [Generating a Query Execution \(Explain\) Plan, page 164](#)
- [Generating an Explain Plan and Displaying it in a Client Application, page 164](#)
- [Rebinding a View, page 165](#)
- [Displaying the Lineage of a View, page 166](#)
- [View Column Dependencies and References, page 168](#)
- [Creating a View from a Cube, page 178](#)
- [Ad Hoc SQL and the SQL Scratchpad Editor, page 178](#)

## About Composite Views

A composite view is a virtual data table defined by SQL and TDV metadata. A view defines a SQL query that comprises a SELECT statement and any ANSI-standard SQL clauses and functions. A view can JOIN or UNION to any resource defined in the TDV virtual data layer.

A view is designated in the resource tree with the View icon.

For more information about the View UI, see [View and Table Editor Panel Reference, page 611](#)

Views can be selectively published to make them available through client applications or the Web. If you want to make a view available to client programs, you must publish that view. See [Publishing Resources to a Database Service, page 340](#) and [Publishing Resources to a Web Service, page 346](#) for more information.

For information on scheduling a view's execution, see [Creating a Timer Event Trigger, page 318](#).

## Creating a New View

This section describes how to create a view that uses relational data source tables.


For details on selecting a location to create a resource, see [Locating a Container for a TDV Resource, page 42](#).

### To create a view

1. Right-click an appropriate location in the resource tree, and select New View, or use File > New > View.
2. In the Input dialog, type a name for the view.
3. Click OK.

The view is added to the specified location in the resource tree, and the view editor opens the Model Panel in the right pane.

Studio provides a view editor that opens automatically when you create a view. You can open the view editor at any time by double-clicking a view's name in the resource tree.



4. Follow the procedure described in [Designing a View and Table Resource](#), page 138.

## Setting Default Query Options

Query hints are options that you can include to optimize your SQL statement for the TDV query engine. You can specify any of the options that are documented in “TDV Query Engine Options” in the *TDV Reference Guide*.

Options specified in a query override any defaults set using the configuration parameter values.

### To specify global query hints

1. Select Administration > Configuration.
2. In the Configuration window, navigate to Default SQL Options.
3. Click the green plus button.

4. Type an option or hint type value for the Key. For example, INDEX.
5. Type a Key Value. For example, employees emp\_dept\_ix.
6. Click OK, to save the changes and exit the Configuration screen.

## Commenting SQL

You can insert standard SQL comments by starting each line with a pair of hyphens. You can also insert multiple-line C-style comments, using `/*` to start the comment and `*/` to end the comment. Each of these methods is described below.

### To insert standard SQL comments

1. Use one of these methods:
  - In the SQL panel, type two hyphens at the beginning of each line you want to be a comment line.
  - Select the lines you want to comment and type Ctrl-Hyphen, which adds two hyphens to the start of each line.

You can type Ctrl-Hyphen again to remove the hyphens.

- Select the lines you want to comment, and choose Edit > Comment Block.

You can type Edit > Comment Block again to remove the hyphens.

**Note:** If the selected block contains some lines that are already commented, another pair of hyphens is added at the beginning of the lines.

Although comments are stripped from the SQL request at runtime, a TDV configuration setting can cause comments to be passed through to the data sources so that client metadata can be recorded at the source. For details, see [SQL Request Annotation Pass-Through, page 137](#).

### To insert C-style comments

1. In the SQL statement, type `/*` to start the comment and `*/` to end the comment.

## Adding Column Level Annotations

Annotations that are added to tables and views, are carried through when you publish the resource. After publishing, the column level annotations can be viewed in Business Directory or through the other client interfaces that you use to access published TDV data.

### To set TDV to pass through SQL annotations

1. On the Studio resource tree, select the table or view for which you want to add column level annotations.
2. Right-click and select Open.
3. Type the text of your comment in the Annotations field.
4. Save your work.
5. Add annotations to other columns if you want to.

## SQL Request Annotation Pass-Through

SQL annotations (comments) sent in requests to data sources can be used for customer implementations to enhance logging, traces, and tracking. By default, TDV trims SQL annotations from client requests.

### To set TDV to pass through SQL annotations

1. On the Studio toolbar, select Administration > Configuration.
2. In the Configuration window, navigate to TDV Server > SQL Engine > SQL Language > Keep Comments.
3. Select the True radio button.
4. Click Apply.
5. Click OK to close the Configuration window.

## Designing a View and Table Resource

View design involves performing one or more of these tasks, depending on your implementation requirements:

- Add resources for the view.
- Join tables by columns and specify join properties.
- Combine the output of multiple SQL selects.
- Specify global query options.
- Specify query options and query engine hints.
- Specify column output to include in or exclude from the view execution result.
- Apply functions on columns to transform result set values.
- Supply aliases for column names.
- Specify the sorting order for columns.
- Specify GROUP BY, HAVING, or EXPRESSION options.
- Specify constraints for the WHERE clause.
- Specifying indexes, primary keys, and foreign keys.

You can accomplish these tasks using the Model Panel, Grid Panel, SQL Panel, Columns Panel, Indexes Panel, and the Foreign Keys Panel.

The following sections describe how to perform these tasks:

- [Designing a View in the Model Panel, page 138](#)
- [Designing a View in the Grid Panel, page 148](#)
- [Designing SQL for a View in the SQL Panel, page 155](#)
- [Generating a Model from the SQL Panel, page 159](#)
- [Defining Primary Key for a View or Table in the Indexes Panel, page 156](#)
- [Defining a Foreign Key for a View or Table Resource, page 157](#)

### Designing a View in the Model Panel

The Model panel is a graphical tool that helps you create SQL statements (without having to write the code) to obtain useful query results from disparate data sources.

## To design a view

1. Select data resources for the view by dragging and dropping tables, procedures, and transformations into a view.
2. JOIN tables by linking table columns.
3. Configure JOIN properties
  - a. Define the JOIN logical operators.
  - b. Specify the preferred join algorithms or suggest semijoin optimizations.
  - c. Provide estimates of table cardinality to help the query engine optimize the execution plan.
  - d. Include all rows from the left, the right, or both sides of the join.
  - e. Force join ordering or swap the order of the tables in the join.
4. Create UNIONS of SELECT statements, bringing together rows from matching tables.
5. Navigate among SELECT statements and the UNION of those SELECTs.
6. Use query hints to set the maximum number of rows to return, to set case sensitivity, to ignore trailing spaces, to mark the query as STRICT (adhere to SQL-92), or to force the query processing to disk if the query is likely to exceed memory constraints.

The following topics have more information on designing views in Studio:

- [Adding a Resource to the Model Panel, page 139](#)
- [Joining Tables in the Model Panel, page 140](#)
- [Enforcing Join Ordering, page 142](#)
- [Creating a Union, page 143](#)
- [Navigating between Tables in the Model Panel, page 145](#)
- [Specifying the DISTINCT Query Option, page 146](#)
- [Specifying Query Hints, page 146](#)


## Adding a Resource to the Model Panel

You can add resources such as database tables, text files, procedures, and other views to the Model panel. Only a procedure that contains either all scalar outputs or just one cursor output can be included in a view.

### To add a resource to the Model panel

1. Create a new view as described in [Creating a New View, page 134](#).
2. Locate a resource in the resource tree.
3. Drag and drop the resource onto the Model panel.

**Note:** You can use Ctrl-click or Shift-click to select multiple resources, and drag and drop them in the Model panel.



4. Rearrange the resources as needed.

### Joining Tables in the Model Panel

A view that you design might involve joining tables. You can often improve query performance by refining the properties of a join process including:


- Specify how the joined columns should be compared.
- Specify the join algorithm and cardinality.
- Choose a semijoin optimization.
- Specify whether to include all rows from a specific table.

In the Model panel, the join between the selected tables is visible as a line connecting those tables. This type of join is called an INNER JOIN. For details on tuning options, see [Performance Tuning, page 475](#)



## To JOIN tables in the Model panel

1. Select the column from one of the tables to be joined. The first column selected is the “left” side of the join, unless Swap Order is selected in the Join Properties window.
2. Hold down the mouse button and drag from the selected column in the left-side table to the column to join it with in what will be the right-side table.



3. Make sure that columns specified for JOINS are of compatible data types.  
To check the data type of a column, click the Columns tab and open the Columns Panel.
4. Right-click the join icon on the JOIN line and select Properties to open the Join Properties window, or double-click the diamond graphic.
5. Select how the columns should be compared (=, <=, >, and so on) from the drop-down list in the top center of the Join Properties window.
6. In the Include rows section, check the boxes to specify the rows you want to include in the join:
  - Select the upper box to specify the LEFT OUTER JOIN.
  - Select the lower box to specify the RIGHT OUTER JOIN.
7. In the Join Details section:
  - a. From the Specify Join Algorithm drop-down list, select the algorithm to use for the join.

For the descriptions of the different algorithms, see [Semijoin Optimization Option](#), page 503.

- b. Specify the Left Cardinality constraint.

Provides cardinality hint for the left side of a join. It should be a positive numerical value, for example 50.

- c. Specify the Right Cardinality constraint.

Provides cardinality hint for the right side of a join. It should be a positive numerical value, for example 500.

- d. If you select the Semijoin Optimization check box, the TDV query engine attempts to use the results from the number of rows to be processed for the join is minimized, and the query engine's performance is enhanced.
  - e. Select one of the following order options:
    - Default Ordering—Applies the default ordering.
    - Swap Order—Swaps the left and right sides of a join.
    - Force Join Ordering—Overrides join ordering optimization.
  - f. Click OK to save the join specification.
8. Click the SQL tab to verify how the join is specified in the SQL statement, similar to the following example:

```
SELECT
    products.ProductID,
    orderdetails.UnitPrice,
    orderdetails.Status
FROM
    /shared/examples/ds_inventory/products products FULL OUTER { OPTION SEMIJOIN="True",
LEFT_CARDINALITY="50", RIGHT_CARDINALITY="500" } JOIN
    /shared/examples/ds_orders/orderdetails orderdetails
    ON products.ProductID = orderdetails.ProductID INNER JOIN
    /shared/examples/ds_orders/orders orders
    ON orderdetails.OrderID = orders.OrderID
```

9. Click OK.

## Enforcing Join Ordering

You can allow the query engine to reorder the query execution plan based on statistics gathered from the data source table and optimization algorithms. However, given knowledge of the table contents, it is often advantageous to force the processing order derived from the written SQL.

**Note:** Joins that contain any user specified options cannot be reordered.

You can direct the query engine to follow the order in which you joined the tables. For more information, see [SQL Join Reordering, page 499](#).

### To enforce the processing order of table joins

1. Join the tables in the order you want.
2. Right-click the join line and select Properties. See [Joining Tables in the Model Panel, page 140](#).

3. In the Join Properties window, select Force Join Ordering.
4. This step adds the phrase {OPTION FORCE\_ORDER="true"} to the FROM clause and informs the query engine to query the tables in the order in which they are specified in the FROM clause.


## Creating a Union

Studio lets you graphically create a UNION between two or more tables.


### To graphically create a UNION

1. Create the first table for the UNION by dragging the resource onto the Model panel (if it is not already there).
2. Right-click in the background field of the Model panel and choose the Add Union option.

The resources are condensed into a Navigator window called Union0. The tables are shown as smaller icons within the Navigator window.




- Right-click again in the Studio design space and choose the Add Union option to open a second UNION design space, called Union1.



- Double-click anywhere in Union1 to open the UNION for editing.

When you double-click Union1, the entire design space represents Union1, and is blank so that you can add resources to include in the UNION in the next step.



- Drag and drop resources into the Union1 side of the SELECT statement.

The definition of the two tables in the UNION must have the same number of columns in the same order, and they must be of compatible data types, for the UNION to function correctly.

- After defining the second table for the UNION, right-click anywhere in the design space and select UP to return to the top-level query view navigator.

By default the two tables are combined with a UNION ALL, but you can change that to a UNION, EXCEPT, or INTERSECT.

7. Double-click the UNION connector to open the UNION properties.
8. Make your design choices in the Union Properties window.
  - a. By default, the two tables are combined with a UNION ALL (the All check box is checked by default), but you can change that to a UNION, EXCEPT, or INTERSECT.
  - b. Optionally, check the PARALLEL, FORCE DISK, or DISABLE PUSH check boxes.

For a description of TDV supported SQL (UNION, EXCEPT, INTERSECT, the All option) and the available query engine UNION options, see the *TDV Reference Guide*.

- c. Click **OK** to save the union properties.
9. Save the view.

### Controlling the Number of UNION ALL and JOIN Flips

To optimize its execution plan, the query engine can flip between UNION ALL and various kinds of JOINS: INNER JOINS, LEFT OUTER JOINS, and RIGHT OUTER JOINS. If the two SELECT statements do not involve duplicates, the distributive law works for UNION DISTINCT and INNER JOINS as well.

By default, the maximum number of flips between UNIONS and JOINS is 2. You can change this maximum, although increasing it can have a negative impact on memory consumption and plan generation time.

#### To change the maximum number of flips between UNION ALL and JOIN

1. From Administration in the Studio main menu, select Configuration.
2. Navigate to Server > SQL Engine > Overrides.
3. Change the Value from its default of 2 to another integer.
4. Click OK at the bottom of the panel.


### Navigating between Tables in the Model Panel

The Model panel is a large area that can hold many tables. Only a portion of the Model panel is visible at any given time. You can adjust the visible area using the scroll bars or by the Navigator window.

### To navigate among the tables in the Model panel

1. Open the Navigator window by clicking the Navigator button.

The Navigator window opens, displaying a miniature version of the Model panel with all its tables in position.



After you first click in the Navigator window, a blue rectangle appears, showing what area is currently visible in the Model panel.

2. Click inside the blue rectangle and drag it over the area you want to see.

### Specifying the DISTINCT Query Option

You can easily add the DISTINCT option to the SQL query in the Model panel. This query option ensures that duplicate rows are ignored.

#### To specify the DISTINCT query option in the Model panel

1. Right-click anywhere in the Model panel.
2. Choose Select Distinct.

This selection adds **DISTINCT** to the view's **SELECT** statement, as in the following example:

```
SELECT DISTINCT
*
FROM
/shared/examples/ds_inventory/products products
```

3. Select the SQL panel and verify that the SQL statement now contains the **DISTINCT** option.

### Specifying Query Hints

Query hints are options that you can include to optimize your SQL statement for the TDV query engine. Options specified in a query override any defaults set using the configuration parameter values.

You can specify the following query hints for the current view in the Model panel:

- Set the maximum number of rows to be fetched
- Set case sensitivity
- Set whether or not to ignore trailing spaces
- Force the Query Engine to use disk instead of memory for temporary query data storage
- Require that mathematical and string functions adhere to SQL-92 (STRICT)

**Note:** Many other query options can be added directly in the SQL panel. These are documented in “TDV Query Engine Options” in the *TDV Reference Guide*.

### To specify query hints in the Model panel

1. Add however many tables you want in the Model panel.
2. Right-click anywhere in the Model panel, and select Query Hints.
3. In the Query Hints dialog box, specify the maximum number of rows to be fetched in the Max Rows Limit field.
4. Select one of the following options in the Case Sensitive drop-down list:
  - Server Default—Default setting of the server.
  - True—This option sets comparisons to case-sensitive mode.
  - False—This option sets comparisons to ignore case.
5. Select one of the following options in the Ignore Trailing Spaces drop-down list:
  - Server Default—Default setting of the server.
  - True—With this option, comparisons ignore trailing spaces.
  - False—With this option, comparisons do not ignore trailing spaces.
6. Select any check boxes that apply:
  - Force Disk—If selected, this option forces the query engine to use disk instead of memory wherever possible.
  - Strict—If selected, query engine does not push mathematical and string functions to the data source if the data source does not follow SQL-92 standards for those functions. This might affect performance.
7. Use the Clear All button if you want to clear all entries.
8. Click OK after setting the options.
9. Click the SQL tab to view the resulting options included in the SQL, as in the following example:

```

SELECT { OPTION MAX_ROWS_LIMIT="50", IGNORE_TRAILING_SPACES="True",
CASE_SENSITIVE="True", STRICT="true", FORCE_DISK="true" }
  DISTINCT products.ProductID,
         products.ProductName,
         products.UnitPrice
FROM /shared/examples/ds_inventory/products products

```

## Designing a View in the Grid Panel

The following sections describe Grid panel tasks. Drawing from the tables you added using the Model panel, use the **Grid** panel to select which columns to add:

- [Listing All Columns from a Table, page 148](#)
- [Adding an Individual Column, page 149](#)

After the columns have been added, you can use the Grid panel to refine column definitions, sorting order, and other attributes:

- [Creating an Alias for a Column, page 150](#)
- [Changing a Column Data Type using the CAST Function, page 150](#)
- [Including a Column in the ORDER BY Clause, page 150](#)
- [Specifying a GROUP BY Clause, page 151](#)
- [Specifying Criteria on a Column, page 151](#)
- [Including a Function in a SELECT or WHERE Clause, page 152](#)
- [Declaring a Variable in a SELECT Statement, page 152](#)

### Listing All Columns from a Table

You can list all columns from a table in the Grid panel. These tables are added to the `SQL SELECT` statement. You can refine their definitions using the Columns panel.

#### To add all columns from a table as rows in the Grid panel

1. Click the List Columns button.

The List Columns from Tables dialog box opens, displaying a field on the left showing the available tables, and a field on the right showing the tables you have selected.



2. You can move tables to the right side in one of two ways:
  - Click the double-headed arrow button to move all available tables to the right side.
  - Select one (or more, using Ctrl-click or Shift-click) of the available tables, and click the right-arrow button to move the selected tables to the right side.

You can move a table back to the left side by selecting it and clicking the left-arrow button.

3. Optionally, if you want to add all columns from tables even if they are already displayed in the Grid panel, uncheck the Skip Duplicate Columns check box.
4. Click OK.
 

Columns from the tables you selected are added to the bottom of the Grid panel listing. The view editor automatically creates aliases for identical column names, whether they came from the same table or different tables. You can select any alias on the Grid panel and type a new alias for the column.
5. Select the SQL panel and see that the **SELECT** statement now includes all of the columns you requested.

### Adding an Individual Column

You can add individual columns from a table, and then move it to the position you want on the Grid panel.

#### To add an individual column as a row in the Grid panel

1. Click the Grid tab to open the Grid panel.
2. Click an empty cell in the left column (the Column column).
3. When the cell becomes a bordered field, click the drop-down button on its right and select a table column from the list.

The list includes all columns from all tables in the model.

4. Optionally, clear the check box in the Output column to exclude the item from the view execution results.

**Note:** You can check or uncheck all check boxes in the Grid Output column at once, using the Select All Outputs or Clear All Outputs toolbar icons, respectively.

## Creating an Alias for a Column

You can supply an alias that is the column name that users see when they browse or query the TDV data services you create, so it is wise to assign an alias that makes sense to those users.

**Note:** If you specify a reserved word as an alias, it is enclosed in double quotes in the SQL statement. For a list of reserved words, see the *TDV Reference Guide*.

### To assign an alias to a column in the Grid panel

1. Click the cell under Alias that corresponds to the column item you want to give an alias.

The editor may have assigned an alias automatically. You can highlight it and type a new alias to replace it.

2. Type an alias for this column in the cell.

**Note:** Automatically generated SQL from some ODBC clients (Excel and others) needs to be modified if you intend to use the alias to query the data sources.

## Changing a Column Data Type using the CAST Function

Changing data types is sometimes necessary because the view might need to be consumed through a client interface that does not support that data type, or perhaps the data type defined in the data source is not optimal for your current needs.

### To declare a variable in a SELECT statement

1. Open any view.
2. Select the Grid tab.
3. Select any row with data.
4. Right click and select Function > Convert > CAST.
5. Click OK.

## Including a Column in the ORDER BY Clause

In the Grid panel you can add an **ORDER BY** clause to the SQL statement to sort the results by one or more columns, in ascending or descending order.

**Note:** If you choose sort order before you choose sort type, Unsorted is the only Sort Type option available.

You should not use OFFSET and FETCH in a TDV view.

### To include a column in the ORDER BY clause

1. Click the cell in the Sort Order column for the row, and select a number to indicate the order in which that column is to be sorted (1 for first, 2 for second, and so on).

**Note:** As you designate more rows, more sort-order numbers become available. If you specify the same number more than once, the editor assigns a distinct sort order number for the other row. Check that the assignments are what you want.

2. Click the cell in the Sort Type column for the row, and select Ascending, Descending, or Unsorted.

**Note:** If you want to remove a row from the ORDER BY clause, select Unsorted in the Sort By column.

3. Click the SQL tab to look at the resulting ORDER BY clause.

### Specifying a GROUP BY Clause

In the Grid panel you can group by an item, an expression, or a restriction involving aggregate functions.

#### To specify a GROUP BY clause

1. To group by an item, click the cell where the item's row crosses the Group By column and choose one of these options from the drop-down list:
  - None—to omit any GROUP BY clause.
  - Group By—to add a clause to GROUP BY the item in this row.
  - Expression—to group by an expression.
  - Having—to place restrictions (involving aggregate functions) on the rows returned from the GROUP BY clause.

### Specifying Criteria on a Column

You can combine multiple criteria in one row using OR logic. Criteria entered in different rows (vertically) are combined using AND logic. A column does not have to be included in the result set to have criteria associated with it.

For example, in an Order table with a total\_price column, if you want to retrieve large and small orders, you might enter >100 in the Criteria column, and <10 in the first Or column.

### To specify criteria on a column

1. To specify a criterion on an item, click the cell where the item's row crosses the Criteria column and enter the first criterion in the cell.
2. To specify more criteria on an item (up to a total of four) click the cell where the item's row crosses an *Or* column and enter the criterion in the cell.

### Including a Function in a SELECT or WHERE Clause

You can specify a function to include in a SELECT statement using a cell in the Column column for the item's row. You can specify a function to include in the WHERE clause of the SQL statement using a cell in the Criteria column for the item's row. The functions available are listed in "TDV Support for SQL Functions" in the TDV Reference Guide.

**Note:** The functions you can add include custom functions. See [Promoting Procedures to Custom Functions, page 191](#) for a description of how administrators can promote procedures, which then appear in the drop-down list of functions.

#### To include a function in a SELECT statement

1. Right-click the cell in the Column section, and select Function > <function type> > <function name>.
2. Specify the input arguments for the function, and click OK.

The function format is provided in the Function Arguments Input window. The function added in this way is included in the SELECT statement.

#### To include a function in a WHERE clause

1. Right-click the cell in the Criteria section, and select Function > <function type> > <function name>.
2. Specify the input arguments for the function, and click OK.

The function format is provided in the Function Arguments Input window. The function added in this way is included in the WHERE clause.

### Declaring a Variable in a SELECT Statement

The variables defined using the following steps are considered "virtual columns," and they are included in the SELECT statement. Virtual columns help to integrate views and procedures.

Typically, virtual columns are implemented in the following ways:

- As a range of values in the filter criteria
- As a single value so it can be used to call a procedure

**Note:** XML types are allowed. If you want to specify an XML schema, you must edit the SQL of the view directly and the declaration of your column needs to include the XML schema definition of that value. See the XML example that follows the steps.

### To declare a variable in a SELECT statement

1. Right-click a Column cell, and select Declaration.
2. In the Add Declaration window, in the Parameter Name field, supply a unique name for the variable.
3. Specify the type of the variable in the drop-down list.
4. In the Default Value field, specify the default value for the variable.
5. Click OK.

The value you defined should appear in the Column cell in the form:  
`{DECLARE <variable_column_name> <data_type> DEFAULT <default_value>}`

### Example of How to Modify the Declaration of the XML Virtual Column

To specify an XML schema, you must edit the SQL of the view directly and the declaration of your column needs to include the parts of the XML schema definition that are relevant for that value. After you edit the SQL of the view directly, you will not be able to edit your SQL model. The following shows the XML schema definition associated with a single virtual column:

```
{DECLARE Request_decl
XML(' {http://www.compositesw.com/example/transaction/orders/v1.0}Request', '<xs:schema
xmlns:xs="http://www.w3.org/2001/XMLSchema"
xmlns:ns1="http://www.compositesw.com/example/transaction/request/v1.0" attributeFormDefault="unqualified"
elementFormDefault="qualified" targetNamespace="http://www.compositesw.com/example/transaction/request/v1.0">
<xs:element name="Request">
  <xs:complexType>
    <xs:sequence>
      <xs:element name="ReqId" nillable="true" type="xs:int"/>
    </xs:sequence>
  </xs:complexType>
</xs:element>
</xs:schema>') DEFAULT NULL
}
{DECLARE inputXML_decl XML DEFAULT null} inputXML,
...
```

## Example that Uses Procedures

This example uses two views and the procedure that is distributed with the product.

### requires\_prod\_id View

-- This view requires that a single product ID to be specified, so it can be used to join with  
-- a lookup procedure.

```
SELECT
  a.ProductID,
  { DECLARE a_prod_id INTEGER } a_prod_id,
  a.ProductName,
  b.ProductDescription
FROM
  /shared/examples/ds_inventory/tutorial/products a INNER JOIN
  /shared/examples/LookupProduct(a_prod_id) b
ON a.ProductID = a_prod_id
```

### wrap\_prod\_id View

```
SELECT
  ProductID,
  a_prod_id,
  ProductName,
  ProductDescription
FROM
  /shared/DEMO/VirtualColumn/for_procedures/requires_prod_id
WHERE
  a_prod_id = 10
```

## Example that Uses a Range of Values

This example uses two views and a procedure.

### proc\_wrap\_prod\_id Procedure

```
PROCEDURE proc_wrap_prod_id(
  IN prod_id_begin INTEGER,
  IN prod_id_end INTEGER,
  OUT result CURSOR (
    OrderID INTEGER,
    ProductID INTEGER,
    Discount NUMERIC(12,2),
    OrderDate DATE,
    CompanyName VARCHAR(50),
    CustomerContactFirstName VARCHAR(30),
    CustomerContactLastName VARCHAR(50),
    CustomerContactPhone VARCHAR(30)
  )
)
BEGIN
  OPEN result FOR
  SELECT
    OrderID,
    ProductID,
```

```

Discount,
OrderDate,
CompanyName,
CustomerContactFirstName,
CustomerContactLastName,
CustomerContactPhone
FROM
    /shared/examples/ViewOrder ViewOrder
WHERE
(ProductID >= prod_id_begin)
and (ProductID <= prod_id_end)
;

END

```

### requires\_prod\_id View

```

SELECT
products.ProductID,
{ DECLARE prod_id_begin INTEGER } prod_id_begin,
{ DECLARE prod_id_end INTEGER } prod_id_end,
products.ProductName
FROM /shared/examples/ds_inventory/tutorial/products products
WHERE
(ProductID >= prod_id_begin)
and (ProductID <= prod_id_end)

```

### view\_wrap\_prod\_id View

```

SELECT
    ProductID,
    ProductName
FROM
    /shared/DEMO/VirtualColumn/range_of_values/requires_prod_id
where
prod_id_begin = 5
and prod_id_end = 15

```

## Designing SQL for a View in the SQL Panel

You can use the SQL panel in the view editor to type and edit a view's SQL. You can upload an existing SQL statement to use as a starting point using the Insert from File button.

**Note:** When you edit the SQL in the SQL panel, the design in the Model panel becomes invalid and the Model and Grid panels disappear. You can regenerate the model to redisplay the Model and Grid panels as described in [Generating a Model from the SQL Panel, page 159](#).

There are some limitations and considerations when editing the SQL:

- The SQL for a view cannot contain an INSERT, UPDATE, or DELETE clause. You have to include such clauses in a SQL script, as described in [Procedures, page 185](#)
- If you want to use the Model panel later for the current view, first save the SQL statement under a different name, and then use the SQL panel for your hand-typed SQL code.
- You are responsible for the syntax of the SQL you type in the SQL panel. Studio does not check the validity of the syntax.
- If table or column names contain special characters, such as @, \$, or &, enclose the names in double quotation marks (" ") in the query.
- You should not use OFFSET and FETCH in a composite view.

For details on the SQL features supported in TDV, see the *TDV Reference Guide*.

### To create or edit a view's SQL in the SQL panel

1. Click the SQL tab in the view editor.
2. Type the SQL code for your view.

You can do most standard editing tasks in the SQL panel. For a list of keyboard shortcuts, see [Studio Code Editing Keyboard Shortcuts, page 607](#).

3. Save the view.

**Note:** You can also save the current SQL using the Save to File button.

## Defining Primary Key for a View or Table in the Indexes Panel

In Studio, the Indexes panel in the view and table editors enables creation of metadata labels for existing indexes and primary keys already present in the data source. You can mark a column in a view as indexed or as a primary key.

Primary keys are similar to indexes. A column designated as a primary key signifies that every value in that column is unique. So when a column is made a primary key, not only is an index created for it, but typically the native data source ensures that every value in that column is unique and ensures this uniqueness for every update and insert.

Identifying indexes and primary keys enable the TDV Query Engine to use logical algorithms for faster more efficient joins that leverage organization of the data source.



### To define and publish an index

1. Open a view or table editor, and click the Indexes tab.
2. Click Add.
3. In the New Index window, supply a name for the index, and click OK.  
The index is listed along with the column projections in the view, as shown in the next screen.
4. Select the column for the index and click the right arrow button.  
You can add as many columns as you want. When you add columns to the index, you can see the synchronization between the list of available columns and indexed columns.
5. Select Unique or Primary Key box to indicate the type of the index.  
If you select Primary Key, the Unique box is automatically selected.  
A Unique index is used when you do not want duplicate values to be retrieved. The same is true of Primary indexes. However, in a table you can have only one index marked as Primary key, but you can have more than one index marked as Unique.
6. (optional) Use the Add button to mark more columns as indexes, and use the Remove button to delete any columns improperly marked as existing indexes.
7. Save the resource.
8. Publish the indexed resource to make the index available for external clients.
9. Open the system table ALL\_INDEXES (in Data Services/Databases/system).
10. Click Show Contents in the Columns tab to view the details of all the available indexes in the system.  
If you have published data source tables, the indexes on those resources would also be listed in ALL\_INDEXES.
11. Click a row in the Result panel output to view the result details. For some extremely large results, such as those generated by using EXTEND on an array to generate BIGINT number values, some of the data might be truncated without a visual indication by Studio.

### Defining a Foreign Key for a View or Table Resource

In a relational table, a foreign key is a column that matches the primary key column in another table. Suppose that column X in Table A relates to column Y in Table B and column Y is a primary key in Table B, the foreign key appears in Table A.

Foreign key relationships indicate that if you join  $A.X = B.Y$ , there is exactly one row in Table B found for each row in Table A. This information is a useful hint for join operations.

In Studio, the Foreign Keys panel in the view and table editor lets you create a definition that acknowledges and allows use of any foreign keys in the data source. For each foreign key you want to define, first you need to select the column that would be the foreign key, and subsequently identify the corresponding primary key column in the parent table.

The processes for defining a foreign key and testing the creation of a foreign key are as follows:

### To define a foreign key

1. Open a view or table.

The view used here has two tables—`orderdetails` and `orders`—from the data source `ds_orders (/shared/examples/ds_orders)`.

The projected columns are `orderdetails.ProductID`, `orderdetails.UnitPrice`, and `orders.ShippingMethodID`. See the Grid panel and Columns panels in the view editor.

2. Click the Foreign Keys tab in the editor to open the Foreign Keys panel.
3. Click the Add button (in the bottom left section of the editor).
4. In the input window that opens, type a name (for example, `FK_ProductID`) for the foreign key that you want to define, and click OK.

The columns that are available for you to mark up as a “foreign key column” are listed in the section Available Columns. These columns are exactly the same columns selected for projection in the view or table. See the Columns panel of the editor.

5. Select a column that you want to identify as a foreign key.

In this example, `ProductID` is selected.

Specify the parent table that contains the primary for this foreign key column. The parent table is also known as the referenced table.

6. Click the Browse button, and locate the parent table in which `ProductID` is the primary key.

In this example, the parent table is:

`/shared/examples/ds_inventory/products`

7. Use the forward arrow button to move `ProductID` from Available Columns to the Foreign Column section.

The columns in the Parent Table are displayed in a drop-down list in the Primary Column section, and the primary key column is visible.

8. Select the primary key column (ProductID) in the drop-down list (in the Primary Column section) and save the resource. Now, the view has a column (ProductID) identified as a foreign key.

Repeating this process, you can define as many foreign keys as you need.

### To test the creation of the foreign key

1. Publish the resource. For details on publishing, see [Publishing Resources, page 325](#). You can also verify that the foreign keys you defined are accessible to external client applications.
2. Open the system table /services/databases/system/ALL\_FOREIGN\_KEYS, and view its contents.
3. Right-click on:  
Data Services/Databases/system/ALL\_FOREIGN\_KEYS
4. Select Show Contents.

Or, open Data Services/Databases/system/ALL\_FOREIGN\_KEYS, and click Show Contents. The foreign keys you defined are listed in the Result panel.

## Generating a Model from the SQL Panel

If you have typed or changed the SQL statement in the SQL panel, you can generate a model based on the SQL currently displayed in that panel. The Model and Grid panels reappear in the view editor when you generate a model.

The model generator does not support all of TDV SQL syntax. SQL features the model generator does *not* support are as follows:

- UNION, INTERSECT, EXCEPT, EXISTS, scalar subqueries, derived tables, IN clause with a subquery, quantified subquery, and the INSERT, UPDATE, and DELETE operations.
- Error messages result for models generated from queries that include these SQL features.

In the regenerated model, the tables would be joined at the top (joining the table tiles), instead of at the appropriate columns, under the following circumstances:

- If the ON clause of the JOIN has one or more of the following items:
  - A function
  - an **OR** condition
  - Any of the following predicates: IN, LIKE, BETWEEN, IS NULL
- If the join is a self-join and no columns are involved in the join, or only columns from the same table are involved in the join.

The model generator accepts all INNER and OUTER JOINS. However, it might not be able to match the columns originating from the left and right sides of the join. When the model generator cannot identify both columns, the two tables in the resulting model are joined by a line that stretches from the title bar of the first table to the title bar of the second table.

### To generate a model from the SQL panel

1. Click the Generate Model toolbar button in the view editor's SQL panel.

Note: If Studio generated the SQL, the Generate Model toolbar button is not available.

## Working with Views and JSON

TDV and Studio support the use of the SQL JSON\_TABLE function. For more information about the SQL syntax, see the *TDV Reference Guide*.

The following sections describe using the JSON\_TABLE with examples:

- [Using a JSON Table Within a TDV View, page 160](#)
- [JSON Table Examples, page 161](#)

### Using a JSON Table Within a TDV View

When using the JSON\_TABLE syntax in a view, you can define the structure and the data.

#### To add and use a JSON table within a TDV View

1. Add the JSON\_TABLE SQL function with the data and structure definitions to the SQL tab of your view.

For example, the JSON table could have:

```
FROM JSON_TABLE({
  "company": {
```

```

"department": [
  {
    "DepartmentID": 1,
    "DepartmentName" : "Sales"
  },
  {
    "DepartmentID": 2,
    "DepartmentName" : "Project"
  },
  { "DepartmentID": 3,
    "DepartmentName" : "Market"
  },
  { "DepartmentID": 4,
    "DepartmentName" : "HR"
  }
]
}},
'$..company.department'

```

2. From within this view you can now use standard SQL functions to manipulate the composite view.

## JSON Table Examples

For example, the SQL for your entire view might resemble one or more of the following.

### View with a Literal JSON Table

```

SELECT
  columnName,
  columnValue
FROM JSON_TABLE('{
  "company": {"department": [
    { "DepartmentID": 1, "DepartmentName": "Sales" },
    { "DepartmentID": 2, "DepartmentName": "Project" },
    { "DepartmentID": 3, "DepartmentName": "Market" },
    { "DepartmentID": 4, "DepartmentName": "HR???" },
    { "DepartmentID": 5, "DepartmentName": "Service" },
    { "DepartmentID": 6, "DepartmentName": "Advertisement" }
  ]}
}')
```

\$..company.department'

COLUMNS(columnName VARCHAR(20) PATH KEY,columnValue VARCHAR(100) PATH VALUE)) JT

### View with a JSON Table and a Self-Join

```

SELECT
  two_references.customerId, two_references_1.price
FROM
  /shared/myViews/json/dynamic/reference_list/two_references two_references INNER JOIN
  /shared/myViews/json/dynamic/reference_list/two_references two_references_1

```

```
ON two_references.customerId = two_references_1.customerId
```

### View with JSON Table and Inner Join

```
SELECT
  literal_json_table_B.employeeName,
  literal_json_table_A.departmentID,
  literal_json_table_A.departmentName
FROM /shared/jsontable/literal_json_table_B inner JOIN
  /shared/jsontable/literal_json_table_A
  ON literal_json_table_B.departmentID = literal_json_table_A.departmentID
order by literal_json_table_B.employeeName
```

## Designing Column Projections Using the Columns Panel

If an external client must receive the data according to a particular external schema with specific data type projections, you can use the Design Mode check box in the Columns panel. The Design Mode check box lets you design a projection of a view, so that you can do a top-down design from the SQL panel.

When you use the Columns panel to design the projections, the SQL implementation is not automatically updated in the SQL panel. You must make sure there is a match between the columns defined in the SELECT statement of the SQL and columns you designed in the Columns panel using the design mode, including the order in which they are provided; otherwise, the query will generate an error when executed.

### To design column projections through the Columns panel

1. Open the Columns Panel in the view editor.
2. Check the Design Mode check box in the upper right corner.

Studio displays the warning below to let you know that changes you make to the Columns panel are not automatically made in the SQL panel which invalidates the SQL implementation; you must make the same edits in the SQL panel to ensure that the query works.

3. Highlight the row below which you want to add the column projection.
4. Click the Add button, and select a data type from the drop-down list.

A new row is created, with a default name and the selected data type for the new column projection.

5. Optionally, highlight the default column name and type a new column name.

6. If the data type needs to change, right-click the Type/Reference value for that row, select Change Type, and specify the correct data type for the column projection.
7. Edit the SQL to include your columns in the **SELECT** statement.

After you have specified all columns are specified in their result-set display order, you can use them in the SQL statement in the SQL panel. However, the SQL is not automatically updated to reflect the design you created in the Columns panel.

## Obtaining View Details

You can find out the details about a resource, such as its name, location in the resource tree, type and owner, and whether it is locked or not, using the Info tab.

### To obtain the details about a view

1. Click the Info tab in the view editor.
2. Annotations are shown in the tooltip displayed when the mouse cursor pauses over a resource in the Studio resource tree, helping identify what the resource represents.

## Executing a View

After you have designed and saved a view (refer to [Designing a View and Table Resource](#), page 138) you can execute its SQL from within Studio to see the result.

For executing a view's SQL through client applications, see *TDV Client Interfaces Guide*.

Executing a view might be affected if the view uses a data source that was originally added to TDV Server using the pass-through mode without saving the password. To execute such a view, you must log into TDV Server with the same login credentials (user name/password) that are necessary to log into the data source. For further information on pass-through credentials, see the details for the Save Password and Pass-through Login fields under [Adding a Data Source](#), page 70.

Executing a view from Studio is blocked if the view's SQL is **SELECT \*** on a view that includes a table with column-based security (see "About Managing Dependency Privileges" in the *TDV Administration Guide*).

**To execute a view from Studio**

1. Double-click the view to open it, or right-click the view. Select Open.
2. Click the Execute button.

The Result panel displays the first 50 rows (default) of view execution results.

3. Use the Load More Results button to view the next 50 rows.

## Generating a Query Execution (Explain) Plan

You can show the query execution plan instead of executing the query.

**To show a query execution plan from Studio**

1. Open a view.
2. Click the Show Execution Plan button.

The Execution Plan panel displays the query execution plan.

3. Scroll down to see more of the query execution plan.

## Generating an Explain Plan and Displaying it in a Client Application

An alternate to show a query execution plan is to precede the query with the keyword EXPLAIN. This feature can be used in Studio, although it is intended for use in JDBC/ODBC client applications. Being able to analyze the execution plans of a query in tools other than TDV can help you optimize your queries faster. The text results are retrieved in a result set that can be consumed by Studio or by your client application. The result set is one column of VARCHAR text.

The default column width of the execution plan is 100 characters. You can change it from Studio using the TDV Explain text width configuration parameter.

Option	Description	Example Syntax
<code>show_source_plan="true"</code>	Retrieves the query plan. This can also be used in the SQL Scratchpad.	<pre>explain select {option show_source_plan="true"} * from &lt;view&gt;</pre>
<code>show_runtime="true"</code>	Retrieves the execution statistics (plan and runtime statistics). This can also be used in the SQL Scratchpad.	<pre>explain select {option show_runtime="true"} * from &lt;view&gt;</pre>



**To explain a query execution plan within your client application**

1. Use your client application to connect through JDBC or ODBC to TDV.
2. Navigate to the TDV table or view with the query you want to analyze.
3. In the SQL editor for that query, type EXPLAIN before the query. For example:  

```
explain select * from emp;
```
4. Run the query.
5. Review the explain plan to determine how to optimize the query.

**To explain a query execution plan within Studio**

1. Open a view.
2. In the SQL Scratchpad, add the keyword EXPLAIN before the query.
3. Click the Execute button.

The Result panel displays the view's query execution plan (rather than the view's execution results). The actual view is not executed.

4. Use the Load More Results button to view the next 50 rows of the plan.

## Rebinding a View

A view depends on one or more underlying sources, and the view is considered bound to those underlying sources. A view can be bound to tabular data or a procedure. Rebinding is useful when:

- You create a view with its sources and later decide to rebind the view to different sources.
- An execution error has occurred for a view because a source with which the view was initially bound does not exist any more.

**To rebind a view to a different source**

1. Open the view.
2. Click the Show Rebind Panel button on the Studio editor toolbar.

The Rebind panel opens in the lower part of the view editor panel and displays the dependencies as determined the last time it was saved.

If a view has never been saved, the rebind window is empty.

3. In the Rebind panel, select the source from the list in the left pane.
4. Click the Rebind button.

The Rebind window appears, displaying the resources available for binding.

5. In the Rebind window, specify the source with which you want to rebind the view, and click OK.
6. Save the view.

If you modify the view or its dependencies, the binding is automatically updated when you save the view, and the Rebind panel reflects the change. For example, if your view has a data source dependency named `ds_orders`, and you rename it `ds_orders_renamed` and save the view, the Rebind panel lists the dependency as `ds_orders_renamed`.

For details on a view's lineage and dependencies, see [Displaying the Lineage of a View, page 166](#).

## Displaying the Lineage of a View

When you are working on a complex query, it is useful to know what resources are involved so you can understand the query's relationships to other resources. The relationships displayed include the resources on which the view depends and any resources that depend on the view. The Lineage panel in Studio shows a view's lineage. The Lineage panel is also available for cached views as well as other resource types. See [Exploring Data Lineage, page 371](#), for more information.


### To display the lineage of a view

1. Open the view and click the Open Lineage Panel toolbar button. For OLAP Views this button is on the SQL tab of the editor.

**Note:** You can also display the lineage for the view by right-clicking a view in the resource tree, and selecting Open Lineage. A new tab opens in the Studio workspace. This method of displaying the view lineage provides more space and is useful if your view has many resources.


The Lineage panel opens in the lower section of the view's editor and displays all the resources involved with the view in a graphical format. The following

screen shows the resources (data sources and tables) on which the sample view ViewOrder depends and the resources that depend on this view.



In the graphical format, the view's dependencies are shown on its left and the resources that depend on it are shown on its right.

2. Select any resource in the Lineage panel to see details about the resource in the right pane. For example, select a table in a view to display the SQL used to generate that view with the selected table highlighted.



3. Use the buttons at the top of the Lineage panel to adjust the display. See [Lineage Panel Buttons and Controls](#), page 373 for more information.

See [Working with the Data Lineage Graph](#), page 376 for more information about the Lineage panel.

## View Column Dependencies and References


TDV provides API tools for you to ascertain the data lineage of the resources involved in a query. You can determine:

- Column dependencies—How the columns are derived from a specified composite view and going back one or more levels through the various resources on which the view depends. You can find out what resources are involved and what transformations might have occurred that affect the results. See [Getting Column Dependencies Using the API](#), page 169, for more information.
- Column references—What resources directly depend on that column. You can find out what other views refer to a specific column in a table or view. See [Getting Column References Using the API](#), page 175, for more information.

## Getting Column Dependencies Using the API


TDV provides a system procedure that you can use against a specified composite view to get its column dependencies, discover where the data comes from, and see how it is derived. The data can come from many different resource types and paths including tables, views, procedures, packaged queries, delimited files, and Web service operations. Some of these possibilities are illustrated here:

Data Lineage—Column Dependencies




If the view depends on a procedure, web service, or packaged query, that is the end of the dependency analysis for that data. No further analysis is done through a procedure, web service, or packaged query.

After you request the column dependencies for a view, the GetColumnDependencies procedure results tell you, for each column in the view, what data source originated the data and what views transformed or filtered the data as shown in this example:



In this example, the column lineage data results might be as shown here:

### Column Lineage Examples



The GetColumnDependencies procedure lets you:

- View the resources involved in creating column results going all the way back to the data source or procedure.
- Find out which columns have been transformed and how.
- Find out which columns are not transformed.
- Discover the original data source type.
- Find out which columns involve constants.
- See who originally created the resources involved and when.
- Create views on top of the procedure to analyze and aggregate data source information.
- Publish the GetColumnDependencies procedure:
  - As a new Data Service. You can then access it with the supported protocols like JDBC, ODBC, ADO.NET.
  - As a new Web service which you can access using REST, SOAP, and the other supported protocols.

### To get the column dependencies for a view

1. In Studio, open the view containing the columns you want to learn about.
2. Click the Info tab and copy the full contents of the Name field which is the path for the view.
3. In the localhost directory, navigate to the lib/resource folder and open the GetColumnDependencies procedure.
4. Click Execute. Studio prompts you to enter the input parameters for this procedure.
5. Paste the view pathpathname copied earlier into the resourcePath field.
6. Enter the other input values for the procedure as shown in the table.

#### Parameter

#### Value Description

resourcePath	Required Enter the path of the resource to be analyzed. The supported resource types are TDV SQL Views in plain or published form.
--------------	---

Parameter	Value Description
columnFilter	Optional. Specify if the column lineage results should be filtered. If empty, no filtering occurs. To filter the results, enter a comma-separated sequence of case-insensitive column names, indicating the columns whose dependencies should be analyzed.
ignoreCaches	Optional. Specify if the analysis should ignore whether depended resources are cached or not. Enter one of these values:  true—Do not return any caches as part of the column lineage.  false—The default. If blank or false, any existing caches in the column lineage are returned in the procedure results.
recursively	Optional. Specify if the analysis should be done recursively all the way to the source level of dependency or only return one level of dependency. Enter one of these values:  true—Return all levels of dependencies down to the original source level.  false—The default. If blank or false, return only a single level of column dependency.

The analysis is done based on the view definition, independently of whether the view is cached or not.

7. Click OK.

TDV executes the procedure and displays the column dependencies in the lower Result For columnDependencies panel.

The contents of the columns are described below:


Column	Description
columnName	The name of the resource column having the column dependency encoded in the row.
dependencyDataSourcePath	The path to the data source containing the resource owning the dependency. Empty if not applicable.
dependencyDataSourceType	The type of the data source containing the resource owning the dependency. Empty if not applicable.
dependencyResourcePath	The path to the resource owning the dependency. Empty if not applicable.



Column	Description
dependencyResourceType	<p>The type of the resource that owns the dependency. Empty if not applicable.</p> <p>The set of data source types consists of all the data source adapter names accepted by TDV.</p> <p>The table and procedure resource types accepted by TDV is as follows:</p> <ul style="list-style-type: none"> <li>Database Table</li> <li>Delimited File</li> <li>Excel Table</li> <li>TDV SQL View</li> <li>System Table</li> <li>SAP RT Table</li> <li>SAP RFC Table</li> <li>SAP AQ Query Table</li> <li>SAP InfoSet Query Table</li> <li>Siebel Table</li> <li>Database Stored Procedure</li> <li>Packaged Query</li> <li>Java Procedure</li> <li>Web Service Operation</li> <li>Composite SQL Script Procedure</li> <li>XQuery Procedure</li> <li>Transform Procedure</li> <li>Basic Transform Procedure</li> <li>Stream Transform Procedure</li> <li>XQuery Transform Procedure</li> <li>XSLT Transform Procedure</li> </ul>
dependencyIdentifier	The column name if the dependency is on a column; otherwise, a literal.
dependencyKind	<p>One of the following:</p> <ul style="list-style-type: none"> <li>• column, to indicate a dependency on a column.</li> <li>• literal, to indicate a dependency on a constant value.</li> <li>• parameter, to indicate a dependency on a dynamic value provided at runtime.</li> </ul>

Column	Description
derivationKind	One of the following: <ul style="list-style-type: none"> <li>direct, to indicate that the value of the dependency is preserved by the dependent column</li> <li>indirect, to indicate that the value of the dependency is transformed by the dependent column</li> </ul>
cardinalityInfo	When applicable, one of the following: <ul style="list-style-type: none"> <li>aggregate, to indicate that an aggregate function is involved in the derivation of the dependent column</li> <li>analytic, to indicate that an analytic function is involved in the derivation of the dependent column</li> </ul>
derivations	When the dependent column is not a direct projection of the dependency, this field denotes how the dependent column is derived.

- To view the details of the column dependency, select a dependency and click the Details button in the Result For columnDependencies panel. Studio displays the full details for the selected column dependency as shown in this example:




- Optionally, save the results as a Comma-Separated Values (\*.csv) file by clicking Save to File on the Result For columnDependencies panel.

- Optionally, open any of the involved resources to see who originally created the resource and when on the resource Info tab.

## Getting Column References Using the API

TDV provides a system procedure that you can use to get column references and discover what views and columns directly reference a specified view column.

This procedure can be executed on a data source table or composite view to understand what upstream references each column in the table or view has. Only one reference level at a time is returned, but you can run the `GetColumnReferences` procedure repeatedly to discover the path of the references.



The `GetColumnReferences` procedure lets you:

- List all views and columns that directly reference a view.
- See the type of reference which might be a `SELECT` clause, a `FROM` clause, a `WHERE` clause, or a `TIMESERIES` clause, or other type of reference.
- See if the column was transformed.
- See who originally created the resources involved and when.

- After you have determined the column reference, you can run the GetColumnReferences procedure again on the referenced view or table to determine the next level of reference.
- Publish the GetColumnReferences procedure:
  - As a new Data Service. You can then access it with the supported protocols like JDBC, ODBC, ADO.NET.
  - As a new Web service which you can access using REST, SOAP, and the other supported protocols.

### To get the column references for a view

1. In Studio, open the data source table or view containing the columns you want to learn about.
2. Click the Info tab and copy the full contents of the Name field which is the path for the view.
3. In the <localhost> directory, navigate to the lib/resource folder and open the GetColumnReferences procedure.
4. Click Execute. Studio prompts you to enter the input parameters for this procedure.
5. Paste the table or view pathpathname copied earlier into the resourcePath field.
6. Enter the other input values for the procedure as follows:

Parameter	Value Description
resourcePath	Required. Enter the path of the resource to be analyzed. The supported resource types are TDV SQL Views or data source tables.
columnFilter	Optional. Specify if the column lineage results should be filtered. If empty, no filtering occurs. To filter the results, enter a comma-separated sequence of case-insensitive column names, indicating the columns whose references should be analyzed.

Note: The analysis is done ignoring whether the specified view or table is cached or not.

7. Click OK.

TDV executes the procedure and displays the column references in the lower Result For columnReferences panel.

The contents of the columns are described in the following table.

Column	Description
columnName	The name of the resource column having the column reference encoded in the row.
referentResourcePath	The path to the resource containing the column reference. Empty if not applicable.
referentContext	<p>The context in which the column is referenced:</p> <ul style="list-style-type: none"> <li>• In a WITH clause, to indicate a reference within a WITH clause.</li> <li>• In a SELECT clause as output, to indicate a reference that is projected by a SELECT clause.</li> <li>• In a SELECT clause as input, to indicate a reference that is used, but not projected, by a SELECT clause.</li> <li>• In a FROM clause, to indicate a reference within a FROM clause.</li> <li>• In a WHERE clause, to indicate a reference within a WHERE clause.</li> <li>• In a TIMESERIES clause, to indicate a reference within a TIMESERIES clause.</li> <li>• In a GROUP BY clause, to indicate a reference within a GROUP BY clause.</li> <li>• In a HAVING clause, to indicate a reference within a HAVING clause.</li> <li>• In an ORDER BY clause, to indicate a reference within an ORDER BY clause.</li> </ul>
referentColumnName	The name of the referent column. Populated only if referenceContext is in a SELECT clause as output; otherwise, empty.
derivationKind	<p>Indicates the type of derivation:</p> <ul style="list-style-type: none"> <li>• Direct, to indicate that the value of the dependency is preserved by the dependent column.</li> <li>• Indirect, to indicate that the value of the dependency is transformed by the dependent column.</li> </ul> <p>Populated only if referenceContext is in a SELECT clause as output; otherwise, empty.</p>

Column	Description
cardinalityInfo	<p>When applicable, one of the following:</p> <ul style="list-style-type: none"> <li>Aggregate, to indicate that an aggregate function is involved in the derivation of the dependent column.</li> <li>Analytic, to indicate that an analytic function is involved in the derivation of the dependent column.</li> </ul> <p>Populated only if referenceContext is in a SELECT clause as output; otherwise, empty.</p>
reference	A textual representation of the column reference.

- To view the details of a column reference, select the reference and click the Details button in the Result For columnReferences panel. Studio displays the full details for the selected column reference.
- Optionally, run the GetColumnReferences procedure again on the referenced view or table in the Result For columnReferences panel to determine the next level of reference.
 

You can run the GetColumnReferences procedure as many times as needed to discover the reference path.
- Optionally, save the results as a Comma-Separated Values (\*.csv) file by clicking Save to File on the Result For columnReferences panel.
- Optionally, open any of the involved resources to see who originally created the resource and when on the resource Info tab.

## Creating a View from a Cube

These objects are only valid if you have the SAP BW adapter installed. For more information on defining and using this type of Studio resource, see the *TDV SAP BW Adapter Guide*.

## Ad Hoc SQL and the SQL Scratchpad Editor

TDV provides an ad hoc SQL editor a SQL Scratchpad editor that let you execute “anonymous” SQL statements that are not bound to a resource. You can define and execute any SQL statements that can be executed for a composite view.

Ad hoc SQL content and history are saved on the local (Studio instance) machine, and retrieved in the following Studio session.

These topics are covered:


- [Opening the SQL Scratchpad Editor, page 179](#)
- [Composing and Executing an Ad Hoc SQL Query, page 180](#)
- [The SQL Scratchpad History Pane, page 181](#)
- [The SQL Scratchpad Result Panel, page 182](#)

### Opening the SQL Scratchpad Editor

There is only one instance of the SQL Scratchpad editor. If it is already open but not the active editor, any of the three methods listed below makes it the active editor by bringing it to the front.

**You can open the SQL Scratchpad from the Studio Modeler panel in one of three ways:**

- From the Studio menu bar, select File > Show SQL Scratchpad.
- On the Studio toolbar, click the Show SQL Scratchpad button.
- Press Ctrl+Q anywhere in the Studio window.



The short bar to the right of the status bar indicates the current line and column position of the cursor, separated by a colon. For example, 1:31 indicates that the cursor is on line 1, column 31.

**You can type queries in the work area and add resources to the queries by:**

- Typing the paths and names of the resources
- Dragging the resources from the Studio resource tree and dropping them onto the work area
- Using the Add Resources button

The following table describes the actions you can perform in the SQL Scratchpad Editor toolbar.

Label	Use to...
Execute	Execute the SQL query currently displayed in the panel and opens the Result panel ( <a href="#">The SQL Scratchpad Result Panel, page 182</a> ) below it, showing up to 50 rows of results. Each time you execute a unique SQL query, it is moved to the top of the list in the History panel.
Export to File	Open a dialog box to save the SQL query as a file.
Import from File	Open a dialog box to import a SQL query from a file.
Add Resources	Open a window where you choose a resource to add to the SQL Scratchpad editor.
Format Query	Format the SQL text according to the settings made on the Editors tab of the Studio Options window.
Toggle Syntax Highlighting	Change between displaying all SQL text in the same font color (usually black) and displaying comments, keywords and literals in the colors you selected in the Editors tab of the Options dialog box.
Show/Hide History View	Display or hides a History pane along the right side of the SQL Scratchpad editor. (See <a href="#">The SQL Scratchpad History Pane, page 181</a> ).
Show Option Dialog	Open the Studio Options window to the SQL Scratchpad tab, where you can change the options for this window.

## Composing and Executing an Ad Hoc SQL Query

This section describes how to create a new ad hoc SQL query in the SQL Scratchpad editor.



### To create and execute an ad hoc SQL query


1. Open the SQL Scratchpad editor.  
See [Opening the SQL Scratchpad Editor, page 179](#) for the three ways you can do this.
2. In the main scratchpad area, type your query.
3. Click the Execute button.

After you click the Execute button, a Result panel (see [The SQL Scratchpad Result Panel, page 182](#)) appears and shows query execution in progress and the results returned. You can dismiss the Results panel by clicking the Delete button on the right side of its tab.

**Note:** If you precede the SQL query with the keyword EXPLAIN, the Result panel displays the query execution plan. In this case, the query is not executed; rather, the plan is formulated and displayed for the user to examine. This plan text is also available to JDBC and ODBC clients.

### The SQL Scratchpad History Pane

If you click the Show History View button, a History pane appears on the right edge of the SQL Scratchpad editor, listing the SQL queries that you have created or changed in this window.



The History pane lets you:

- See the distinct queries you have executed. The history list retains the number of queries you specify in the Studio Options window, with the most recently used query at the top.
- Instantly display a previous query in the work area.
- Save all distinct queries automatically.
- Lock a query so it cannot be deleted.

You can Alt-click an unlocked query in the history list to lock it. You can lock as many queries as you want.

When a query is locked, a lock icon appears next to it. Locked queries do not count toward the Maximum History Size set in the Studio Options window.

- Unlock a query so it can be deleted. Alt-click a locked query in the history list to unlock it.
- Delete a selected query from the history list (after unlocking it, if necessary).
- Change the maximum number of queries to save in the history list. Click Maximum History Size in the Studio Options window and choose a number from the drop-down list.

Changes to maximum history size do not take effect until you restart Studio.

## The SQL Scratchpad Result Panel

The Result panel appears in the bottom area of the SQL Scratchpad editor when you click the Execute button on the toolbar. The Result panel displays up to 50 lines of execution results. If more than 50 lines were returned, you can see more of them by clicking the Load More Results button.

The table below describes the buttons and the actions you can perform in the Result panel toolbar. The Cancel button appears in the Result panel during execution of long queries, letting you halt execution. When you close the Result panel, any query execution in progress is canceled.

You can dismiss the Result panel by clicking the Delete button on its tab.

Label	Use to...
Save To File	Open a dialog box to save the results as a file. The default file type is a comma-separated values file (*.csv).
Details	Open a Result Details window that lists all of the column headings and values for the selected row. Click Next to list details for the next row, or Prev to list details for the previous row. To dismiss the window, click OK.

Label	Use to...
Load More Results	Load the next rows (up to 50) of the result. If 50 or fewer results were returned, this button is dimmed.
Clear	Clear all results from the Result panel.
Show Execution Plan	Open a tab, next to the Result tab, that shows the execution plan for the SQL executed.

If you click Show Execution Plan on the Result tab, an Execution Plan opens adjacent to the Results tab. The Execution Plan tab shows the execution plan and details for the SQL executed. The execution ID is shown on both tabs, so that the two can be correlated. An Execution Plan tab to the left of a Result tab indicates a stale plan.



# Procedures

---

This topic describes how to design procedures to query and manipulate data stored in a data source. It also describes transformations and how to use them to map your data into different formats.

- [About Procedures, page 185](#)
- [Creating a SQL Script Procedure, page 186](#)
- [Working with SQL Scripts, page 188](#)
- [Java Procedures, page 195](#)
- [XQuery Procedures, page 196](#)
- [XSLT Procedures, page 200](#)
- [Packaged Queries, page 203](#)
- [Parameterized Queries, page 212](#)
- [Physical Stored Procedures, page 217](#)
- [Using Stored Procedures, page 222](#)
- [Executing a Procedure or Parameterized Query, page 224](#)
- [Using Design Procedure By Example for Introspected Procedures, page 229](#)

Transformations are a special class of procedures. For more information about working with transformations, see [Using Transformations, page 231](#).

## About Procedures

Procedures are predefined programs that can be executed to query and manipulate data stored in a data source. They have scalar input and output parameters. Some of them return one or more cursors, which represent tabular output data.

TDV supports the following types of procedures.

Procedure Type	Further Information
SQL scripts	<a href="#">Working with SQL Scripts, page 188</a>
Custom Java procedures	<a href="#">Java Procedures, page 195</a>

Procedure Type	Further Information
Packaged queries	<a href="#">Packaged Queries, page 203</a>
Parameterized queries	<a href="#">Parameterized Queries, page 212</a>
Physical stored procedures	<a href="#">Physical Stored Procedures, page 217</a>
Transformations	<a href="#">Using Transformations, page 231</a>

Although different languages (TDV SQL script, Java, SQL native to data sources, XSLT, XQuery) are used to formulate procedures, they all function alike in the TDV system. You can invoke one procedure type from within another.

You can use any text editor to write a procedure, and use Studio to add it to the server. You can also use Studio's procedure editor to create and edit any type of procedure, except Java procedures. You can add a procedure to any location except Data Services in the resource tree. For details, see [Locating a Container for a TDV Resource, page 42](#).

For details on creating or adding procedures, see:

- [Creating a SQL Script Procedure, page 186](#)
- [Adding a Custom Java Procedure, page 163](#)
- [Java Procedures, page 195](#)
- [Creating a Packaged Query, page 204](#)
- [Quick Steps for Creating a Parameterized Query, page 212](#)
- [Creating an XML, XSLT, or Streaming Transformation, page 234](#)
- [Creating an XQuery Transformation, page 240](#)

For a description of how to move a procedure to a Data Services container, or if you want to make a procedure available to client programs or as a Web service, you must publish that procedure. For details, see [Publishing Resources, page 325](#).

## Creating a SQL Script Procedure

This section describes how to create a SQL script—a procedure written in TDV's SQL script language, as described in "TDV SQL Script" in the *TDV Reference Guide*.

The parameters you define in the SQL script panel must match the parameters that you define in the Parameters panel, including the order in which they are defined.

### To create a SQL script

1. Right-click the container to which you want to add the script, and select New SQL Script.

2. Type a name for the script in the Input dialog, and click OK.

The editor opens in the My SQL Script panel on the right.

For information about the procedure editor, see:

— [Procedure Editor Panel Reference, page 613](#)

3. Use the SQL Script panel to formulate and edit the SQL script.

- You can use any non-declarative statement as the first statement after BEGIN.
- The first non-declarative statement after BEGIN must not end with a semicolon (;), but every other statement must end with a semicolon.
- If you have a script stored in your file system, you can upload it using the Insert from File button.
- Type the script between the lines BEGIN and END.
- The SQL Script panel can highlight SQL syntax elements (comments, keywords, and so on). You can turn highlighting on and off with the Toggle Syntax Highlighting toolbar button. To change highlighting, select Edit > Options in the main toolbar and open the Editors tab.
- Drag and drop tables, views, or other procedures from the Studio resource tree into the procedure editor panel. This action inserts the full TDV resource name at the drop point.
- Insert standard SQL or C-style comments by highlighting one or more lines and typing:
  - Ctrl-Hyphen to insert two dashes (--) at the start of each line.
  - Ctrl-/ (forward-slash) to enclose the lines between /\* and \*/.

See [Commenting SQL, page 136](#) for information about inserting comments into SQL in TDV.


- Keywords can be used in a SQL script, as long as you enclose them in double quotes; for example:

```
SELECT "begin" INTO ...
```

— If you want to do an INSERT, UPDATE, or DELETE operation, you must include the INSERT, UPDATE, or DELETE statement in a SQL script.

4. Save the script.

Here is a sample SQL script. Note the error messages, and the row number and character position fields at the bottom of the panel (separated by a colon).



```

PROCEDURE LookupProduct (
  IN desiredProduct INTEGER,
  OUT result CURSOR (
    ProductName VARCHAR (50),
    ProductID INTEGER,
    ProductDescription VARCHAR (255)
  )
)
BEGIN
  OPEN result FOR
  SELECT
    products.ProductName,
    products.ProductID,
    products.ProductDescription
  FROM
    /shared/examples/ds_inventory/products products
  WHERE
    products.ProductID = desiredProduct;
END

```

5. See these sections for more information:

- For more information about working with the SQL script, see [Working with SQL Scripts, page 188](#).
- For information on how to define caching for your procedures, see [TDV Caching, page 391](#).
- For details on executing a SQL script, see [Executing a Procedure or Parameterized Query, page 224](#).

## Working with SQL Scripts

As part of creating a SQL script, you might also want to do the following:



- [Designing Parameters for a SQL Script, page 189](#)
- [Promoting Procedures to Custom Functions, page 191](#)
- [Pushing a Custom Function to the Native Data Source, page 192](#)
- [Using Pipes and Cursors, page 194](#)

## Designing Parameters for a SQL Script

If you want to create a script by first designing its parameters, you must design the parameters in the [Parameters Panel, page 617](#) and then write a procedure in the SQL Script panel.

**Note:** If a SQL script has an array as an input parameter, you can supply the input value when executing the script in Studio.

The Design Mode, which you use in this procedure, lets you formulate the input/output parameters for a procedure.

For more on SQL script execution, see [Executing a Procedure or Parameterized Query, page 224](#).

### To design the parameters for a SQL script in the Parameters panel

1. Create a new SQL script as described in [Java Procedures, page 195](#).
2. Select the Parameters tab.
3. Check the Design Mode check box at the top right to make the Parameters panel editable.

Studio displays a Design Mode Notes dialog box.

The Design Mode check box lets you do a top-down design from the Parameters panel.

When you use the Parameters panel to design the interface, the SQL implementation is not automatically updated in the SQL Script panel. You must make sure there is a match between the definitions in the SQL Script panel and the definitions in the Parameters panel using the design mode, including the order in which they are provided; otherwise, the script will generate an error when executed.

4. Review the warning and click OK.
5. Click the Add button to start adding parameters, and select a data type.

When you click Add and select a data type, a new parameter is added with a default name and the specified data type.

Supported data types are:

- Binary—BINARY, BLOB, VARBINARY
- Decimal—DECIMAL, DOUBLE, FLOAT, NUMERIC
- Integer—BIGINT, BIT, INTEGER, SMALLINT, TINYINT
- String—CHAR, CLOB, LONGVARCHAR, VARCHAR
- Time—DATE, TIME, TIMESTAMP
- Complex—CURSOR, XML

The Browse option is for choosing a definition set. See the topic [Definition Sets, page 297](#), for details on definition sets.


6. Right-click the parameter name, choose Rename, and type the new name.
7. Optionally, change a parameter's data type:
  - a. Right-click the data type name and select Change Type.
  - b. Right-click the parameter name or data type, and select a data type from the drop-down list.
  - c. Optionally, specify the length or the number of digits for certain data types.
  - d. Click OK.
8. Select the parameter, and click Cycle I/O Direction to indicate whether the parameter is input, output, or both.

The Cycle I/O Direction button is not available for parameters that are part of a cursor.

9. Use the navigation buttons to move a parameter up, down, left, or right.

The up and down navigation buttons are enabled when there is more than one parameter.

The left navigation button is enabled for a CURSOR parameter. The right navigation button is enabled for a parameter in a row immediately after the last parameter in a CURSOR.



10. After specifying all of the parameters you want to define, save the edits.
11. In the SQL Script panel, complete the procedure using the parameters designed in the Parameters panel.
12. Save the script.

After the parameters in the design match the parameters in the script on the SQL Script panel, the name of the script is displayed in black.

## Promoting Procedures to Custom Functions

You can use a procedure with scalar output (that is, a procedure that returns a single value; it can have zero, one, or multiple inputs) to directly manipulate data as part of a SELECT statement, or as a criterion in a condition. (See [Including a Function in a SELECT or WHERE Clause, page 152](#).) To use a procedure in this way, you promote it to a custom function.

**Note:** To *promote* a saved procedure is to add it to the drop-down list of custom functions in the Studio user interface, using the procedure described below.

An administrator can promote any SQL script or transformation using the Administration > Custom Functions menu option in Studio.

**Note:** A custom function cannot be rebound.

### To promote a procedure to a custom function

1. Log in as the administrator, or have the administrator perform these steps for you.
2. Locate and open a SQL script. Make sure it has exactly one scalar output.
3. In Studio, use the Administration > Custom Functions menu.  
If the number of candidate SQL scripts is large, it might take Studio a while to prepare the list.
4. If you want to narrow the list, type a string in the Find field and click Search.  
To view the full list again after a search, clear the string from the Find field and click Search again.
5. Select the procedure to promote to a custom function.
6. Click OK.

This function will now be available for a view as a custom function.

## Pushing a Custom Function to the Native Data Source

You can force a custom function to be executed by the native data source rather than by the TDV query engine. For a description of the types of SQL scripts that can be made into custom functions, see [Promoting Procedures to Custom Functions, page 191](#).

To promote a SQL script to a custom function that is always pushed to a native data source, you use the Native Only check box, as described in the procedure below.

**Note:** The TDV query engine might push a custom function to the data source even without your checking the Native Only check box. The check box is available to guarantee that the custom function is pushed.

### To push a custom function to the native data source

1. Log in as the administrator, or have the administrator perform these steps for you.
2. Locate and open a SQL script with one scalar output and check the Native Only check box.
3. In Studio, use the Administration > Custom Functions menu.  
If the number of candidate SQL scripts is large, it might take Studio a while to prepare the list.
4. Select the procedure to promote to a custom function.

5. Click OK.
6. Determine which adapter file you want to modify using the following guidelines and tips:
  - Changes made under `/conf/adapters` remain after applying hotfixes, and are included in any CAR file.  
This is true for `/conf/adapters/custom` and `/conf/adapters/system`.
  - Changes made to system adapters under `/conf/adapters/system` might require slightly more editing. For example, for Oracle you would need to define a `<common:attribute> </common:attribute>` for 11g.

**Note:** If you want a custom function to be pushed to *all* versions of a data source, add the name and signature of that custom function to the “generic” capabilities file for that data source.

  - Changes should not be made under `/apps/dlm`.
  - You can choose to create a custom adapter to manage your customizations, but if you are adding missing capabilities it might not be recommended.
7. Locate the capabilities file to customize.

For example, to add a custom function, `ss10`, intended for a custom Netezza data source, open the file:

```
<TDV_install_dir>\conf\adapters\system\<netezza_ver>\<netezza>.xml
```

8. From a text editor, open and add XML with the name, type, value, and configID of the custom function. For example, to add custom function `ss10`, add XML similar to this:

```
<common:attribute xmlns:common="http://www.compositesw.com/services/system/util/common">
  <common:name>/custom/ss10(~string,~string)</common:name>
  <common:type>STRING</common:type>
  <common:value>ss10($1,$2)</common:value>
  <common:configID>ss10(~string,~string)</common:configID>
</common:attribute>
```

9. Restart the TDV Server.

The custom function, when invoked, will be pushed to the native data source for execution. For example, when `ss10` is invoked in a SQL statement that includes, a Netezza table, the function will be pushed to the Netezza data source for execution.

## Using Pipes and Cursors

Pipes and cursors can be used separately or in combination to solve a variety of challenges within TDV. They are useful when some preprocessing needs to be done to complex data—for example, stripping out rows where the condition is difficult to express in SQL, or returning a flattened row from an XSLT transformation on an XML JMS message.

### Pipes

A pipe is a cursor that can have data inserted into it from many sources. TDV only sees pipes as OUT parameters for a procedure. You can use INSERT statements to get the data into the pipes for processing. For example:

```
PROCEDURE q(OUT name VARCHAR)
BEGIN
DECLARE c CURSOR (name VARCHAR);
CALL /shared/rtnPipe(c);
FETCH c INTO name;
END
```

### Cursors

For TDV, a cursor is a result set returned from a single data source. A cursor can be thought of as a pointer to one row in a set of rows. The cursor can only reference one row at a time, but can move to other rows of the result set as needed.

Cursors can be used to perform complex logic on individual rows.

To use cursors in SQL procedures, you need to do the following:

- Declare a cursor that defines a result set.
- Open the cursor to establish the result set.
- Fetch the data into local variables as needed from the cursor, one row at a time.
- Close the cursor when done.

### Static Cursor Example

```
DECLARE <cursor-name> CURSOR FOR <select>;
```

### Dynamic Cursor Example

```
PROCEDURE p(OUT p_name VARCHAR)
BEGIN
DECLARE c CURSOR (name VARCHAR);
OPEN c FOR SELECT name FROM /shared/T;
FETCH c INTO p_name;
```

```
CLOSE c;
END
```

The dynamic cursor can be reopened:

- With the same query or a different query
- Only after being closed

```
PROCEDURE p(OUT p_name VARCHAR)
BEGIN
DECLARE c CURSOR (name VARCHAR);
OPEN c FOR SELECT name FROM /shared/T;
CLOSE c;

-- Reopen with same query
OPEN c;
CLOSE c;

-- Reopen with new query
OPEN c FOR SELECT name FROM /shared/U WHERE birthdate > '2000-01-01';
CLOSE c;
END
```

## Java Procedures

Java procedures are programs that you write in Java to access and use TDV resources. You can add these procedures as TDV Server data sources, execute them against a data source, use them in views or procedures, and publish them as TDV database tables or Web services.

For details about the TDV APIs for custom Java procedures and examples of Java procedures, see “Java APIs for Custom Procedures” and “Java for Custom Procedures Examples” in the *TDV Reference Guide*.

For details about adding a Java procedure to TDV Server, see [Adding a Custom Java Procedure, page 163](#).

This topic contains:

- [Viewing Java Procedure Parameters, page 195](#)

For information on how to define caching for your procedures, see [TDV Caching, page 391](#).

### Viewing Java Procedure Parameters

When you add a Java procedure to the server, the procedure name is displayed in the Studio resource tree.

### To view the parameters in a Java procedure

1. Open the Java procedure in the resource tree.

The editor for the procedure opens on the right, displaying the Parameters panel.

This panel displays the input or output parameters for the procedure. You can only *view* the parameters in the Parameters panel, because the parameters are defined and edited in the source Java code.

Each parameter is displayed with its TDV JDBC data type and the data type native to the corresponding data source. The output parameters shown in this panel are rendered as columns in the result set when you execute the procedure.

For details on executing a Java procedure, see [Executing a Procedure or Parameterized Query](#), page 224.

## XQuery Procedures

XQuery procedures are programs that you write in XML to access and use TDV resources. You can add these procedures as TDV Server data sources, execute them against a data source, use them in views or procedures, and publish them as TDV database tables or Web services.

**Note:** The XQuery and XSLT procedures cannot be used as resources in the Any-Any transformation editor.

This topic contains:

- [Creating an XQuery Procedure](#), page 196
- [Designing Parameters for an XQuery](#), page 197
- [XQuery 3.0 Support](#), page 199
- [XPath 3.0 Support](#), page 199

For information on how to define caching for your procedures, see [TDV Caching](#), page 391.

### Creating an XQuery Procedure

This topic describes how to create an XQuery procedure.



### To create an XQuery procedure

1. Select a folder in the Studio resource tree, and then right-click and select New XQuery Procedure, or select File > New > XQuery Procedure.
2. Supply a name for the procedure in the XQuery.
3. Type a name and click OK.

The editor opens in the XQuery panel on the right.

4. Use the XQuery panel to formulate and edit the XQuery XML script:
  - You can use any non-declarative statement as the first statement after **BEGIN**.
  - If you have a script stored in your file system, you can upload it using the Insert from File button.
  - The XQuery panel can highlight XML syntax elements (comments, keywords, and so on).
  - Insert standard XML comments by highlighting one or more lines and typing:
  - Ctrl-Hyphen to insert two dashes (--) at the start of each line.
5. Save the script.

For details on executing an XQuery procedure, see [Executing a Procedure or Parameterized Query, page 224](#).

## Designing Parameters for an XQuery

If you want to create a script by first designing its parameters, you must design the parameters in the [Parameters Panel, page 617](#) and then write a procedure in the XQuery panel.

For more on execution, see [Executing a Procedure or Parameterized Query, page 224](#).

### To design the parameters for an XQuery in the Parameters panel

1. Create a new XQuery procedure as described in [XQuery Procedures, page 196](#).
2. Select the Parameters tab.
3. Check the Design Mode check box at the top right to make the Parameters panel editable.
4. Click the Add button to start adding parameters, and select a data type.

When you click Add and select a data type, a new parameter is added with a default name and the specified data type.

Supported data types are:

- Binary—BINARY, BLOB, VARBINARY
- Decimal—DECIMAL, DOUBLE, FLOAT, NUMERIC
- Integer—BIGINT, BIT, INTEGER, SMALLINT, TINYINT
- String—CHAR, LONGVARCHAR, VARCHAR
- Time—DATE, TIME, TIMESTAMP
- Complex—CURSOR, XML

The Browse option is for choosing a definition set. See the topic [Definition Sets, page 297](#), for details on definition sets.

5. Right-click the parameter name, choose Rename, and type the new name.
6. Optionally, change a parameter's data type:
  - a. Right-click the data type name and select Change Type.
  - b. Right-click the parameter name or data type, and select a data type from the drop-down list.
  - c. Optionally, specify the length or the number of digits for certain data types.
  - d. Click OK.
7. Select the parameter, and click Cycle I/O Direction to indicate whether the parameter is input, output, or both.
 

The Cycle I/O Direction button is not available for parameters that are part of a cursor.
8. Use the navigation buttons to move a parameter up, down, left, or right.
 

The up and down navigation buttons are enabled when there is more than one parameter.

The left navigation button is enabled for a `CURSOR` parameter. The right navigation button is enabled for a parameter in a row immediately after the last parameter in a `CURSOR`. After specifying all of the parameters you want to define, save the edits.
9. In the XQuery panel, complete the procedure using the parameters designed in the Parameters panel.
10. Save the procedure.

After the parameters in the design match the parameters in the script on the XQuery panel, the name of the script is displayed in black.

## XQuery 3.0 Support

TDV supports the following functionalities for XQuery 3.0

1. Function annotations %public and %private
2. Variable annotations %public and %private
3. CASE clause in a typeswitch expression to list multiple alternative types separated by "|"
4. In FLOWR expressions, the following clauses are supported.
  - a. COUNT
  - b. GROUP-BY
5. FILTER function is implemented with a function() argument
6. The XQuery 3.0 parser has been extended to support partial function application ("?" as a function argument) in dynamic function calls. Previously this feature was supported only in direct function calls to a named function.
7. The extensions for maps are available in XQuery 3.0

## XPath 3.0 Support

TDV supports the following functionalities for XPath 3.0

1. String concatenation operator "||"
2. Simple mapping operator "!"
3. Casting from strings (and ws:untypedAtomic) to union and list types is supported. The effect is the same as casting to an attribute with the given type, and then atomizing the attribute. For example, casting to a type list of-integerdefined as a list type with an item of xs:integer returns a sequence of xs:integer values. XPath 3.0 also allows, in some cases, casting to a union type from types other than strings.
4. Certain union types appear in a SequenceType (e.g as the declared type of a function argument). the union types accepted are those that are not derived by restriction from another union type that meets the same criteria.
5. The XPath 3.0 parser has been extended to support partial function application ("?" as a function argument) in dynamic function calls. Previously this feature was supported only in direct function calls to a named function.

6. The extensions for maps are available in XPath 3.0

7. Functions, Operators and datatypes:

`fn:path()`

## XSLT Procedures

XSLT procedures are programs that you write in XML to modify XML documents—for example, to convert them to other formats based on an XSL style sheet. You can add these procedures as TDV Server data sources, execute them against a data source, use them in views or procedures, and publish them as TDV database tables or Web services.

The XSLT procedure editor is a stand-alone, language-specific processor that lets you compose and execute XSLT scripts.

**Note:** The XQuery and XSLT procedures cannot be used as resources in the Any-Any transformation editor.

This topic contains:

- [Creating an XSLT Procedure, page 200](#)
- [Designing Parameters for an XSLT Procedure, page 201](#)

For information on how to define caching for your procedures, see [TDV Caching, page 391](#).

## Creating an XSLT Procedure

This topic describes how to create an XSLT procedure.

### To create an XSLT procedure

1. Select a folder in the Studio resource tree, and then right-click and select New XSLT Procedure, or select File > New > XSLT Procedure.
2. Type a name for the procedure in the New XSLT Procedure dialog box and click OK.

The editor opens in the XSLT panel on the right.

3. Use the XSLT panel to formulate and edit the XSLT XML script.
  - The XSLT procedure editor supports XSLT 1.0 and 2.0.
  - If you have a script stored in your file system, you can upload it using the Insert from File button.
  - The XSLT panel can highlight XSLT syntax (elements, attributes, and so on).
  - Insert standard XML comment notation by highlighting one or more lines and typing Ctrl-Hyphen.

The procedure editor inserts “<!--” at the start, and “-->” at the end, of each line you have highlighted.

4. Save the script.

For details on executing an XSLT procedure, see [Executing a Procedure or Parameterized Query, page 224](#).

## Designing Parameters for an XSLT Procedure

If you want to create a script by first designing its parameters, you must design the parameters in the [Parameters Panel, page 617](#) and then write a procedure in the XSLT panel.

For more on execution, see [Executing a Procedure or Parameterized Query, page 224](#).

### To design the parameters for an XSLT in the Parameters panel

1. Create a new XSLT procedure as described in [XSLT Procedures, page 200](#).
2. Select the Parameters tab.
3. Check the Design Mode check box at the top right to make the Parameters panel editable.
4. Click the Add button to start adding parameters, and select a data type.

When you click Add and select a data type, a new parameter is added with a default name and the specified data type.

Supported data types are:

- Binary—BINARY, BLOB, VARBINARY
- Decimal—DECIMAL, DOUBLE, FLOAT, NUMERIC
- Integer—BIGINT, BIT, INTEGER, SMALLINT, TINYINT
- String—CHAR, LONGVARCHAR, VARCHAR
- Time—DATE, TIME, TIMESTAMP
- Complex—CURSOR, XML

The Browse option opens an Add Definition Type window in which you can select an XML schema definition set, select Type in the Show pane on the right, and select a type from the list. See [Definition Sets, page 297](#) for details on definition sets.

5. Right-click the default parameter name, choose Rename, and type a new name.
6. Optionally, change a parameter's data type:
  - a. Right-click the data type name and select Change Type.
  - b. Right-click the parameter name or data type, and select a data type from the drop-down list.
  - c. Optionally, specify the length or the number of digits for certain data types.
  - d. Click OK.
7. Select the parameter, and click Cycle I/O Direction to indicate whether the parameter is input, output, or both.

The Cycle I/O Direction button is not available for parameters that are part of a cursor.

8. Use the navigation buttons to move a parameter up, down, left, or right.

The up and down navigation buttons are enabled when there is more than one parameter.


The left navigation button is enabled for a CURSOR parameter. The right navigation button is enabled for a parameter in a row immediately after the last parameter in a CURSOR. After specifying all of the parameters you want to define, save the edits.

9. In the XSLT panel, complete the procedure using the parameters designed in the Parameters panel.
10. Save the procedure.

After the parameters in the design match the parameters in the script on the XSLT panel, the name of the script is displayed in black.

### Parameter Entry

When you click the icon to execute an XSLT procedure with parameter input, an Input Values for <procedure\_name> dialog box appears. It displays parameter names down the left side, and prepared XML code fragment with a question mark that you can replace with the input value.



You can replace the question mark with an input value, or check the Null box to eliminate the XML code fragment.

## Packaged Queries

*Packaged queries* let you use database-specific queries defined within the TDV system and sent for execution on the targeted data source. Sometimes, you already have a complex query written for a particular database and it might not be feasible to rewrite that query in TDV SQL.

For example, your query might require a database-specific feature not available in TDV or perhaps the query takes advantage of the database-specific feature for performance reasons. In such cases, your database-specific query can be created as a packaged query and subsequently be used in other queries.

Multiple database-specific SQL statements can be executed sequentially by the same packaged query as long as only the last SQL statement returns a single cursor with at least a single column output. See the section on [Multiple SQL Execution Statements in a Packaged Query](#), page 211.

Every packaged query is associated with a specific data source.

A packaged query is stored in TDV with the associated data source's metadata, and it functions like a stored procedure, accepting input parameters and producing rows of data. It must have exactly one output parameter that is a cursor with at least one column.

Because the TDV system cannot automatically determine the required inputs and outputs of a database-specific query, it is necessary for the user to supply this information.

For details on specifying parameters for a packaged query, see [Specify Input Parameters for a Packaged Query, page 206](#).

For details on executing a packaged query, see [Executing a Procedure or Parameterized Query, page 224](#).

This section includes:

- [Creating a Packaged Query, page 204](#)
- [Specify Input Parameters for a Packaged Query, page 206](#)
- [Multiple SQL Execution Statements in a Packaged Query, page 211](#)

## Creating a Packaged Query

### To create a packaged query

1. Right-click an appropriate location in the resource tree to add the packaged query, and select New Packaged Query.

The New Package Query window opens.

2. Type a name for the packaged query.
3. Select the data source with which to associate the packaged query.

If you want to associate the packaged query with a different data source later on, you can use the rebinding technique, which is described in the section [Rebinding a Procedure, page 222](#).

4. Click OK.

The editor opens on the right, displaying the SQL panel.

Use the SQL panel to formulate and edit the SQL for the packaged query. The parameters you define in the SQL panel must match the parameters designed in the Parameters panel, including the order in which they are provided.

5. In the SQL panel for the packaged query:
  - a. If the database-specific query already exists in the file system, upload the file using Insert from file in the editor's toolbar.



The SQL from the file is copied onto the SQL panel.

- b. If the database-specific query is not available elsewhere, type it in the SQL panel. Add the string "<version 2>" to the beginning of the first SQL line to handle null values passed by input parameters and to automatically escape any single-quote characters that might appear in the substitution values of any string or TIMESTAMP input parameters.

Packaged Query SQL does not require full pathnames to resources because the packaged query is already associated with the data source.

The packaged query must have exactly one output parameter that is a cursor with at least one column. In the following, the data source is `orderdetails` (specified in the FROM clause).

Define input parameters with curly braces, {N}, enclosing numerals that start from zero to N, as the input parameter placeholders (in this example specified in the WHERE clause). For details on defining input parameters and examples, see [Specify Input Parameters for a Packaged Query, page 206](#).

**Note:** If the packaged query is equivalent to a single SELECT statement with a table or cursor output, check the Single Select check box. This flag tells the TDV query engine that the packaged query can be treated as a derived table, potentially enhancing the efficiency of the query plan. Because TDV does not process the packaged query, the user must make the determination whether the output qualifies for this optimization. Marking the packaged query as a Single Select allows TDV to add predicates (filter conditions) to the packaged query so that it can be a target of a semijoin optimization.

6. Click the Parameters tab to display the Parameters panel.

Use the Parameters panel to design the input and output parameters for the query. The parameters defined in the Parameters panel must match the parameters defined in the SQL panel, including their order. After all the parameters are specified, you can use them to do a top-down design of the SQL in the SQL panel.

To proceed with the example in [Creating a Packaged Query, page 204](#), add one output parameter (`UnitPrice`) and two input parameters (`ProductID` and `Status`) in the Parameters panel.

- a. Select the output parameter named **result**, and click Add.
- b. Select Decimal > DECIMAL as the data type.

A new parameter is added with the specified data type.

- c. Rename the newly added parameter as `UnitPrice` (to indicate the output), and click ENTER.
- d. Make sure that this parameter is a part of the CURSOR output by moving it to the right of result using the right-arrow button, if necessary.
- e. Add another parameter of the type Integer > INTEGER.

This is the first input parameter in our example. If it is placed under result as a part of the CURSOR output, use the left triangle button on the toolbar to move it outside the output cursor. A right-arrow icon appears next to it.

A right-arrow icon denotes an input parameter; a left-arrow icon denotes an output parameter.

- f. Rename the parameter as `ProductID`, and click ENTER.
  - g. Add another input parameter named `Status` of the type String > CHAR.
7. Save the packaged query.
  8. Execute the packaged query.

Executing a packaged query is similar to executing a parameterized query. For details, see [Executing a Parameterized Query, page 225](#).

## Specify Input Parameters for a Packaged Query

An input parameter is not required for a database-specific query. However, when creating a packaged query you can define one or more numbered input parameters to insert prior to execution and submission of the database-specific query. For each input value in the database-specific SQL, you must create an input parameter in the packaged query using the Parameters panel editor in Studio.

For example, your database-specific query might be used to fetch a row from a table but require an ID to identify the specific row. Packaged queries can easily define an ID input parameter or other parameter values for insertion at runtime.

When TDV Server executes a packaged query, it inserts actual values into the database-specific query before sending the packaged query to the data source for execution.

An input parameter consists of a name and a data type, both of which you specify when you define the parameter. The parameter name is displayed at query execution time, prompting for an input value. The parameter name has no effect on the database-specific query; it is used by users of your packaged query. However, the data type you specify does affect how a value is formatted when it is inserted into the database-specific query.

## Data Types

Packaged queries support the following input data types:

DECIMAL, DOUBLE, FLOAT, NUMERIC, BIGINT, BIT, INTEGER, SMALLINT, TINYINT, CHAR, LONGVARCHAR, VARCHAR, DATE, TIME, TIMESTAMP

## Input Substitution

The package query can define N inputs, with substitution patterns numbered from {0} to {N-1}.

## Input Substitution Pattern

Packaged queries use one of two different input substitution patterns for each numbered input. The first line of the SQL must begin with <version 2>

- {N}—the numbered input is replaced with the data value with no changes.
- {N:string-sql-literal}—for data types of VARCHAR and TIMESTAMP the numbered input placeholder is replaced with the substituted string value and enclosed within single quotes.

If any single-quote characters are present in the string value that is to be substituted, they are automatically escaped with a second single-quote.

Null values are substituted.

Package queries that do not require an input, do not need a substitution pattern or substitution placeholders; however, the query must have exactly one output parameter that is a cursor with at least one column.

When **STRING** and **DATE** data types are used, you should use a single quote before and after the input substitution pattern. This rule does not apply to numeric data types.

## Input Parameters Evaluation

This section illustrates how the packaged query input parameters are evaluated at runtime. The first six query examples are valid. The final two query examples are invalid.

### Valid Query 1: Simple Substitution

In the following example {0} is a string, {1} is a number, and the package query is defined with the following:

```
<version 2>
SELECT customer.balance
FROM customer
WHERE customer.name = '{0}' AND customer.id = {1}
```

The pattern for a string is enclosed in single quotes. The first input value replaces all the occurrences of {0}, the second input value replaces {1}, and so on.

### Valid Query 2: Multiple Substitutions

Each input substitution pattern is allowed to appear more than once in a packaged query:

```
<version 2>
SELECT customer.name, customer.balance
FROM customer
WHERE
(customer.id = {0} AND customer.zip = {2})
OR (customer.id = {1} AND customer.zip = {2})
```

### Packaged Query before Substitution

```
<version 2>
SELECT customer.name, customer.balance
FROM customer
WHERE
(customer.id = {0} AND customer.zip = {2})
OR (customer.id = {1} AND customer.zip = {2})
```

### Packaged Query after Substitution

Given actual input values like a first input value of 101, a second input value of 102, and a customer.zip value of 94403, the substitution would look like the following:

```
<version 2>
SELECT
customer.name, customer.balance
FROM
customer
WHERE
(customer.id = 101 AND customer.zip = 94403)
OR (customer.id = 102 AND customer.zip = 94403)
```

### Valid Query 3: Escaping Characters to Stop Substitution

If a pattern such as '{i}' needs to be preserved, use a backslash (\) to escape the opening and closing curly braces ('\{i\}').

### Packaged Query before Substitution

```
<version 2>
SELECT customer.name, customer.balance
FROM customer
WHERE
```

```
(customer.id = {0})
AND (customer.note = 'preserved \{1\}input')
OR (customer.id = {1} AND customer.zip = {2})
```

### Packaged Query after Substitution

Substituting the same input values as the previous example:

```
SELECT customer.name, customer.balance
FROM customer
WHERE
(customer.id = 101
AND (customer.note = 'preserved {1} input')
OR (customer.id = 102 AND customer.zip = 94403
```

**Note:** The backslash (\) is removed from the original query. Escaping the second curly brace is optional.

### Valid Query 4: Escaping Escaped Characters

If backslashes are part of a valid string (for example, '\{i\}') that should not be altered, add another backslash character ('\{i\\}').

### Packaged Query before Substitution

```
<version 2>
SELECT customer.name, customer.balance
FROM customer
WHERE
(customer.id = {0})
AND (customer.zip = '\\{2\\}')
OR (customer.id = {1} AND customer.zip = {2})
```

### Packaged Query after Substitution

Substituting the same input values as the previous examples:

```
SELECT customer.name, customer.balance
FROM customer
WHERE
(customer.id = 101
AND (customer.zip = '\\{2\\}')
OR (customer.id = 102 AND customer.zip = 94403)
```

### Valid Query 5: {N:string-sql-literal} Option

If a query input is a string containing a single quote, the input placeholder should be {N:string-sql-literal} so that it is enclosed in single quotes and escaped by the packaged query to become two single quotes after substitution.

### Packaged Query before Substitution

```
<version 2>
SELECT customer.balance
FROM customer
WHERE
customer.name = {0:string-sql-literal} AND customer.id = {1}
```

### Packaged Query after Substitution

The first substitution value is “Michael’s son” and the second is “123”.

```
SELECT customer.balance
FROM customer
WHERE
customer.name = 'Michael's son' AND customer.id = 123
```

### Valid Query 6: Another Escape Example for Numeric Values

If a query input contains a number enclosed in curly braces such as ‘{55}’, escape each curly brace with a backslash. There is no need to escape the curly braces, if the curly braces enclose a string such as ‘{the Second}’.

### Packaged Query before Substitution

```
<version 2>
SELECT customer.balance
FROM customer
WHERE
customer.id = {0}
AND customer.name = 'George {the Second}'
AND customer.id = '{55}'
```

### Packaged Query after Substitution

```
SELECT customer.balance
FROM customer
WHERE
customer.id = 123
customer.name = 'George {the Second}'
AND customer.id = '{55}'
```

### Invalid Query A

The following query is invalid because substitution pattern input {1} is missing from the query.

```
SELECT customer.name, customer.balance
FROM customer
WHERE customer.id = {0} AND customer.status = {2}
```

## Invalid Query B

The following query is invalid because the database-specific query defines four inputs, but the packaged query has defined only three input substitutions. The fourth SQL input placeholder{3} makes the query invalid. You need to define one more input parameter. Also the customer.zip is an integer that does not need to be enclosed in single quotes.

```
SELECT customer.name, customer.balance
FROM customer
WHERE
customer.id = {0} AND customer.zip = '{1}'
AND customer.status = {2} AND customer.email = {3}
```

## Multiple SQL Execution Statements in a Packaged Query

You can execute multiple SQL statements sequentially with a single packaged query. Multiple database-specific SQL statements can be invoked to create tables, modify tables, drop tables, insert rows, update rows, delete rows, invoke procedures, commit transactions, or roll them back. The sequence of SQL executions ends when an error occurs or after a SQL statement returns a result set.

### Define a Multi-Part Packaged Query

Sequences of SQL statements can be sent to the data source through packaged queries as long as no SQL statement except the last one returns a result. The return of a result set cursor, or an exception, signals the end of the sequence of SQL executions.

The first line of SQL in the packaged query must set the multi-part separator character or set of characters. The following sample multi-part separator sets the SQL statement delimiter as two semicolons separated by a space:

```
<version 2> multipartseparator=; ;
```

This statement can be used to define other unique character sets to comply with any special data source query language requirements, but make sure the chosen delimiter is not used within any string, which can cause an unintended break.

Using a separator like “;” causes problems if a semicolon also shows up inside a string value substituted into the query.

Given definition of the multi-part separator, SQL statements are parsed and executed sequentially until the last statement returns a result set.

**Note:** If you execute anything that modifies the state of the connection in a way that survives beyond the current transaction, you can cause unexpected results for another user when and if the connection is put back into the pool.

## Parameterized Queries

Studio can create SQL SELECT statements that include named parameters in the projections or selections. In the TDV system this feature is called a *parameterized query*. Such queries are implemented as single-statement SQL scripts. The SQL script code is automatically generated when you design a parameterized query with the Model and Grid panels. For details on SQL script languages, see the *TDV Reference Guide*.

The resources you can use in a parameterized query are tabular data and any procedure that outputs either a set of scalars or one cursor.

A parameterized query lets you include {param NAME TYPE} structures in the Grid panel to parameterize parts of the view. The resource itself is actually a SQL script with a model, so it functions like a procedure within the system.

The following sections describe how to create and execute a parameterized query:

- [Quick Steps for Creating a Parameterized Query, page 212](#)
- [Add Input Parameters, page 213](#)
- [Adding a Parameter to a SELECT Clause, page 214](#)
- [Adding a Parameter to a WHERE Clause, page 215](#)
- [Adding a Parameter to a FROM Clause, page 215](#)
- [Executing a Parameterized Query, page 225](#)

### Quick Steps for Creating a Parameterized Query

Here are some quick steps for using a table in a parameterized query. For details and diagrams, see [Add Input Parameters, page 213](#).

#### To create a parameterized query

1. Select File > New > Parameterized Query from the menu bar, and give it a name.
2. Add the appropriate table to the Model panel on the right.  
See [Adding a Resource to the Model Panel, page 139](#) for details.
3. Click the Grid tab.
4. On the Grid panel, specify a column to project, or leave the cell entry as \* (to select all columns).
5. Right-click a blank Column cell, and select Parameter.



6. In the Add Parameter dialog:
  - a. Type a unique name for the parameter in the Parameter Name field (for example, selectedValue).
  - b. Select a data type from the drop-down list, and click OK.

The entry is displayed in the Grid in the following format:  
`{param <parameter name> <parameter data type>}`

The corresponding Alias cell is automatically assigned a unique value (for example, Expr1).

7. Click the icon to execute the parameterized query.  
 The Input Values for <resource> window opens and prompts you to provide a value for the parameter you added in a previous step.
8. Type in the value for the parameter and click OK to execute the query.

## Add Input Parameters

You can define input parameters for the SELECT, WHERE, or FROM clause of a parameterized query.

- For the SELECT clause, add it from a Column cell in the Grid panel. See [Adding a Parameter to a SELECT Clause, page 214](#).
- For the WHERE clause, add it from a Criteria cell in the Grid panel. See [Adding a Parameter to a WHERE Clause, page 215](#).
- For the FROM clause, include a procedure with an input parameter in a parameterized query. See [Adding a Parameter to a FROM Clause, page 215](#).

This section provides the details of adding parameters using an editor window (Add Parameter). You can also type the parameters in the Grid panel.

### About Parameter Names

- When you type a parameter, it must be in the format `{param <name> <type>}`. The parameter name is case-sensitive.
- Several parameters can have the same name, provided they are distinguished by lowercase and uppercase letters, or by data type.
- Different parameters can have the same name and data type, if they have different aliases.

## Adding a Parameter to a SELECT Clause

When you want parameters to be used in a SELECT clause, you must add them from cells in the Column column.

### To include a parameter in the SELECT clause of a parameterized query

1. Right-click a location in the resource tree and select New Parameterized Query.
2. In the Input window, supply a unique name for the parameterized query, and click OK.

The editor for building the query appears.

3. Add the resources to the Model panel.

You can add any type of table (relational, LDAP, delimited file) and a procedure that contains scalar outputs or one cursor output.

See [Adding a Resource to the Model Panel, page 139](#) for details.

4. Click the Grid tab.
5. In the Grid panel, which works like the Grid panel in the view editor, click the first Column cell and select a column.
6. Right-click the next Column cell and select Parameter.
7. In the Add Parameter dialog, type a name in the Parameter Name field, and select a data type.

This entry now appears in the Column cell.

8. Click the name in the Alias cell and rename it if you want.
9. Click the SQL Script tab if you want to view the auto-generated SQL script.
  - The parameterized query is treated as a PROCEDURE in the SQL script.
  - The parameter defined in a previous step appears as an input parameter of the procedure, and is also included in the SELECT clause of the parameterized query.
  - The output of the parameterized query is rendered as a CURSOR-type OUT parameter of the procedure.
10. Click the Parameters tab if you want to view how the parameters are displayed.
11. Save the parameterized query.

## Adding a Parameter to a WHERE Clause

When you want parameters to be used in a WHERE clause, you must add them from cells in the Criteria column.

### To include a parameter in the WHERE clause of a parameterized query

1. In the resource tree, right-click a container and select New Parameterized Query.
2. In the Input window, supply a unique name for the parameterized query and click OK.

The editor for building the resource opens in the right pane.

3. Click the Model tab.
4. Drag and drop tables, views, or other procedures from the Studio resource tree into the Model panel.
5. In the Grid panel, click a Column cell to select one of the column names.
6. Click a second Column cell and select another column name.
7. Right-click the Criteria cell corresponding to the second column name under Column, and select Parameter.
8. In the Add Parameter window, supply a name for the parameter, select the data type, and click OK.

This parameter appears in the Criteria column.

9. Click the SQL Script tab if you want to view the auto-generated SQL script.  
The parameter you added is placed in the parameterized query's WHERE clause.
10. Save the parameterized query.

## Adding a Parameter to a FROM Clause

The following steps use a transformation as a sample procedure type to include in a parameterized query. The steps are similar for other types of procedures.

### To include a parameter in the FROM clause of a parameterized query

1. Right-click a node in the resource tree and select New Parameterized Query.
2. In the Input window, supply a unique name for the parameterized query and click OK.

The editor opens in the right pane.

3. Drag the transformation that requires input parameters and drop it onto the Model panel. For information on transformations, see [Using Transformations, page 231](#).

The Input Parameters for <transformation name> window opens.

In this window, the upper section displays the input parameters. The icon next to each parameter represents its type.

4. To display the parameter's definition, click the Show Definition button.

The window displays the parameter's name and type.

In the **Value** group box, all options are mutually exclusive. Null specifies a NULL value; if it is disabled, the parameter cannot be NULL. Literal applies a value selected in the upper section. Query Parameter accepts a name for the parameter.

Each parameter in the upper section is displayed with its initial value. If the parameter is nullable, the default is null. If the parameter is not nullable, the default value depends on type: zero for numeric, an empty string for a character, and the current date for a date.

5. Select the Query Parameter radio button, type the name, and click OK.

Do not include string values in quotation marks. The parameter name must be unique and begin with a letter. It can contain any number of alphanumeric characters and can include an underscore. It must not contain any spaces.

6. Click OK to save the entry and close the window.

The name of the parameter appears as the input parameter (IN) and is also included in the FROM clause.

7. If you want to view the auto-generated SQL script, click the SQL Script tab in Studio.
8. Save the parameterized query.

Here is an example of adding a parameter to the FROM clause of a parameterized query.

```

PROCEDURE paramQueryWithWebService(
  IN ticker VARCHAR(255),
  OUT result CURSOR (
    ID INTEGER,
    PARENT_ID INTEGER,
    "DEPTH" INTEGER,
    NAME VARCHAR(255),
    XPATH VARCHAR(255),
    "PATH" VARCHAR(255),
    "POSITION" INTEGER,
    "VALUE" VARCHAR(255)
  )
)
BEGIN
  OPEN result FOR
  SELECT
    *
  FROM
    /shared/sources/transformations/basic/trans_getQuote('
<ns1:Body>
  <ns2:getQuote xmlns:soap-env="http://schemas.xmlsoap.org/soap/enve
  <symbol>' || ticker || '</symbol>
</ns2:getQuote>
</ns1:Body>
</ns1:Envelope>') trans_getQuote;
END

```

The name of the parameter (ticker) appears as the input parameter (IN) and is also included in the FROM clause.

## Physical Stored Procedures

TDV supports the introspection of data sources that contain stored procedures written in SQL. Procedures stored in data sources are referred to as *physical stored procedures*.

**Note:** In this document, the terms “physical stored procedure” and “stored procedure” are use interchangeably.

Physical stored procedures have certain capabilities and limitations:

- They can have scalar parameters, but the direction of scalar parameters might not always be detected.
- They can return one or more cursors that represent tabular output.
- Array-type parameters are not allowed in published stored procedures.

- If they are in a physical data source, you can manually specify cardinality for them. See [Creating Cardinality Statistics on a Data Source, page 492](#).
- A stored procedure that returns only one cursor can be used within a view.
- A stored procedure that returns multiple cursors or scalar parameters cannot be included in a view.
- TDV supports the introspection of some stored procedures for some data sources.
- Cursors are not introspected for DB2, SQL Server, and Sybase databases.
- In Oracle data sources, the cursor type is introspected as type OTHER. If you do not change the cursor's signature but execute the Oracle stored procedure, cursor values are interpreted as binary data. However, if you edit the stored procedure and define the cursor's signature, its output is displayed in tabular form.

To edit stored procedures and define cursor signatures, see:

- [Editing a Stored Procedure in an Introspected Data Source, page 218](#)
- [Editing a Stored Procedure in Microsoft SQL Server, page 221](#)
- [Editing a Stored Procedure in DB2, page 221](#)

## Editing a Stored Procedure in an Introspected Data Source

During introspection, the direction of the scalar parameters and cursors in stored procedures might be unidentified. A stored procedure with an unidentified scalar parameter or cursor direction returns an error when run as-is. In such cases you need to specify parameter and cursor direction manually.

This section uses an example to show how to specify scalar parameter or cursor direction, and define a cursor signature. The stored procedure discussed here has two scalar parameters (one input and one output) and it returns a single cursor that has seven columns.

To edit a stored procedure in an introspected data source, see:

- [Specifying the Direction of Scalar Parameters and Cursors, page 218](#)
- [Defining a Cursor for Projection, page 219](#)

## Specifying the Direction of Scalar Parameters and Cursors

If introspection results include a parameterized query with scalar parameters whose direction is undefined, follow these steps to define the direction of those scalar parameters.

### To specify the direction of a scalar parameter or cursor

1. Double-click the stored procedure to open it, or right-click it and select Open. The editor opens on the right.  
If the direction of an introspected parameter or cursor is unknown—whether it is IN, INOUT, or OUT—the icon next to it looks broken.  
If you create a copy of a stored procedure in Studio, Studio automatically introspects the procedure (that is, gathers metadata for it) and assigns the default I/O direction of IN to any parameter or cursor whose direction is unknown.
2. Select the Design Mode check box in the editor's toolbar so you can start editing the parameters.
3. Select the parameter whose direction is unknown, and use the direction arrows buttons on the toolbar to specify the direction.
4. Save the stored procedure.

### Defining a Cursor for Projection

If introspection results include a parameterized query with one or more cursors whose direction is undefined, follow these steps (using the sample cursor and its parameters as a guide) to manually define a cursor for projection.

#### To define a cursor for projection

1. Double-click the stored procedure to open it, or right-click it and select Open. The editor opens on the right.
2. Select the Design Mode check box in the editor's toolbar so you can start editing the parameters.
3. Click the Add button, and select Complex > CURSOR.  
A new cursorParam of type CURSOR is added.
4. Select the cursorParam and click Cycle I/O Direction one or more times to change the direction to OUT.  
The other two valid direction icons are IN and INOUT.
5. With cursorParam still selected, click Add and select Time > TIMESTAMP.  
A new parameter named timestampColumn is automatically placed under cursorParam.
6. Rename the newly added parameter date and click Enter.

7. Add more child parameter names and types to cursorParam one at a time, in the following order, and specify each parameter's type as noted.

ord\_num (type NUMERIC)  
 qty (type SMALLINT)  
 title\_id (type CHAR)  
 discount (type DOUBLE)  
 price (type DECIMAL)  
 total (type DOUBLE)

Your selection of the cursor columns is complete.

If you are unsure what columns and data types to use for the cursor, use Studio's Design By Example tool to select the parameters. See [Designing a Cursor by Example, page 220](#). When you use Design By Example, all previously defined parameters for the cursor are overwritten.

8. Select the parameter named RETURN\_VALUE and click the Delete button, or select Delete from the right-click menu.
9. Save the stored procedure.

For details on execution, see [Executing a Stored Procedure, page 226](#).

## Designing a Cursor by Example

When you use Design By Example for a cursor, all previously defined parameters for the cursor are overwritten.

### To design a cursor by example

1. Follow Step 1 through Step 5 as described in [To define a cursor for projection, page 219](#).
2. Save the stored procedure after specifying the direction for any scalar parameter whose direction is unknown.
3. Click Design By Example on the procedure editor toolbar.

The Input Values for <resource> window opens.

4. Supply a value for the scalar input parameter and click OK.

The Design By Example window opens to display all the columns in the cursor, which is named result.

5. Click OK to accept the parameters.

All the cursor columns are included for projection in the stored procedure.

You can rename any of the parameters or columns, and also change their data types, as long as the data types are compatible with the ones in the underlying physical stored procedure.



6. Save the stored procedure.

For details on executing stored procedures, see [Executing a Stored Procedure](#), page 226.

## Editing a Stored Procedure in Microsoft SQL Server

The stored procedure discussed in this section is in a data source called Northwind in a Microsoft SQL Server database, with two scalar parameters whose directions are known. The stored procedure returns a cursor, which has two columns. The cursor will not be introspected during data source introspection. If you use the Design By Example window, both cursors will always be found in the same order (unless the stored procedure has changed because of introspection).

### To edit a stored procedure that returns a single cursor

1. Open the stored procedure by double-clicking the stored procedure or right-clicking it and selecting Open.

The editor opens on the right. This stored procedure has one input parameter and one output parameter.

2. You can design the cursor manually or by using the Design By Example tool, as described in [Editing a Stored Procedure in an Introspected Data Source](#), page 218.

## Editing a Stored Procedure in DB2

This section describes how to edit a stored procedure that does not have any scalar parameters but returns two cursors.

### To edit a stored procedure that returns two cursors

1. Open the stored procedure by double-clicking the stored procedure, or by right-clicking it and selecting Open.

The editor opens on the right. There is no scalar parameter in this stored procedure.

2. Check the Design Mode check box.

This selection puts the editor in design mode, so you can start adding and editing parameters.

3. Add and edit parameters as required.

4. Click Design By Example on the toolbar, and use the scroll bar in the Design By Example window to view the two cursors.

Use the expand/collapse symbol on the left of the parameter name to expand/collapse cursor display.

5. Click OK to include both the cursors for projection.
6. Save the stored procedure.

For details on executing stored procedures, see [Executing a Stored Procedure](#), page 226.

## Using Stored Procedures

Using stored procedures involves these activities:

- [Rebinding a Procedure](#), page 222
- [Setting Transaction Options for a Procedure](#), page 223
- [Executing a Procedure or Parameterized Query](#), page 224

### Rebinding a Procedure

A procedure depends on one or more underlying sources, and the procedure is considered “bound” to those underlying sources.

The following procedure bindings are available:

- A SQL script can be bound to a table or a procedure.
- A transformation can be bound to hierarchical data (XML or WSDL).
- A packaged query can be bound to a data source.

Rebinding a procedure is useful:

- If after creating a procedure you decide to rebind the procedure to different sources.
- If an execution error occurs because a source no longer exists and you want to rebind the procedure with a new source.

If you modify a procedure or its dependencies, the binding is automatically updated when you save the script, and the Rebind panel reflects the change. For example, if your procedure has a data source dependency named `ds_orders`, and you rename it `ds_orders_renamed` and save the script, the Rebind panel lists the dependency as `ds_orders_renamed`.

### To rebind a procedure to a different source

1. Open the procedure.
2. Click the Show Rebind Panel toolbar button.

The Rebind panel opens in the lower section of the procedure editor, and displays the immediate dependencies as determined by the last-saved version of the procedure. (If a procedure has never been saved, the Rebind panel is blank.)

3. In the Rebind panel, highlight the source in the left pane and click Rebind.
4. In the Rebind dialog that opens, specify the source with which to rebind the script and click OK.
5. Save the procedure.

## Setting Transaction Options for a Procedure

You can force Studio to ensure consistent execution results for a given set of input parameter values (variant). If the procedure is executed more than once for a variant, it returns the result set from the first execution. Results from these procedure variants are valid only for the lifetime of a transaction unless caching is enabled.

**Note:** When transaction procedure caching is enabled, results are cached until the transaction is completed. This can affect performance if the procedure results are unusually large or the transaction remains unresolved for a long time.

Studio also minimizes repeated calls to the data source—for example, if a procedure has an input parameter like this:

```
getAccountHistory(IN acctNum INTEGER, OUT results CURSOR)
```

If you call this procedure for the first time in a transaction with a given input value, the procedure runs as usual. If you call the same procedure again with the same input value in the same transaction, Studio returns the results of the previous call instead of re-executing the procedure.

**To set transaction options**

1. On the Info tab of the procedure definition, check the box labeled Execute only once per transaction for each unique set of input values to ensure consistent results during a single execution.

## Executing a Procedure or Parameterized Query

You can initiate execution of a procedure in various ways:

- [Executing a Procedure in Studio, page 224](#)
- [Executing a Parameterized Query, page 225](#)
- [Executing a Stored Procedure, page 226](#)
- [Executing a Procedure through JDBC, page 227](#)

## Executing a Procedure in Studio

When you execute a procedure in Studio, you have the option (with SQL scripts and parameterized queries) to use the **Trace** button to see line-by-line execution details. If input parameter values are required for the procedure, a window opens with the parameter names and fields for you to type the values before execution proceeds.

**To execute a procedure in Studio**

1. Open the procedure.
2. If you want to see line-by-line execution details, set the Trace button.
3. Click the Execute button.
4. If input parameter values are required, supply those values and click OK.
5. Execute the procedure.
6. Review the execution details for each line are shown in the Console tab.
7. You can cause debug messages to be posted to the console or log by calling `print`, `log`, or `logError`.

## Executing a Parameterized Query

This section provides examples of executing a parameterized query, an XSLT transformation, and physical stored procedures that return scalar parameters and cursors.

When you execute a parameterized query that has input parameters, you are prompted to supply values for them.

The parameterized query used here has one input parameter (desiredProduct) and an output cursor.

```

PROCEDURE LookupProduct {
  IN desiredProduct INTEGER,
  OUT result CURSOR {
    ProductName VARCHAR(50),
    ProductID INTEGER,
    ProductDescription VARCHAR(255)
  }
}

BEGIN
  OPEN result FOR
  SELECT
    products.ProductName,
    products.ProductID,
    products.ProductDescription
  FROM
    /shared/examples/ds_inventory/products products
  WHERE
    products.ProductID = desiredProduct;
END

```

The screenshot shows a SQL editor window with the following tabs: 'EgXSLTTransformationOnpro...', 'LookupProduct', and '\*CompositeView'. The main editor area contains the SQL code for the 'LookupProduct' procedure. The code defines an input parameter 'desiredProduct' of type 'INTEGER' and an output cursor 'result' containing columns 'ProductName', 'ProductID', and 'ProductDescription'. The procedure body opens a cursor for a SELECT query that filters products by 'desiredProduct'.

### To execute a parameterized query

1. Double-click to open the parameterized query, and click the Execute button in the editor.

The window opens so you can provide parameter values.

This window displays the input parameters defined for the query. The icon to the left of a parameter represents the parameter type. To see the type as text, let the cursor hover over the icon. For XML parameters you might have access to a button on the window so that you can open up an XML editor.

2. Type a value in the Value field, or check Null (if the parameter is nullable).

For this example, supply a value for the defined input parameter, `desiredProduct`.

3. Click OK.

When the parameterized query is executed, the product name, ID and description are displayed.

4. In the Result For result panel:
  - a. To view the next fifty rows in a large data set, click Next.
  - b. To view the details of a specific row in a Result Details dialog, select the row and click Details. To see details for an adjacent result, click Prev or Next. For some extremely large results, such as those generated by using `EXTEND` on an array to generate `BIGINT` number values, some of the data might be truncated without a visual indication by Studio.
  - c. To save the results, use Save to File.
  - d. To clear what is displayed in the tab, click Clear.

**Note:** Result for result appears on the tab of the Result panel because result was the name used for the output parameter in the query. If you assign a different name to the output cursor, such as `productFound`, the tab would show Result for `productFound`.

## Executing a Stored Procedure

This section describes how to use Studio to execute a stored procedure that returns one or more cursors. A stored procedure can contain any number of cursors.

### To execute a stored procedure that returns a single cursor

1. Edit the stored procedure as described in [Editing a Stored Procedure in an Introspected Data Source](#), page 218.

The following steps apply to the stored procedure described in [Designing a Cursor by Example](#), page 220.

2. Save the stored procedure, and click Execute.

Because the stored procedure has a scalar input parameter, the Input Values for <resource> dialog opens. See [Executing a Parameterized Query](#), page 225 for a description of this window.

3. Supply a value for the scalar parameter and click OK.

The stored procedure is executed and the cursor output is displayed.

**To execute a stored procedure that returns two cursors**

1. Edit the stored procedure as described in [Editing a Stored Procedure in an Inspected Data Source, page 218](#).
2. Save the stored procedure.
3. Click Execute.

You can view the results of cursors in any order. However, due to JDBC driver constraints, all rows of the first-opened cursor need to be buffered before the rows of the next cursor are returned. Therefore, if you are interested in the results of the second cursor and want to improve performance, close the first cursor to disable buffering.

**Executing a Procedure through JDBC**

The name of the sample stored procedure is SP\_D1. The username and password are guest and password. This section contains sample Java code to execute a stored procedure that returns two cursors.

**To execute a stored procedure through JDBC**

1. Publish the stored procedure as a TDV data service in the following directory: Data Services/Databases/ds
2. Write and compile the Java code, and save the class file in a directory.  
See [Sample Code Using MultipleCursors, page 227](#).
3. From the directory where you saved the class file, run the following command:

```
java -classpath <path_to_csjdbc.jar_file>/csjdbc.jar;. <MultipleCursors>
```

MultipleCursors is the name of the class file, and csjdbc.jar is the name of the JAR file containing the class file.

**Sample Code Using MultipleCursors**

```
import java.sql.*;

public class MultipleCursors
{
    private static final String COMPOSITE_URL =
        "jdbc:compositesw:dbapi@localhost:9401?domain=composite&dataSource=ds";

    private static final String COMPOSITE_DRIVER =
        "cs.jdbc.driver.CompositeDriver";

    private static final String COMPOSITE_USER = "guest";
```

```

private static final String COMPOSITE_PASSWORD = "password";

public static void main(String[] args) {
    try {
        Class.forName(COMPOSITE_DRIVER);
    } catch (ClassNotFoundException ex) {
        ex.printStackTrace();
        return;
    }

    try {
        executeProcedure();
    } catch (SQLException ex) {
        ex.printStackTrace();
        return;
    }
}

private static void executeProcedure()
    throws SQLException
{
    Connection conn = DriverManager.getConnection(
        COMPOSITE_URL, COMPOSITE_USER, COMPOSITE_PASSWORD);

    CallableStatement stmt = conn.prepareCall("{call SP_D1(?,?)");
    stmt.registerOutParameter(1, Types.OTHER);
    stmt.registerOutParameter(2, Types.OTHER);
    stmt.execute();

    printResultSet((ResultSet)stmt.getObject(1));
    printResultSet((ResultSet)stmt.getObject(2));

    stmt.close();
    conn.close();
}

private static void printResultSet(ResultSet rs)
    throws SQLException
{
    ResultSetMetaData metaData = rs.getMetaData();
    int rowIndex = 0;
    while (rs.next()) {
        System.out.println("Row " + rowIndex++);
        for (int i=1; i<=metaData.getColumnCount(); i++) {
            System.out.println(" Column " + i + " " + metaData.getColumnName(i) +
                " " + rs.getString(i));
        }
    }
}
}

```



## Using Design Procedure By Example for Introspected Procedures

You can use Studio or you can use the command line to complete the steps. These steps help make use of database procedures that have cursor outputs that might not be detectable by TDV until after the procedure has been executed by TDV.

These steps are helpful if you have Oracle procedures with cursor outputs that you want to use in further data customizations within TDV.

### To use the design procedures by example functionality

1. Execute the procedure. For more information, see [Executing a Procedure or Parameterized Query, page 224](#).
2. Provide valid input values to the procedure.
3. Review the cursor output and review the data type information.

TDV automatically does this for you, but reviewing at this stage can help you decide how you might want to make use of the data.

4. Save the cursor and data type information.
5. Use the saved information to design other TDV resources.

Alternatively, you can make use of the following API call from the command line or within a script:

```
designProcedureByExample <path> <inputs> <commitChanges>
```

- Provide the path to the procedure with the output cursors that you want TDV to execute.
- Provide valid input values for the procedure that you want TDV to execute.
- Set commitChanges to TRUE to save the output cursor metadata to the TDV repository for the procedure.



# Using Transformations

---

This topic describes how to design transformations that are saved as procedures to query and manipulate data stored in a data source

The data for modeling can come from a mix of relational (tabular) and hierarchical (such as XML) sources. Having tools to help you transform your data is helpful when designing your data virtualization layer.

This section assumes that you understand XML, XQuery, and WSDL.


- [Studio Transformation Types, page 232](#)
- [Creating an XML, XSLT, or Streaming Transformation, page 234](#)
- [Creating an XQuery Transformation, page 240](#)
- [Upgrading XML to Tabular Mapping Transforms, page 249](#)
- [Executing a Transformation, page 251](#)
- [Converting XML to JSON using Design By Example, page 252](#)
- [JSON XML List Formatting Example, page 253](#)

Information about the Any-Any Transformation Editor is in:

- [Using the Any-Any Transformation Editor, page 255](#)

## Studio Transformation Types

Studio has a built-in transformation mechanism.



You can use to create the following types of transformations:

Type	Description
Any-Any Transformation	<p>The Transformation Editor allows you to transform data from any type of data source structure to any type of target.</p> <p>The transformation of the data will happen in real time. Where possible the queries are pushed to the data source for execution. Data will be streamed, if possible, from the source to the target.</p>
XML to Tabular Mapping	<p>This transformation accepts an XML or WSDL source as input, and generates a tabular mapping to the elements in the source schema.</p> <p>The mapping can be thought of as producing a set of rows, each of which represents a node in the original XML document.</p>

Type	Description
XSLT Transformation	<p>The XSLT transformation lets you define how the XML data should be transformed using a graphical editor in Studio. It accepts an XML or WSDL source as input. Complex transformations are possible by writing custom XSLT. The only requirement is that the XSLT must produce tabular data with the following structure:</p> <pre data-bbox="496 361 821 685"> &lt;results&gt;   &lt;result&gt;     &lt;column_one&gt;a&lt;/column_one&gt;     &lt;column_two&gt;b&lt;/column_two&gt;     &lt;column_three&gt;c&lt;/column_three&gt;   &lt;/result&gt;   &lt;result&gt;     &lt;column_one&gt;d&lt;/column_one&gt;     &lt;column_two&gt;e&lt;/column_two&gt;     &lt;column_three&gt;f&lt;/column_three&gt;   &lt;/result&gt; &lt;/results&gt; </pre>
Streaming Transformation	<p>The Streaming transformation lets you define how the XML data should be transformed using a graphical editor in Studio. This transformation is useful for transforming a large amount of XML data. This transformation does not require the entire XML source document to be realized in memory.</p>
XQuery Transformation	<p>The term <i>XQuery</i> stands for XML Query, a query that returns results in the form of an XML document.</p> <p>An <i>XQuery transformation</i> is a TDV resource that reads data from related sources, such as tables, views, and procedures, and assembles that data into an XML document that conforms to a user-specified schema called the <i>target schema</i>. An XQuery transformation looks and acts like any other procedure in the TDV system.</p> <p>Underlying an XQuery transformation is an <i>XQuery procedure</i> that is run by an XQuery processor.</p> <p>The target schema for the output XML document can be created or edited in the definition set editor.</p> <p>Studio also provides a graphical editor for mapping the target schema and tabular sources that are to supply the data for the XQuery in the transformation.</p>

## Creating an XML, XSLT, or Streaming Transformation

The steps you follow to create an XML to tabular, XSLT, or streaming transformation include:

- [Adding a New Transformation \(XML, XSLT, or Streaming\)](#), page 235
- [Adding an XSLT Transformation for a Table, a View, or a Function](#), page 236
- [Mapping Source Data to Target Output Columns \(XSLT or Streaming\)](#), page 236 (XSLT and streaming only)
- [Adding Target Columns through the Outputs Panel \(XSLT\)](#), page 239 (XSLT only)

Adding target output columns is optional.

### XSLT Transformation Limitation

The Data Map panel of the XSLT transformation does not display input fields for tables, views, and functions. Because the XSLT transform requires that the object being transformed has a Schema to generate Input Fields for the object.

TDV automatically generates a schema for XML-File data sources and WSDL data sources.

### XML to Tabular Mapping

This transformation accepts an XML or WSDL source as input, and generates a tabular mapping to the elements in the source schema.

The mapping can be thought of as producing a set of rows, each of which represents a node in the original XML document. The XML document is converted into a table that represents the document's data and nodes, as described in the following table.

Column Name	Column Type	Description
id	INTEGER	Unique identifier for an element or attribute value.
parent_id	INTEGER	Unique identifier for the parent of this element.
depth	INTEGER	Number of elements in the path.
name	VARCHAR	Local name of the element or attribute.
xpath	VARCHAR	Xpath expression that fully describes the location of the element or attribute.


Column Name	Column Type	Description
path	VARCHAR	Path to the element or attribute. The path consists of a forward-slash-separated list of enclosing element names, ending with the local name of the element or attribute.
position	INTEGER	Position of this element relative to the path attribute.
value	VARCHAR	Value of the element or attribute.

## Adding a New Transformation (XML, XSLT, or Streaming)

The steps to add an XML, XSLT, or streaming transformation are the same.

### To create an XML, XSLT, or streaming transformation

1. Have an XML or WSDL source for the transformation ready, and know its location on the server.
2. From the resource tree, right-click and select **New Transformation**, or select File > New > Transformation.
3. In the New Transformation window, specify the type of transformation (XML to Tabular Mapping, XSLT Transformation, or Streaming Transformation), and click Next.



4. Locate and select an appropriate XML source for the transformation in the displayed tree.
5. Type a name for the transformation in the **Transformation Name** field.
6. Click **Finish**.

When you click **Finish**, the transformation is added to the resource tree, and the editor for the transformation opens in the right pane.

If the transformation is of the type XML to Tabular Mapping, it is ready to be used like any other procedure. In other types of transformations—**Streaming** and **XSLT**—the source elements and target output columns need to be mapped. (See [Mapping Source Data to Target Output Columns \(XSLT or Streaming\)](#), page 236.)

## Adding an XSLT Transformation for a Table, a View, or a Function

The XSLT transform requires an XML schema and you can only use it indirectly on a table, view or function.

### To add an XSLT transformation on a table, view, or function

1. Create an XML Definition Set to act as an XML schema if one does not exist.
2. Within Studio, create a procedure to act as a wrapper for the object.
3. Edit the procedure so that it uses a tag from the XML Definition Set as its return type.

## Mapping Source Data to Target Output Columns (XSLT or Streaming)

The **Data Map** panel (see [Data Map Panel](#), page 617) is available for XSLT transformations and streaming transformations. This panel lets you create and modify target output columns, map elements from the source XML document to the targets.

The following guidelines apply when using the **Data Map** panel:

- When you map source elements to target output columns in the **Data Map** panel, the XSLT is automatically generated in the **XSLT** panel.
- If you edit the text in the **XSLT** panel, the **Data Map** panel is permanently disabled. In this situation, design the outputs in the **Outputs** panel.
- You can map a source to more than one target, but you cannot map a single target to more than one source.
- The data types of the source and the target should match. Even if the data types do not match exactly, the link is valid if one data type is castable to the other.
- The target name is displayed as a column name in the output when the transformation is executed.
- When a link is selected, it is displayed as a thick line.



On the **Data Map** panel, you can:

- Manually create target columns and map them to source XML data.
- Automatically create target columns and map them to source XML data.
- Rename a target column and change its data type.
- Unlink or move targets.


### **To manually create target columns and map them to source XML data**

1. If necessary, open the transformation.  
The transformation editor displays the **Data Map** panel.
2. If necessary, expand the nodes in the **Source** column to display all XML source definitions.
3. In the **Target** column, select the **outputs** node or an existing column, click **Add** ( ) in the toolbar, and select the data type for the output column from the drop-down list.  
An output column with a default name is created. You can create as many target columns as you need.
4. Connect a source and a target by selecting them individually and clicking the **Create Link** button.
5. Save your edits.

### **To automatically create target columns and map them to source XML data**

1. If necessary, open the transformation.  
The transformation editor displays the **Data Map** panel.
2. If necessary, expand the nodes in the **Source** column to display all XML source definitions.
3. Select the source in the **Source** column.
4. Click the **Create Link And Target** button.

A target with the same name and data type of the source is created in the **Target** column, and a link is also created between the source and the target.



Selecting multiple sources and clicking **Create Link And Target** creates a separate target and link for each source. Selecting a source and clicking **Create Link And Target** several times creates that many targets and links pointing to the same source.

5. Save your edits.

### To rename a target column and change its data type

1. If you want to rename a target, right-click the column name, select **Rename**, and supply a new name.
2. If you want to change the target's data type:
  - a. Right-click the target name and select **Change Type** from the menu  
Or  
Select the target and click the **Change Type** toolbar button.
  - b. In the **Choose Data Type** window, click the data type name and select a data type from the drop-down list.
  - c. Optionally, specify the length or the number of digits for certain data types.
  - d. Click **OK**.

### To unlink or move targets

1. To unlink a target and a source, grab and drag the link away from the target or source, and release the mouse button.  
You can also select the link and click the **Delete** button to unlink a target and a source.
2. To align a target with its source, highlight the target and move it up or down using the up or down button.
3. Save your edits.

## Adding Target Columns through the Outputs Panel (XSLT)

When you add target output columns through the **Outputs** panel for XSLT transformations, the XSLT in the XSLT panel is not automatically updated. You must manually update the XSLT.

For descriptions of the panels, see [XSLT Panel for XSLT Transformations, page 617](#) and [Outputs Panel, page 618](#).

You can map an element in the source document to an XML-typed column in the result. When you do this, the element's entire sub-tree (attributes, namespaces, child elements, and contents) in the XML source document becomes the text of the XML typed column. This includes the element itself.


This feature allows you to map a subtree of the source XML document to a column of type XML or VARCHAR in the transformation output cursor.

You cannot make such a mapping through the **Data Map** panel. You must make this mapping by customizing the XSLT that is generated.


### To add target output columns through the XSLT and Outputs panels

1. If necessary, open the transformation.
2. Edit the XSLT in the **XSLT** panel, as needed.  
If you edit the XSLT in the **XSLT** panel, the **Data Map** panel is permanently disabled, but the **Outputs** panel becomes editable (**Change Type**, **Delete** and **Rename** on a context menu) and the **Add** button in the **Outputs** panel toolbar is enabled.
3. Optionally, on the **Outputs** panel add target output columns, the same way you would design parameters for a SQL script on the **Parameters** panel.

See [Designing Parameters for a SQL Script](#), page 189.



- Update the XSLT in the **XSLT** panel to correspond to any output elements you added.



- Save the transformation.

## Creating an XQuery Transformation

This topic describes how to create an XQuery transformation.

### To create an XQuery transformation

- Have an XML definition set ready. The definition set provides the target schema for the output document.  
For details on creating a definition set, see [Definition Sets](#), page 297.
- Select a folder in the Studio resource tree, and then right-click and select New Transformation, or select File > New > Transformation.
- In the New Transformation window, select XQuery Transformation and click Next.

4. Supply a name for the transformation in the **Transformation Name** field.
5. Locate and select the XML definition set in the resource tree displayed in the left panel.
6. In the right panel, where all the elements in the XML definition set are displayed:
  - a. (Optional) Expand the nodes and view the elements to see what is available.
  - b. Select a top-level element.


This top-level element determines the type and name of the root element in the output XML document.

To have many top-level elements available for selection, use an XML definition set similar to UserSchema, which you can find in Data Services/Web Services/system/admin/

7. Click **Finish**.

The transformation is added to the resource tree, and its editor opens in the right pane displaying the **Model** panel by default. The **Model** panel in the XQuery transformation lets you map source data to the target schema and transform tabular data into XML data.

The following sample entries in the Model panel of an XQuery transformation named InventoryTransactions. Cells that are not appropriate to the transformation are dimmed; the other cells remain white.



8. Use the following sections to complete the definition of this transformation:
  - [Specifying a Target Value, page 242](#)
  - [Viewing the Source Scope, page 243](#)
  - [Specifying the Source for a Top-Level Element, page 245](#)
  - [Specifying Settings for Target Sources in an XQuery Transformation, page 245](#)
  - [Specifying Global Input Parameters in an XQuery Transformation, page 247](#)
  - [Viewing and Editing the XQuery, page 247](#)
  - [Viewing Output Parameters in the XQuery Transformation, page 248](#)

## Specifying a Target Value

You can specify a value for any target that has a white cell in the Target Value column for its row. The Target column displays the XML schema that is uploaded (through the definition set) for this transformation. This is the target schema for the XML document that the XQuery would return. Expand the nodes in this column to view the target elements.

The tree-structure display in the Target column represents the hierarchical structure of the elements in the target schema. Elements followed by square brackets are unbounded, meaning that their occurrence is unlimited. Elements rendered in italicized type are optional.

The Target Value column (available for table columns, not for tables) contains the actual expressions (projections) that determine the values for the elements in the **Target** column. The expression (projection) in each cell is relative to the views, tables, and procedures that are currently in scope. The **Target Value** column is similar in functionality to the column named **Column** in the view editor's **Grid** panel.

### To specify a target value

1. If necessary, click the **Expand All Rows** toolbar button to see the tables and columns you need to edit.
2. Click the cell below **Target Value** corresponding to the target table's row.
3. Select a value from the drop-down list, or type a value.
4. If the source settings are not displayed in the lower section of the editor, click the **Show Source Settings** toolbar icon, or click an icon in the **Source Settings** column.

Tabs open in the lower part of the editor showing the settings for a source: a join XPath expression (**Join** tab), a filter XPath expression (**Filter** tab), a sort order (**Sort Order** tab), or an input parameter (**Inputs** tab) as in a procedure. The **Schema** tab shows the schema for the selected source.

Name	Type / Reference	Native Type
TransactionID	INTEGER	int(11)
TransactionDate	DATE	date
ProductID	INTEGER	int(11)
PurchaseOrderID	INTEGER	int(11)
TransactionDescription	VARCHAR(255)	varchar(255)
UnitPrice	DECIMAL(19,0)	decimal(19,0)
UnitsOrdered	INTEGER	int(11)
UnitsReceived	INTEGER	int(11)
UnitsSold	INTEGER	int(11)
UnitsShrinkage	INTEGER	int(11)

- Specify a join relation between the current source and one of its direct ancestors in the **Join** panel.

For example, **PurchaseOrderID = \$INV/PurchaseOrderID** means that **PurchaseOrderID** in **PurchaseOrder** is joined to **PurchaseOrderID** in the ancestor **InventoryTransactions**.

- Specify a filter on the current source (the equivalent of a **WHERE** clause in a **SELECT** statement) in the **Filter** panel.

For example, **\$INV/TransactionID > 25** is a filter on **TransactionID** in the **Source** named **inventorytransactions**. The filter is used to constrain the data returned from this resource.

- Specify the order in which the results from the current resource are to be sorted for the XML document (the equivalent of an **ORDER BY** clause in a **SELECT** statement) in the **Sort Order** panel.
- Specify the values for a source's inputs if the source is a procedure with input parameters in the **Inputs** panel.
- Click the icon in the **Source Settings** column at any time to view or edit the setting.

## Viewing the Source Scope

Before you view drop-down lists in the **Target Value** column, you might want to widen the column so you can see entire names.

The **Source** column (available for tables) lets you specify the tabular sources that provide data for the resulting XML document. Each source specified in this column corresponds to a top-level element (non-leaf node) in the target schema.

Resources specified in the **Source** column exist in a “scope” relative to the target XML document to which they provide data. At a particular location in the document, the source scope is defined as:

- The current resource (table, view, or procedure)
- All the resources that are directly above this resource in the document (direct ancestors)
- The input to the XQuery

The scope defines what resources are available to the value expression.

The scope for **Transaction** is its own source, the `inventorytransactions` table, and the global input **SupplierName**.

The scope for **PurchaseOrder** is its own source, the `purchaseorders` table, its direct ancestor, the `inventorytransactions` table, and the global input **SupplierName** (line #2).

The scope for **Supplier** is its own source, the `suppliers` table, its direct ancestors, the `purchaseorders` and `inventorytransactions` tables, and the global input **SupplierName** (line #3).

The scope for **Product** is its own source the `LookupProduct` procedure, its direct ancestor `inventorytransactions` table, and the global input **SupplierName** (line #4). The sources (`purchaseorders` and `suppliers`) in the scope of its sibling or peer resource (**PurchaseOrder**) are excluded from the scope of **Product**.


The **Source Alias** column (available for tables) lets you specify aliases for the sources in the **Source** column. The aliases are used when join conditions, filters, and inputs are supplied for a source value. This column is populated automatically when a resource is added to the **Source** column, but it can also be edited as a text field.

The **Source Settings** column (available for tables) displays icons indicating that certain settings have been specified for the corresponding source. When clicked, these icons display the corresponding settings in the lower section of the editor. For example, you can click the **Schema** icon to display the schema for the corresponding source.



### To view the source scope for an element

1. Click a cell in the **Target Value** column.
2. View the drop-down list.



Multiple input parameters are shown at the end of the drop-down list, in the order in which they were defined in the **Inputs** panel.

## Specifying the Source for a Top-Level Element

Top-level elements (which have leaf nodes under them) have white cells in the Source column corresponding to their rows. The Source column (available for tables) lets you specify the tabular sources that provide data for the resulting XML document. Each source specified in this column corresponds to a top-level element (non-leaf node) in the target schema.

### To specify the source for a top-level element

1. Double-click the cell corresponding to a top-level element in the **Target** column; or select its top-level element in the **Target** column.
2. Click the **Choose Source** toolbar button).
3. In the **Choose a Table or Procedure** window that opens, select the source.

## Specifying Settings for Target Sources in an XQuery Transformation

To specify the sources, values, and other settings for target sources in the

## XQuery transformation

1. In the **Model** panel, specify the sources, target values, and source aliases to provide the data and constraints for the output XML document.

In the current example, the top-level elements in the **Target** column are **Inventory Transactions**, **Transaction**, **PurchaseOrder**, **Supplier**, and **Product**. You can specify a source for each of these elements.

2. To specify a source:
  - Double-click the **Source** cell corresponding to the top-level element in the **Target** column.

Or

- Select the top-level element in the **Target** column and click the **Choose Source** toolbar button.

3. In the window that opens, select the source table and click **OK**.
4. If you want to change the automatically assigned alias, type a different alias in the **Source Alias** column for the source you just added.

The aliases are used when join conditions, filters, and inputs are supplied for a source value.

5. To specify a value for a target, click the **Target Value** cell corresponding to the target in the **Target** column, and select a value from the drop-down list, as follows.

For a target value, you can supply a literal value or a system function to be evaluated at runtime. Literal values must be enclosed in single or double quotes.

6. To specify a source setting, click the appropriate icon in the **Source Settings** column, or click the **Show Source Settings** toolbar icon to display the source settings panel in the lower section if it is not already visible. Then open the **Join**, **Filter**, **Sort Order**, or **Inputs** panel and supply the settings.

`PurchaseOrderID = $INV/PurchaseOrderID` (in the **Join** panel) means that **PurchaseOrderID** in **PurchaseOrder** is joined to **PurchaseOrderID** in the ancestor **InventoryTransactions**. The syntax for the value expression `$INV/PurchaseOrderID` contains a reference to the alias (**INV**) for the parent source **inventorytransactions** preceded by the dollar sign (**\$**).

7. To supply a value for an input parameter, if the source is a procedure that has input parameters, use the **Inputs** panel (in the source settings panel).
  - a. Click the **Inputs** tab to open the **Inputs** panel.
  - b. Click the **Inputs** icon in the **Source Settings** column.

In the **Inputs** panel, the names of the inputs are displayed, and the **Is NULL** check box is selected by default.


- c. Click the row in the **Value** column, and select an appropriate value for the input parameter in the drop-down list.

## Specifying Global Input Parameters in an XQuery Transformation

You can specify global inputs to the XQuery, which are subsequently available to be mapped (as values) to any compatible element in the target schema.

### To specify global input parameters in an XQuery transformation

1. Click the **Inputs** tab (in the upper section of the editor).
2. Click **Add** in the toolbar, and specify the data type for the input parameter.



3. Rename the parameter as needed.

This input parameter is available in the **Model** panel, and you can specify it as a target value for an appropriate target element.


4. (Optional) Click the **Outputs** tab to view the outputs.
5. Save the transformation.

## Viewing and Editing the XQuery

After specifying all required sources, values, and other settings for target sources, you can view and edit the resulting XQuery.

### To view and edit the XQuery

1. Click the **XQuery** tab in the editor to view the auto-generated XQuery for the model you designed in the **Model** panel.




2. View and edit the XQuery text in this panel as necessary.  
Editing the XQuery permanently disables the **Model** panel for the current transformation.
3. Save any changes you have made to the transformation.

### Viewing Output Parameters in the XQuery Transformation

You can view the output parameters in the XQuery transformation.

## To view the output parameters in the XQuery transformation

1. Specify the sources, values, and other settings for target sources as needed.
2. Select the **Outputs** tab in the editor to view the output parameters. The output parameters shown in the **Outputs** panel are rendered as elements in the output XML document.



For details on executing the transformation, see [Executing a Transformation](#), page 251.

## Upgrading XML to Tabular Mapping Transforms

If you have existing XML to Tabular Mapping transforms that you would like to update to be compatible and editable using the Any-Any Transformation Editor, you can follow the steps in this section to accomplish that. There are two different upgrade paths:


- [Upgrading and Creating a Backup of an XML to Tabular Mapping Transform](#), page 250
- [Creating an Upgraded XML to Tabular Mapping Transform](#), page 250

## Upgrading and Creating a Backup of an XML to Tabular Mapping Transform

The steps in this task will keep the name of your existing transform as is and convert it to the new Any-Any style of transform, it will also create a backup XML to Tabular Mapping transform saved with the name given.

### To upgrade and create a backup of an XML to Tabular Mapping transform

1. Make sure that your TDV Studio environment is running the latest service pack and that `server_util.sh -reset namespace` has been run to update the TDV Server and repository.
2. Open Studio.
3. Locate an existing XML to Tabular Mapping transform in your Studio navigation tree.
4. Select the transform, right-click and select Upgrade Transform.



5. Select the top radio button, accept or rename the transform to a name that will be easy to understand later.
6. Click **OK**.


The Studio navigation tree is updated. Your transform is converted and a new backup of the old XML to Tabular Mapping transform is add to the tree.

## Creating an Upgraded XML to Tabular Mapping Transform

The steps in this task will rename your existing transform and convert it to the new Any-Any style of transform.

### To upgrade an XML to Tabular Mapping transform

1. Make sure that your TDV Studio environment is running the latest service pack and that `server_util.sh -reset namespace` has been run to update the TDV Server and repository.
2. Open Studio.
3. Locate an existing XML to Tabular Mapping transform in your Studio navigation tree.
4. Select the transform, right-click and select Upgrade Transform.



5. Select the bottom radio button, and accept or rename the transform to a name that will be easy to understand later.
6. Click **OK**.
7. Click Refresh All to refresh the Studio navigation tree with the upgraded transform.
8. Optionally, open the new transform and edit it for your current needs.

## Executing a Transformation

If the executed transformation is an XQuery transformation, you can save the result as an XML file and view it in a browser.

### To execute a transformation

1. In Studio, open the transformation.
2. Click the **Execute** toolbar button.

If there is no need for an input parameter value, the procedure is executed immediately.

3. If you need to supply a value for one or more input parameters, type a value or select **Null** (default) for each field in the **Input Values for <resource>** dialog.

Do not enclose string values in quotes.

4. In the **Input Values for <resource>** dialog, click **OK**.
5. If the executing task is successful, the **Result** tab displays the result set, fifty rows at a time.
6. In the **Result** panel:
  - a. To view the next fifty rows in a large result set, click **Next**.
  - b. To view the details of a specific row, select the row and click **Details**. For some extremely large results, such as those generated by using **EXTEND** on an array to generate **BIGINT** number values, some of the data might be truncated without a visual indication by Studio.
  - c. To save the results, use **Save to File**.
  - d. To clear what is displayed in the tab, click **Clear**.

## Converting XML to JSON using Design By Example

If using one of the standard transform methods doesn't work for you for some reason, it is possible that you can convert XML to JSON using the Design By Example functionality that exists within TDV.

### To convert JSON to XML form (or Tabular form)

1. Create a REST data source.
2. Select JSON format.
3. Add a new operation.
4. Introspect the operation.
5. Open the Operation and for Header/Body Parameters, select Design by Example.
6. Select an element.
7. Execute the operation.
8. Review the XML that is returned.



## JSON XML List Formatting Example

Formatting lists using JSON can be done in many ways. Typically, they are done using a nested element in XML. The following example gives one option. There are many others. Consulting a good JSON reference can help you determine how best to format the list that you need to create.

```
"https://www.facebook.com/sacramentosports?ref=br_tf": {  
  "about": "Welcome to the official Sacramento Sport Facebook Page!",  
  "affiliation": "National Basketball Association, Western Conference, Pacific Division",  
  "category": "Professional sports team",  
  "category_list": [  
    { "id": "109976259083543", "name": "Sports Venue & Stadium" }  
  ],  
  { "id": "189018581118681", "name": "Sports Club" }  
],  
"checkins": 7149,  
"is_published": true,  
"location":  
{ "street": "One Sports Way", "city": "Sacramento", "state": "CA", "country": "United States", "zip": "95834",  
  "latitude": 38.64906488403, "longitude": -121.51807577132 }
```



# Using the Any-Any Transformation Editor

---

Before using the Transformation Editor there are a few concepts that you can familiarize yourself with. This topic also covers the basic usage of the Transformation Editor.

- [Transformation Editor Concepts, page 255](#)
- [Using the Transformation Editor, page 260](#)
- [Caching Transform Data, page 295](#)

Tutorials that walk you through the creation of several different types of Any-Any transforms can be found in the *TDV Tutorials Guide*.

## Transformation Editor Concepts

The Transformation Editor is an editor within TDV that can be used to define the transformation rules for the source data sets. It can transform data from any source structure to any target structure. The transformation of the data happens in real time as data is streamed, if possible, from the source to the target. The source and target are not persistent structures.

A transformation is a procedure in TDV and it can be used by other resources in TDV as a procedure. When caching is enabled on a transform, it is cached in the same way as any other procedure in TDV. It produces XQuery code that is used to execute the transformation. The XQuery code is not directly editable.

The Transformation Editor can map and transform data to and from the following:

- Relational (Cursors)
- XML (Hierarchies)
- Scalar (Procedures)


You can also browse to and drag existing resources defined in Studio into the Transformation Editor. Concepts in other sections under this topic include:

- [The Transformation Editor Window, page 256](#)
- [Transformation Editor Terminology, page 257](#)
- [About Transformation Editor Operations and Parameter Containers, page 257](#)
- [Transformation Editor Limitations, page 258](#)

## The Transformation Editor Window

The following graphic identifies the main components of the Transformation Editor window.

Transformation Editor




Palette

Workspace

## Transformation Editor Terminology

The following graphic identifies some of the detailed components of the Transformation Editor window.



## About Transformation Editor Operations and Parameter Containers

Each of the following Transformation Editor operations can be used to define the logic associated with the transformation:

Name	Description
Cast	Use to convert one data type to another data type.
Expression	Use to define an expression that can be used to compute results.
in	Container for the input parameters for the transform. This container can be empty and not connected to any object on the workspace.
Loop	Use to generate target sequences based on a source sequence.
out	Container for the transformation outputs. This container cannot be empty.

Name	Description
Query	Use to join, filter, and group data.
Resource	Use to add a table, view, XML file, SQL script, or other valid TDV resource to the Transformation editor.
Switch	Use to conditionally map a target from one of a set of sources.  You can have any number of inputs, and one output. Each input has an expression associated with it. The first expression that evaluates to true causes its associated input to be passed through as the output.
Union	Use to combine the result sets of two or more items in your transform. All the source inputs must have the same data type. Unions can be used to remove duplicate rows between the items that are input.

## Transformation Editor Limitations

There are limitations when using the Transformation Editor:

- Loop chaining is not supported.  
A loop iterator that contains a sequence cannot be used as the source of another loop. To work around this:
  - Instead of multiple loop operations, use a single loop with multiple iterators.
  - Map the child sequence to a child transformation and perform the required secondary looping within that child transform.
- XML Limitations
  - XML substitution groups are not currently supported.
  - XML type restrictions are not supported. The Transformation Editor can use XML types with restrictions, but the restrictions are currently ignored.
  - XML `any` and `all` elements and groups are not fully supported.
  - Some TDV procedures output XML without a schema. The ability to use such procedures might be limited.
  - The XML File, Web Service, and XML/HTTP data sources automatically generate or provide the ability to associate the data source's XML definitions set with the signatures of the resources within those data sources. This allows the Transformation Editor to operate using the XML schemas associated with these resources. If your existing data sources do

not have the associated definition set, you can try re-introspecting or recreating them to get it.

- XML unions (element-based) are not supported. However, XML choices are supported and appear as a canonical Union type within the Transformation Editor.
- Code Generation
  - Query and Join hints are only applied to queries that will be optimized into SQL.
  - SQL push optimizations are only applied to query operations and the sources they directly depend upon.
  - There is no indicator of whether or not a query will be generated as XQuery or SQL. You will need to look at the generated source code to see whether it was optimized or not. In general, if a query's sources are relational, SQL will be generated.
  - No runtime schema validation is performed.
- Other Limitations
  - There is no technique to perform element selection. Transformations that make decisions based on element names are not supported.
  - Cross joins are not supported.
  - There is no way to handle case-sensitivity mismatches.
  - There is no literal format for durations.
  - The cast operation is not supported for casting to a complex structure. If you need to cast the children of a structure, you must assign the structure field by field and insert casts as appropriate for each of the fields. If the structure is a sequence, you can insert a loop operation into your mapping to iterate over all the elements and then provide the individual assignments (with appropriate casting) to the target structure.
  - There are several SQL functions that do not work well. These include: CAST, CORR, COVAR\_SAMP, STDDEV, STDDEV\_POP, STDDEV\_SAMP, SUM\_FLOAT, VAR\_POP, VAR\_SAMP, VARIANCE, VARIANCE\_POP, VARIANCE\_SAMP, XMLATTRIBUTES, XMLFOREST, XMLQUERY
  - Creating placeholders for intermediate values is not allowed. The workaround is to invoke a child transformation and use the outputs of that transformation as a reference for the intermediate values you want to

reuse. Invocations of child transformations are optimized to avoid the overhead of a full TDV procedure invocation.

- If you rename an element that is directly based on an XML element, the transformation may not work. Avoid renaming element based on XML elements. When you create an element based on an XML element, it normally gets a default name and namespace that matches the XML element. This can be fixed by renaming the element to match the native XML element name.

## Using the Transformation Editor

This topic covers basic usage and some common use cases for the Transformation Editor. Transforms can be used to convert data from one type of structure to another, to insert calculations, and to otherwise change the data in ways that are typical for data processing and analysis.

Data can be transformed between relational and hierarchical structures.

This section describes how to perform basic actions within the Transformation Editor:

- [Creating a New Transform, page 261](#)
- [Undoing and Redoing Actions in the Transformation Editor, page 262](#)
- [Zooming and Arranging the Model, page 262](#)
- [Editing Operations in the Transformation Editor Model, page 263](#)
- [Adding Resources, page 265](#)
- [Working with Connections and Loops, page 265](#)
- [Working with Operations, page 275](#)
- [Working with Operation and Parameter Container Details, page 282](#)
- [Deleting Operations in the Transformation Editor, page 288](#)
- [Working with Messages, page 289](#)
- [Editing Parameters on the Parameters Tab, page 291](#)
- [Viewing and Copying the XQuery Code From Your Transform, page 294](#)
- [Validating the Transform XQuery Code Using Studio, page 294](#)
- [Rebinding Transformation Operations, page 292](#)
- [Working with the Transformation Editor XQuery Tab, page 293](#)



Use-case tutorial that describes using the Transformation Editor to combine the various elements to create a procedure are included in the *TDV Tutorials Guide*.

## Creating a New Transform

Transforms, like procedures, are resources that are available from the Studio resource tree.

### To create a new any-any transformation

1. Select a folder in the Studio resource tree.
2. Right-click and select New Transformation, or select File > New > Transformation.
3. Select **Any-Any Transformation**.
4. Click **Next**.
5. Type a name for the transformation.
6. Click **Finish**.

When you click Finish, the transformation is added to the resource tree, and the Transformation Editor opens in the right pane.

7. To add items, see the instructions in
  - [Editing Operations in the Transformation Editor Model, page 263](#)
  - [Designing a Query Operation, page 275](#)
  - [Adding Expression Operations, page 274](#)
  - [Adding Cast Operations from the Palette, page 277](#)
  - [Adding Union Operations, page 278](#)
  - [Adding Switch Operations, page 279](#)
8. To draw lines between the items, see the instructions in [Adding Assign Links, page 266](#) or [Adding Loop Links, page 266](#).
9. Right-click items on the editor to get a menu with available actions. Most items have:

Copy	Add Parameter	Edit	Change Type
Rename	Change Facets	Delete	Cut


10. Save your transform.

## Undoing and Redoing Actions in the Transformation Editor


The Transformation Editor provides undo and redo capability.

### To undo and redo actions in the Transformation Editor

1. Open your transform.
2. Edit your transform as necessary.
3. To undo a previous action select Edit > Undo <action> from the Studio menu.



4. To redo an action, select Edit > Redo <action>.



5. Save your transform.

## Zooming and Arranging the Model

The Transformation Editor view and certain operations on the model can be expanded and collapsed. Searching the model for specific items is also possible. Selections made for zoom and positioning of operations on the Model tab are temporary only. Studio regularly attempts to auto-arrange the view on the Model tab.

### To auto-arrange things on the Model

1. Open a transform.
2. Click Refresh Layout.

**To zoom the model**

1. Open an existing transform in the Transformation Editor.
2. Use the following zooming tools to expand or collapse your transform model:



- Zoom In
- Zoom Out
- Zoom to Fit Contents
- Full Screen

Your mouse scroll wheel can also be used to zoom in and out.

3. Continue working with the model.

**To grab and pan things in the Transformation Editor Model tab**

1. Right-click and drag anywhere in your model.

**To move things in the Transformation Editor Model tab**

1. Click an operation to select it.
2. Click it again and then drag it to the location where you want it.
3. Arrange your other items.
4. Continue working with the model.

**Editing Operations in the Transformation Editor Model**

Each of the following Transformation Editor operations has editors that can be used to define the logic associated with the transformation:

Resources	Queries	Loops
Switches	Expressions	

When writing expressions, use the inputs of the operation that contains the expression.

### To update operations in the Transformation Editor Model tab

1. Open your transform.
2. Double-click an operation on the Model tab to select it.

Depending on the type of operation you have selected you should get one of the following editors:

Operation Type	Editor	Description
Expressions	Expression Operation Editor	Provides the name given to the expression and an editable text field that you can use to type your valid expression syntax.
Loops	Loop Iterator Editor	Provides the name given to the loop. You can add levels, define item filters, and use the arrows to arrange the nesting of the levels.
Queries	Query Editor	Provides a complex visual modeling tool with three tabs to help you define the query used within your transform.
Resources	Invoke Resource Operation Editor	Provides the name of the resource, the path to the resource in Studio, and a button that can be used to navigate through a Studio resource tree of valid resources for selection.
Switch	Switch Case Editor	You can use the Switch operation with one or more pairs of expressions. The Switch function evaluates each pair of expressions, and returns the result corresponding to the first boolean expression in the list that evaluates to True.
Cast	Choose Data Type	You can use the CAST function converts a value from one data type to another.
Union		There is no editor for this operation. The operation is created with two inputs and one output that you can use to connect the items that you want to union. Use to combine the result sets of two or more items in your transform. All the source inputs must have the same data type. Union removes duplicate rows between the items that are input.

3. Use Close, OK, or other mechanisms to close the editors when you are finished editing.

4. Save your transform.

## Adding Resources

The Transformation Editor can map and transform data to and from relational, XML, or scalar data structures.

You can browse to and drag existing resources defined in TDV into the Transformation Editor.

**Note:** The XQuery and XSLT procedures cannot be used as resources in the Any-Any Transformation Editor.

### To add resources to the Transformation Editor Model tab

1. Open a transform.
2. Locate the resource that you want to add from the Studio resource tree.
3. Click-and-drag that resource onto the Transformation Editor workspace.

Or

1. Open a transform.
2. Click-and-drag the Resource palette icon onto the Transformation Editor workspace.
3. Right-click it and select Edit Resource.
4. Click Choose Resource or type the full Studio resource tree path to the resource you want to use.
5. Optionally, from the Select Resource window navigate to and select your resource, then click **OK**.
6. Click **OK**.

## Working with Connections and Loops

Connections and loops help define how data within the transform is processed. This section includes the following topics:

- [Adding Assign Links, page 266](#)
- [Adding Loop Links, page 266](#)
- [Using Auto Map Link Mode, page 267](#)
- [Using Auto Fill Link Mode, page 268](#)
- [Editing Loop Operations, page 269](#)

- [Adding Cast Operations to Connection Lines, page 271](#)

## Adding Assign Links

Links are arrows that you draw between resources to indicate direction of the data transformation. Assignments are used to map data movement between sources and targets.

### To add assign links in the Transformation Editor Model tab

1. Select the Assign Link Mode. Alternatively hold SHIFT key while creating a link (Shift+Minus) Transformation Editor toolbar icon.



2. Click an operation handle, while holding your mouse button down, drag the line to the row you want to connect it to.
3. Save your transform.

## Adding Loop Links

Loop links add more operations to your Transformation Editor model to make it easier for you to define iterations through sequences. If one of the endpoints of a loop link is a loop, a new loop operation is created on the Model tab.

### To add a loop between two operations in the Transformation Editor Model tab

1. Select the Loop Link Mode. Alternatively hold SHIFT key while creating a link (Shift+Minus) Transformation Editor toolbar icon.



2. Click an operation handle, and while holding your mouse button down, drag the line to the row you want to connect it to.
3. Save your transform.


A new box is drawn on the model to represent the loop. Use this new operation to define the behavior of the loop logic.

## Using Auto Map Link Mode

Auto map is a quick way to assign table or view metadata from one operation to another in your transformation. The auto map mode compares the names of the parameters and maps the values that match each other.


### To use the auto map feature

1. Open an existing or create a new transform.
2. Make sure that your transform has at least two operations or resources that contain data structures.
3. Select Auto Map Link Mode.
4. Click and drag the mouse to draw a line between two operations with similar parameters.



5. Release the mouse to connect the two operations.

TDV maps the two structures according to the names that match. For example:



6. Keep or delete the mappings as needed for your transformation.
7. Save your transform.

## Using Auto Fill Link Mode


Auto fill can be used to assign and replicate a metadata structure from one operation into another in your transform. If the target operation of your auto fill action does not have the parameters that are part of the source operation, they are added to the target operation.

### To use the auto fill feature

1. Open an existing or create a new transform.
2. Make sure that your transform has at least two operations or resources that contain data structures as they exist for view, table, or XML schemas.
3. Select Auto Fill Link Mode.
4. Click and drag the mouse to draw a line between two operations with similar parameters.
5. Release the mouse to connect the two operations.



TDV maps the two structures according to the names that match and adds any extra parameters to the target of the auto map. For example:



6. Keep or delete the mappings and parameters as needed for your transformation.
7. Save your transform.

## Editing Loop Operations

Loop operations make it easier for you to define looping references and transformations. Edit the loop to define the behavior of the loop logic. When editing, consider the following limits:

- Loop operations are used to generate sequences.
- The size of the target sequence will match the source sequence.
- The content of the target sequence does not necessarily need to match the source.
- Only the size of the target sequence is controlled by the loop.
- Item filters can be used to limit the size of the target sequence.


SQL functions can be used in the Query operation if the query gets pushed to a SQL database for execution. Outside of the Query operation you can use canonical, XQuery or custom functions.

If your loop operation contains an expression that contains illegal characters you must enclose them in double quotes. The following characters are considered illegal:

\\, [, ], ", (, ), !, @, \$, %, +, \*, ?, {, }, |, ~, <, >, <=, >=

## To edit a loop between two operations in the Transformation Editor Model tab

1. Double-click to select a loop.



Depending on what iterator rows you have connected, the loop editor might have one or more iterator levels already defined.

2. To add a new iterator, click the green circle with a plus symbol in it.

A Name is the name given to the iteration level of the loop which matches the name of the source input of the loop. The Level indicates the nesting level associated with an iterator.

3. To define the filter logic, type text into the Item Filter Field. The item filter is processed every iteration.

Value	Description
True	<p>If the item filter evaluates to true, then the current loop entries used to generate a target sequence item.</p> <p>If the item filter is true, then the target sequence will contain as many items as in the source sequence.</p>
False	<p>If it evaluates to false, it will be skipped.</p>
Complex Expressions	<p>If you provide a more complex expression, output is constrained to data that meets the criteria specified.</p> <p>For example, for <code>totalPrice &gt; 50.0</code>, the loop only outputs entries where the total price is greater than 50.</p> <p>It is only valid for expressions to refer to the input of the loop.</p>


4. Use the arrows to the right of the Item Filter fields to arrange the Filter Name fields in the order that makes sense for the given loop logic that you need to define.
5. Click Close to save your definitions and close the Loop Iterator Editor.
6. Save your transform.

## Adding Cast Operations to Connection Lines

While designing your transform, you might notice that some of the link lines are red or orange, which indicates that there is some error or warning message associated with them that needs fixing. Often the warning message can be fixed by adding a CAST function between the two connected points.

### To add cast operations to connection lines

1. Open your transform.
2. Select a connection that is displayed in orange or red.
3. Right click and select Insert Cast.
4. From the Transformation Editor palette, select Cast.  
The Cast operation is added to the transform.
5. Double-click the Cast operation.



6. Select the data type that you want your data to become.
7. Specify any additional data type details.
8. Click **OK**.
9. Save your transform.

## Working with Expressions


Expressions are so commonly used during the definition of an Any-Any Transform, that this topic has been given extra importance so that you will see it.

- [About Expressions, page 272](#)
- [Adding Expression Operations, page 274](#)

## About Expressions

An expression is a combination of one or more values, operators, and functions that resolve to a value, like a formula. You can use expressions to return a specific set of data. The Transformation Editor can accommodate expressions in queries, loops, switches, and in the stand-alone Expression operation.

When writing expressions, use the inputs of the operation that contains the expression. For example if the operation has an EMP input column named, when you are defining the expression for that operation you can use the EMP input column as a symbol within the expression.



Because of the flexibility required by the Transformation Editor, the expression syntax that is supported is also flexible. Valid expressions can contain operators, names, paths, and literal values. The following table can be used to give you ideas for what you might want to use when defining your Expression.

Expression Components	Description
Operators	Expression operators are used to compute values, for example, with + or -. Operators contain one or two arguments. The supported operators are: NOT, AND, OR, <=, >, <, <>, >=, =, +, *, -, /, and function calls
Names	Valid syntax for names is: [ {namespaceURI}   prefix: ] name  Examples: "customer", "{http://biz.com}customer", "biz:customer"

Expression Components	Description
Paths	<p>Paths can be used to refer to hierarchical elements of input parameters. Paths are names separated by slashes (/).</p>
Literal Values	<p>Literal values for use in expressions include:</p> <ul style="list-style-type: none"> <li>• boolean: true   false</li> <li>• integer: [0-9]+</li> <li>• nil: null</li> <li>• string: 'text'</li> <li>• decimal: [0-9]+.[0-9]*</li> <li>• hexadecimal: 0x[0-9a-f]*</li> <li>• datetime: yyyy-mm-dd [t-hh:mm]   z]</li> </ul>
Function Calls	<p>The Transformation Editor makes use of the following categories of functions:</p> <ul style="list-style-type: none"> <li>• Canonical—A function type that can be used regardless of the target language.</li> <li>• SQL—A function type that can be used only within SQL code.  <p>Queries can be generated into SQL. Use the <code>sql:</code> prefix to specify a SQL function in an expression.</p> </li> <li>• XQuery—A function type that can be used only within XQuery code.  <p>Most operators are generated into XQuery. Use the <code>xquery:</code> prefix to specify a XQuery function in an expression.</p> </li> <li>• Custom—A function type that is defined as custom within TDV.  <p>Use the <code>custom:</code> prefix to specify a custom function in an expression.</p> </li> </ul> <p>The following canonical functions are available for use within expressions:</p> <ul style="list-style-type: none"> <li>• Aggregate: AVG, MIN, MAX, SUM, COUNT</li> <li>• Character: CONCAT, SUBSTRING, UPPER, LOWER, LENGTH, TRANSLATE, REPLACE, MATCHES, CHARACTER_LENGTH</li> <li>• Numeric: ABS, CEIL, FLOOR, ROUND</li> <li>• Date: CURRENT_DATE, CURRENT_TIME</li> </ul>

Canonical functions are built in and cannot be created.

When creating a custom function, the Transformation Editor follows the same rules as for TDV SQL. You create a procedure with one output and promote it as a custom function within the TDV. Using it within a transform, requires the use of the "custom" prefix. For example, if you made a custom function called "amazing", then you'd invoke it within a transform expression using "custom:amazing(x,y,z)".

XQuery functions must be invoked with the "xquery" prefix. For example, to invoke the XQuery concat function, you would use "xquery:concat()". XPath expressions are not supported.

Transform expressions don't allow dashes within symbol names. Replace dashes (-) with underscores (\_).

## Adding Expression Operations

Most operations have an editor that allows you to define expressions.

### To transform your data using Expression

1. Create your transform, for instructions, see [Creating a New Transform](#), page 261.
2. From the Transformation Editor palette, select Expression.
3. Click and drag the mouse anywhere in the Model tab.
4. Double-click the Expression operation that you just added.
5. Use the editor to specify your expression syntax. For example, type syntax similar to any of the following:

— salary < 50000

— EMP > 34

— {http://biz.com}customer/biz:orderID < 900 AND NOT  
 {http://biz.com}customer/biz:customerID = 20

— Sales/finalsale > 1000

If your expression contains illegal characters you must enclose them in double quotes. The following characters are considered illegal:

\, [, ], ', (, ), !, @, \$, %, \*, ?, {, }, |, ~, <, >, <=

6. Save your transform.

## Working with Operations

Operations provide the main processing functionality to transform your data. This section includes the following topics:

- [Designing a Query Operation, page 275](#)
- [Adding Cast Operations from the Palette, page 277](#)
- [Adding Union Operations, page 278](#)
- [Adding Switch Operations, page 279](#)
- [Using the Create Operation Button, page 282](#)

### Designing a Query Operation


The Query editor that can be accessed through the Transformation Editor is similar in behavior to the Studio View editor. Queries allow data to be joined, sorted, grouped, filtered, and projected.

SQL functions can be used in the Query operation if the query gets pushed to a SQL database for execution. Outside of the Query operation you can use canonical, XQuery or custom functions.

#### To transform your data using query


1. Create your transform, for instructions, see [Creating a New Transform, page 261](#).
2. From the Transformation Editor palette, select Query.
3. Click and drag Query anywhere in the Model tab.
4. Double-click the Query operation to obtain a Query editor.
  - On the Join tab of the editor, you can click and drag resources from the Studio resource tree. You can also draw relationship lines between the rows of the resources that have been added. For more information on

similar functionality, see the View editor documentation in the *TDV User's Guide*.



- On the Grid tab you can:
- Specify columns for projection.
- Move the columns up or down to determine their output order.
- Supply aliases for column names.
- Sort columns in ascending or descending order.
- Specify the **GROUP BY** option.
- Specify query constraints in the **WHERE** or **HAVING** clause of the query.
- Add functions and declare variables for the query.





Field	Alias	Output	Sort Type	Sort Order	Group By	Criteria
orderdetails/OrderDetailID	OrderDetailID	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
orderdetails/OrderID	OrderID	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
orderdetails/ProductID	ProductID	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
orderdetails/Quantity	Quantity	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
orderdetails/UnitPrice	UnitPrice	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
orderdetails/Status	Status	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
orderdetails/Discount	Discount	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/CompanyID	CompanyID	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/CompanyName	CompanyName	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/ContactFirstName	ContactFirstName	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/ContactLastName	ContactLastName	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/BillingAddress	BillingAddress	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/City	City	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/StateOrProvince	StateOrProvince	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/PostalCode	PostalCode	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/CountryRegion	CountryRegion	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/ContactTitle	ContactTitle	<input checked="" type="checkbox"/>	UNSORTED		WHERE	
customers/PhoneNumber	PhoneNumber	<input checked="" type="checkbox"/>	UNSORTED		WHERE	

5. Save your transform.

## Adding Cast Operations from the Palette


You can use the CAST function converts a value from one data type to another.

A cast operation is always required when performing a narrowing conversion, such as converting from an xs:string to a VARCHAR.

### To transform your data using cast

1. Create your transform, for instructions, see [Creating a New Transform, page 261](#).
2. From the Transformation Editor palette, select Cast.
3. Click and drag the mouse anywhere in the Model tab.
4. Click to select the Cast operation that you just added.
5. Draw a link from the column that you want to transform with the cast function, to the CAST operation.
6. Save your transform.

## 7. Double-click the Cast operation.



## 8. Select the data type that you want your data to become.


## 9. Specify any additional data type details.

10. Click **OK**.

## 11. Connect the result side of the Cast operation with the column where the data will be consumed next.

## 12. Save your transform.

The following model diagram shows a transform using Cast operations:




## Adding Union Operations

Union functionality provides the ability to combine data into one unified data set. You can specify whether or not to filter out duplicates.

The sources for a union must have exactly the same structure (element names and types) in order for them to be combined using a union operation. The two different spellings of "flag" and "falg" will produce an error. You can create a child transformation to act as an intermediate value or as a structure cast.


## To transform your data using union

1. Create your transform, for instructions, see [Creating a New Transform](#), page 261.
2. From the Transformation Editor palette, select Union.
3. Click and drag the mouse anywhere in the Model tab.



4. Connect at least two parameters from somewhere else in your transform to the Union operation. The two parameters must be of the same data type.
5. Connect the Union operation's result to another operation within your transformation.
6. (Optional) Add more source parameters by:
  - a. Click the Union operation to select it.
  - b. Right-click and select **Add Source** from the menu.
7. (Optional) Select **Distinct**, to indicate that you only want unique values in the outcome of the Union operation.
8. Save your transform.

The following model diagram shows a simple transform using the Union operation:




## Adding Switch Operations

You can use the Switch operation to conditionally control the flow of data from one or more sources. Each source has a corresponding case expression. At runtime, the case expressions are evaluated from top to bottom. The first case expression to evaluate to true causes the corresponding source to be output from the switch.


### To transform your data using switch

1. Create your transform, for instructions, see [Creating a New Transform](#), page 261.
2. From the Transformation Editor palette, select Switch.
3. Click and drag the mouse anywhere in the Model tab.



4. Connect at least one parameter from somewhere else in your transform to the Switch operation.
5. Connect the Switch operation's results to other operations within your transformation.
6. (Optional) Add more source parameters by:
  - a. Click the Switch operation to select it.
  - b. Right-click and select **Add Source** or **Add Parameter Insert** from the menu.
7. (Optional) Rename source or result parameters by:
  - a. Select the operational handle of the parameter you want to rename.
  - b. Right-click and select **Rename "<parm\_name>"**.
 Or, click Rename from the Transformation Editor Model tab toolbar.
  - c. Type the new name.

8. Define the conditions on the switch. Each condition is called a **Case**. Each Case is evaluated in the order specified and the first case to evaluate to true is returned in the result.




- To add new Case expressions, click the green plus button.
- To edit the expression defined for each case, click in the text edit fields and edit the text as necessary to define your expression.
- To adjust the order that the conditions are evaluated, use the arrow buttons to move the row up or down.
- To close and save your definitions, click **Close**.

If your expression contains illegal characters you must enclose them in double quotes. The following characters are considered illegal:

\, [ , ] , { , ( , ) , ! , @ , \$ , + , \* , ? , { , } , | , ; , < , > , < , =

9. Save your transform.

The following model diagram shows a transform using the Switch operation:



## Using the Create Operation Button

### To use the Create Operation button

1. Open a transform.
2. Click Create Operation.

The last operation that was selected or is currently selected on the palette is added to the transform workspace.

3. Save your transform.

## Working with Operation and Parameter Container Details

Most operations contained detailed elements that can be edited or configured to customize the behavior of your transform. This section includes the following topics:

- [Defining Element Facets, page 282](#)
- [Defining Constant Values, page 283](#)
- [Editing Import Paths, page 284](#)
- [Edit Namespace Prefix Maps, page 286](#)
- [Using Cycle I/O Direction to Add or Delete Parameters, page 288](#)


## Defining Element Facets

Element facets are the details defined for each of the elements being defined for the XQuery transformation code. They are primarily responsible for setting minimum and maximum occurrences, and indicating if the value can be NULL or not.

Restrictions are used to define acceptable values for XML elements or attributes. Restrictions on XML elements are called facets.

## To define element facets

1. Access the Element Facets Editor in several ways including:
  - From the right-mouse menu of an operation handle, by selecting Change Facets.




2. Review and modify the values for Min and Max occurrence.
3. Determine the setting you want specified for Nullable:
  - Unknown
  - True
  - False
4. Click **OK**.

If the min and max values were changed, they are displayed next to the parameter name.

## Defining Constant Values

Depending on the structure and content of your transform, you might want certain parameters to always evaluate to the same value. This constant value must be a valid value for the data type of the parameter for which you are defining it.

After the value is defined, it will display in the operation handle similar to the following:



Which would evaluate similar to the following in the generated XQuery:

```
element source
{
  456
}
```

### To define constant assignments

1. Access the Constant Assignment edit field in several ways including:
  - From the right-mouse menu of an operation handle, by selecting Create Constant Assignment.
  - From the Transformation Editor Model tab toolbar.The operation handle populates with a value of zero.
2. From the right-mouse menu, select one of the following:
  - Edit
3. Type the value that you want used as the constant. For example:
  - 50000
  - 34
4. Save your transform.

### Editing Import Paths

Import paths allow you to point the Transformation Editor at a set of one or more definition sets that are defined within TDV. These definition sets are then used by the Transformation Editor to provide you with a set of types that you use for parameters. By default, the Transformation Editor points to the following paths:

- /lib/types/sql
- /lib/types/extendedSql
- /lib/types/xmlSchema2001

The paths control what types are available when adding parameters or changing their type.

If your transform uses type definitions from several definition sets and two or more of the definition sets contain an element with the same name, the first occurrence of it is the one that controls the element definition. The order that the definition sets is read can be edited.

### To add a definition set to the list of import paths


1. Open your transform.
2. From the Studio resource tree, click and drag a definition set into the Transformation Editor. Or, add a new parameter and browse to the definition set.
3. Save your transform.



### To edit the list of import paths


1. Open your transform.
2. Select Edit Import Paths from the toolbar.

The Edit Imported Definition Sets editor opens and displays the list of paths currently available to the Transformation Editor.



3. Click Import Paths to obtain a selection window that you can use to navigate through a list of valid Studio resources available to add as an imported definition set.

- Use the Select Resources dialog to select the additional definition set that you want added to the Imported Paths list.



- Click **OK**.
- Determine if the order of the list should be changed and if any included paths need deletion.
  - To reorder paths, select a path and use the up and down arrows.
  - To delete a path from the list, select the path and click the red X.
- Close the Edit Imported Definition Sets dialog.
- Save your transform.

### Edit Namespace Prefix Maps

Namespaces are used to avoid element name conflicts. Because element names are defined by the developer, there can be conflicts when code from more than one developer is combined. The name conflicts in XML can be avoided using a name prefix.

The XML Namespace represents the root URL path that is used for XML-based names. The Namespace is augmented with the specific names of things that are then created.


For example, `http://masterschool.com/transform` could be the root path assigned to your specific `business_school_transform`, which would result in the following:

`http://masterschool.com/transform/business_school_transform`

### To edit the namespace prefix maps

1. Open your transform.
2. Select Edit Namespace Prefix Maps from the toolbar.

The editor opens and displays the list of prefixes currently used by the Transformation Editor.



3. To add a new prefix, use the green arrow button to create a new Namespace prefix.
4. To edit an existing, double-click in the cell that you want to edit and begin typing to edit the namespace text.

If you changed the text in the Prefix column and that name had been shown as part of your transform, the new name should now appear in your transform on the Model tab.

If you changed the text in the Namespace column, the actual namespace that is used when the transform is executed is changed.

5. Click **OK** to save your changes.

### To view the namespace prefix maps declared for your transform

1. Open your transform.
2. Click the XQuery tab.
3. In the XQuery declarations section, look for text similar to the following:

```
declare namespace xquery = "http://compositesw.com/transform/xquery";
declare namespace sql = "http://compositesw.com/transform/sql";
declare namespace ext2 = "http://www.compositesw.com/extensions2";
declare namespace xs = "http://www.w3.org/2001/XMLSchema";
```

### Using Cycle I/O Direction to Add or Delete Parameters

The Cycle I/O Direction button can be used to add parameters to the in and out containers.

#### To use the Cycle I/O Direction button

1. Open a transform.
2. Select the in or out container.
3. Right-click and select Add Parameter.
4. Specify a data type for the parameter and name the parameter.
5. Click the Cycle I/O Direction button.

The parameter is moved to the operation that it wasn't in.

6. Optionally, click the button again to add the parameter in both operations.
7. To delete the parameter, select the parameter and then delete it.

If a parameter was added to the in and out containers using the Cycle I/O Direction button, deleting the parameter from one of the operations deletes it from both operations.

8. Save the transform.

### Deleting Operations in the Transformation Editor

In and out are not considered operations and cannot be deleted. Even if there are no parameters in the in container, you cannot delete it from the Transformation Editor Model tab.

### To delete operations from the model tab of the Transformation Editor

1. Click the operation to select it.
2. Click the delete button on your keyboard or select Delete from the right-mouse menu.
3. Save your changes.

## Working with Messages

The Transformation Editor has a lot of built-in validation of the design phase of your transform. Viewing the messages can help you resolve design problems that prevent your transform from executing. By reviewing and attempting to resolve the various messages can be used to improve the quality of your resulting transform.

- [Viewing Messages, page 289](#)
- [Using Messages to Refine Your Transform, page 290](#)


## Viewing Messages

### To view messages

1. Open your transform.
2. Click Show Messages on the toolbar.

The messages pane opens in the split panel and displays messages for the transform you are editing. In the following example, the messages button was

selected while on the Parameters tab, but messages can be viewed from other portions of the Transformation Editor.



3. Review the messages.
4. Determine a best course of action to correct your transform.
5. Use the Model and Parameters Tab to implement the necessary changes.
6. Save your transform.

## Using Messages to Refine Your Transform

When you select a message in the messenger tab, the affected item is selected on the Model tab. You can use these features of the Transformation Editor to speed your design and deployment of your transforms.

### To view messages

1. Open your transform.
2. Click Show Messages on the toolbar.
3. Select a message in the message tab.

Use the up and down arrow buttons to move up or down the error message list and change the focus in the Model tab.

4. Edit the selected item in the Model tab.
5. Save your transform.

### Editing Parameters on the Parameters Tab

The Transformation Editor's Parameters tab displays all of the parameters listed in the in and out containers from the Model tab.

The parameters displayed in the Transformation Editor conveys the cardinality of the parameters in the following ways:

- If the parameter is a sequence, square brackets are shown along with its name. For example, "a[ ]".
- If the max occurs of a sequence is non-zero, that number is displayed within the square brackets. For example, "a[45]".
- If the min occurs of a sequence is non-zero, that number is displayed as the first part of a range. If max occurs is 0, the range has no upper bound and is displayed similar to "a[4-\*]". If max occurs is specified, it is displayed similar to "a[4-45]".

The Parameters tab of the Transformation Editor can be useful as a single parameter editing tool across all of the operations in your transform. It can be more efficient, for example, to use the Parameters tab to change the data type of all TINYINT parameters to INT.

### To edit parameters using the Parameters tab

1. Open your transform.
2. Select the Parameters tab.

The following graphic shows several parameters that exist for the in and out containers.

Name	Type	Native Type	Definition Set
Parameters			
CustomersParam	Struct	foo:Customers	/shared/XMLdefinitionsset
foo:customer []	Struct	foo:Customer	/shared/XMLdefinitionsset
foo:customerID	Integer	xs:integer	/shared/XMLdefinitionsset
foo:customerName	String	xs:string	/shared/XMLdefinitionsset
foo:customerEmail	String	xs:string	/shared/XMLdefinitionsset
foo:orders []	Struct	foo:Order	/shared/XMLdefinitionsset
foo:orderID	Integer	xs:integer	/shared/XMLdefinitionsset
foo:orderSubTotal	Decimal(19)	xs:float	/shared/XMLdefinitionsset
foo:orderSalesTax	Decimal(19)	xs:float	/shared/XMLdefinitionsset
foo:orderTotal	Decimal(19)	xs:float	/shared/XMLdefinitionsset
foo:orderSubmitDate	Date	xs:date	/shared/XMLdefinitionsset
foo:orderProcessDate	Date	xs:date	/shared/XMLdefinitionsset
foo:orderShipDate	Date	xs:date	/shared/XMLdefinitionsset
foo:orderItems []	Struct	foo:OrderItem	/shared/XMLdefinitionsset
foo:orderitemID	Integer	xs:integer	/shared/XMLdefinitionsset
foo:orderitemName	String	xs:string	/shared/XMLdefinitionsset
foo:orderitemDescription	String	xs:string	/shared/XMLdefinitionsset
foo:orderitemQuantity	Integer(10)	xs:int	/shared/XMLdefinitionsset
foo:orderitemPrice	Decimal(19)	xs:float	/shared/XMLdefinitionsset
TIMESTAMPParam	SqlDateTime	TIMESTAMP	/lib/types/sql

3. Select any row.
4. To add a new parameter, use the green plus button.
5. To adjust the order or position of the parameters use the arrow buttons.
6. Optionally, you can:
  - Rename
  - Change the data type
  - Change the I/O direction
  - Change Facets
7. Save your transform.

## Rebinding Transformation Operations


When importing or exporting information to and from Studio, sometimes the relative location of source data or objects change. For example, when exporting a transform to a CAR file so that it can be used by a colleague, the XML data source might depend on an XML file with data that is stored in C:/temp but is in the D:/users/temp directory on the colleague's computer. For the transform to work on the colleague's computer they must point the transform at the new location for the data by rebinding the transform.



## To rebind a transform

1. Open the transform that appears to need rebinding.

Typically, Studio knows that a rebind issue has occurred and displays the Rebind tab for the transform.



2. If you need to modify a data source or other resource to point to the location of the data on your machine, do so.
3. Click the Rebind button.
4. Navigate to the valid location for the resource in your Studio tree.
5. Click **OK**.

## Working with the Transformation Editor XQuery Tab

The XQuery tab that is included as part of the Transformation Editor is an excellent tool to use for reviewing the XQuery code that will be generated by the transform that you are defining. After adding a few operations and connections to your transform, you can preview the code to get a feel for how the transform will act when it is executed. As you get more comfortable with the code that TDV will generate for your transform, you can design models that produce the results that you need.

Queries that are part of your transform have generated SQL that you can review. TDV optimizes the SQL so that it can be pushed for execution at the database level.

Topics included in this section are:

- [Viewing and Copying the XQuery Code From Your Transform, page 294](#)
- [Validating the Transform XQuery Code Using Studio, page 294](#)

## Viewing and Copying the XQuery Code From Your Transform

Looking at the code on the XQuery tab of the Transformation Editor can help you understand the code that TDV generates for the transform that you are defining. If the source code generated by the Transformation Editor is inadequate for your unique situation, you can copy the XQuery source of the transform into a newly created XQuery Procedure.

### To view and copy the XQuery code

1. Open the Transformation Editor.
2. Save your transform.
3. Select the XQuery tab.
4. Scroll up and down to review the code.
5. Select a portion or all of the code and copy it (using ctrl+c).

## Validating the Transform XQuery Code Using Studio

Copy and paste the XQuery code into a different Studio procedure editor to validate that what the Transformation Editor is generating is valid.

This validation method can be used to move your transform code out of the confines of the Transformation Editor code generator so that you can define your transform using XQuery code directly.

### To validate the XQuery code that is created by the Transformation Editor

1. Open your transform.
2. Select the XQuery tab.
3. Use your mouse to highlight and select all of the code text.
4. Copy the selected text.
5. From the Studio resource tree, right-click Shared.
6. Select New XQuery Procedure.
7. Name your new procedure.
8. Select all of the text in the XQuery tab and paste your transform XQuery code.
9. Save the procedure.
10. Execute the procedure.
11. If errors are generated, return to your transform and attempt to resolve them using the Transformation Editor.

## Using a Transform as a Resource in Another Transform

Reusing transform definitions can speed development of larger more complex data transformation tasks.

### To transform your data using nested transforms

1. Create your transform, for instructions, see [Creating a New Transform, page 261](#).
2. From the Studio tree, select an existing transform and click and drag it onto the Model tab.
3. Save your transform.

## Caching Transform Data

The Transformation Editor's Caching tab gives you access to set up several of the standard TDV caching features. Because TDV treats transforms as if they were procedures, the caching features that you can enable are the features that are generally supported for other TDV procedure resources. For information on caching with TDV, see [TDV Caching, page 391](#).

The procedure caching process uses one storage table for each output cursor and an additional storage table for any scalar outputs. For example, a procedure with two INTEGER outputs and two CURSOR outputs would use three tables:

- One for the pair of scalars
- One for the first cursor
- One for the second cursor

If a procedure has input parameters, the cached results are tracked separately for each unique set of input values. Each unique set of input parameter values is called a variant.

A procedure cache that uses non-null input parameters must be seeded with at least one variant from a client application other than Studio, for the **Cache Status** to change from **NOT LOADED** to **UP**. Using the **Refresh Now** button does not change the status of a cache that is not loaded. Even if procedure caching configuration is correct, the status does not show that it is loaded until a client seeds the cache.

When a procedure cache is refreshed, all the cached variants already in the table are refreshed. If no variants have yet to be cached, then nothing is refreshed or only the null input variant is refreshed. You can refresh a procedure cache from Studio or using the **RefreshResourceCache** procedure. (See the *TDV Application Programming Interfaces Guide*.)

### To define a cache for your transform

1. Open your transform.
2. Validate that the input parameter values for your transformation do not exceed 255 characters.

If the parameter exceeds 255 characters, the procedure call is not cached. Instead, it is executed as if caching was disabled. TDV tracks procedure variants by converting the input parameter values to a string to compare for uniqueness.

3. Select the Caching tab.
4. Click Create Cache.
5. Define the cache.

See the *TDV User's Guide* for more information on caching concepts and how to define caching on a procedure.

6. Save your transform.
7. Optionally, configure the **Maximum number of procedure variants** field in the **Advanced** section of the **Caching** panel to store the variant result sets produced from your transforms.

By default, the maximum number of stored variants is 32. If the cache is full, the least recently used variant is swapped out for the latest variant.

# Definition Sets

---

This topic describes definition sets including what they are, how to define them, and how to use them in TDV.

These topics are covered:

- [About Definition Sets, page 297](#)
- [Creating a Definition Set, page 298](#)
- [Using a SQL Definition Set, page 305](#)
- [Using an XML Definition Set, page 306](#)
- [Using a WSDL Definition Set, page 307](#)

## About Definition Sets

A *definition set* is a set of definitions you create that can be shared by other TDV resources. A definition set includes SQL data types, XML types, XML elements, exceptions, and constants. You can refer to the resources in a definition set from any number of procedures or views. The changes you make in a definition set are propagated to all the procedures or views using the definition set. You cannot publish a definition set. The definition sets you create are reusable and can be shared with any user with appropriate access privileges in the system.

TDV supports three types of definition sets:

- XML-based
- SQL-based
- WSDL-based

TDV supports these definition sets with the following data types and arrays of those types:

BINARY, BLOB, VARBINARY, DECIMAL, DOUBLE, FLOAT, NUMERIC, BIGINT, BIT, INTEGER, SMALLINT, TINYINT, CHAR, CLOB, LONGVARCHAR, VARCHAR, DATE, TIME, TIMESTAMP, CURSOR, ROW, XML

Studio has an editor for building and editing definition sets. The definition set editor opens automatically when you create a definition set. For details, see [Creating a Definition Set, page 298](#). At any time, you can open the definition set in the editor by double-clicking the definition set in the resource tree.


## Creating a Definition Set

You can create a definition set anywhere in the Studio resource tree except within Data Services. For other details, see [Locating a Container for a TDV Resource](#), page 42.

This section describes how to create SQL, XML, or WSDL definition sets. An XML definition set can be created from either a schema or a raw XML file instance.

### To add a new SQL, XML, or WSDL definition set

1. Right-click at an appropriate location in the resource tree, and select New Definition Set. Or, at the chosen location you can select File > New > Definition Set.



2. In the New Definition Set dialog:
  - a. Type a name for the definition set.
  - b. Choose a type for the definition set—SQL, XML, or WSDL—in the Type drop-down list.
  - c. Click OK.

The definition set is added to the specified location in the resource tree, and the definition set editor opens in the right pane.

3. Add definitions to the definition set using the instructions for the type of definition set:
  - SQL—See [Creating a SQL Definition Set](#), page 299.
  - XML—[Creating an XML Definition Set](#), page 302.
  - WSDL—[Creating a WSDL Definition Set](#), page 304.

## Creating a SQL Definition Set

You can create a SQL definition set that defines parameters, exceptions, and constants. You can then refer to the parameters, exceptions, and constants in a definition set from any procedure or view in TDV, and also share the definition set with any user who has appropriate privileges in the system. You can type the SQL definitions directly, or import existing definitions.

### To create a SQL definition set

1. Follow the steps in [Creating a Definition Set, page 298](#), choosing SQL as the type of definition set.

See [SQL Definition Set Editor, page 624](#) for information about the SQL definition set editor toolbar buttons and panel features.


2. Select the Types tab in the editor.

You can create type definitions for a SQL definition set in one of two ways:

- You can add new type definitions one at a time.
- You can upload an existing definition set. You can include both SQL-type definitions and XML-type definitions in a SQL-type definition set.

3. Add one or more new definitions by following these steps:
  - a. Click the Add button and select one of the data types from the menu.


Studio adds a definition of the specified type, giving it the default name `NewTypeDefinition`. For example, if you select `String > CHAR`, the new definition would look like this:



- b. Rename the newly added type definition by clicking in the Name field and typing the new name. Or, you can right-click and select `Rename` from the menu.
  - c. If the type is `Complex` and you have created multiple `xmlElements`, you can move or indent a type definition by using the navigation arrows in the editor's toolbar.
  - d. Repeat to create as many type definitions as you need.
  - e. Save the definition set.
4. Optionally, add an existing definition set from the Studio resource tree by following these steps:
    - a. Click the `Add` button and select `Browse` from the menu.



The Add Definition Type window opens.




- b. In the resource tree in the left pane, select a definition set.
- c. In the right pane, select the definition set.

The qualified name for the selected definition set appears in the Type field at the bottom if the window.


- d. Click OK.
  - e. Back in the new definition set panel, rename the newly added definition set by clicking in the Name field and typing the new name. Or, you can right-click and select Rename from the menu.
  - f. Expand the definition set and edit it as necessary. You can:
    - Use the right-click menu to rename, change the data type or value, or delete a type definition.
    - Move or indent a type definition using the navigation arrows in the editor's toolbar.
  - g. Save the definition set.
5. To add exceptions, select the Exceptions tab, click the Add button, and add exceptions the same way you added types.

The **Exceptions** example below displays some exceptions available in the system.



6. To add constants, select the Constants tab, click the Add button, and add constants the same way you added types and exceptions.

The Constants panel with an example constant is shown below.



7. To supply a value for a constant:
  - a. Select the constant.
  - b. Right-click the Value field and select Change Value.
  - c. In the input dialog, supply a value for the constant, and click OK.
8. Optionally, click the Info tab to review information about this definition set or supply an annotation for the definition set.
9. Save the definition set.

You can now reference the SQL definition set and all of the data types contained in the definition set from stored procedures, XQuery procedures, and XSLT procedures. See [Using a SQL Definition Set, page 305](#).

## Creating an XML Definition Set

You can create an XML definition set by typing it in or by importing existing XML definitions.

## To create an XML definition set from an XML file instance

1. Follow the steps in [To add a new SQL, XML, or WSDL definition set, page 298](#), choosing XML as the type of definition set.

The XML Schema tab is displayed in the editor that opens on the right. See [XML Definition Set Editor, page 624](#) for information about the XML definition set editor toolbar buttons and panel features.

2. Enter XML schema definitions in one of three ways:
  - Type the XML schema definitions directly into the panel.
  - Import the XML schema definitions from an existing file in your file system as follows:
    - a. Click the Import XML Schema Definitions From File(s) button.
    - b. In the File Location dialog, type the full pathname to the XML file in the File field, or browse to the XML file that you want to import.
    - c. Optionally (in the File Location dialog), check the Show Advanced Options check box to view the connection properties and alternate location mappings for this file.
    - d. Click OK.
    - Import the XML schema definitions from an XML Instance as follows:
      - e. Click the Create XML Schema Definitions From XML Instance button.

Studio opens an Open dialog in which you can choose the XML file. This needs to be an XML file, not a schema.

- f. Click Open.

3. In the editor, view and optionally edit the schema.
4. Use the Validate XML Schema Definitions button in the toolbar to validate the schema.

The validation process parses the XML file into a schema of element declarations and type definitions, which now appear in the XML Schema panel.

A field in the lower right corner of the panel shows the current line and column position of the cursor (separated by a colon) to help you find errors in the schema if it is found to be invalid.

5. Use the Format XML Schema Definitions button in the toolbar to format the definitions with indentation and font coloring (keywords in orange type and literal definitions in blue type).
6. Save the definition set.

You can now reference the XML definition set and all of the XML types defined in the definition set from stored procedures, XQuery procedures, and XSLT procedures. See [Using an XML Definition Set, page 306](#).

## Creating a WSDL Definition Set

You can create a WSDL definition set by typing it in or by importing existing WSDL or XML schema definitions.

### To create a WSDL definition set

1. Follow the steps in [To add a new SQL, XML, or WSDL definition set, page 298](#), choosing WSDL as the type of definition set.

The WSDL tab is displayed in the editor that opens on the right. See [WSDL Definition Set Editor, page 626](#) for information about the WSDL definition set editor toolbar buttons and panel features.

2. Enter WSDL schema definitions in one of these ways:
  - Type the schema definitions directly into the panel.
  - Import the WSDL or XML schema definitions from an existing file in your file system as follows:
    - a. Click the Import WSDL and XML Schema Definitions From File(s) button.
    - b. In the File Location dialog, type the full pathname to the WSDL or XML file in the File field, or browse to the WSDL or XML file that you want to import.
    - c. Optionally, check the Show Advanced Options check box to view the connection properties and alternate location mappings for this file.
    - d. Click **OK**.
3. Use the Validate WSDL and XML Schema Definitions button in the toolbar to validate the schema.

Validating the schema parses the schema into Element Declarations and Type Definitions, which you can find in the XML Schema panel.

A field in the lower right corner of the panel shows the current line and column position of the cursor (separated by a colon) to help you find errors in the schema if it is found to be invalid.

4. Use the Format WSDL and XML Schema Definitions button in the toolbar to format the definitions with indentation and font coloring (keywords in orange type and literal definitions in blue type).

You can now reference the WSDL definition set and all of the XML types defined in the definition set from stored procedures, XQuery procedures, and XSLT procedures. See [Using a WSDL Definition Set, page 307](#).

## Using a SQL Definition Set

You can reference a SQL definition set and all of the data types defined in the definition set from SQL scripts, stored procedures, XQuery procedures, and XSLT procedures.

The procedure described here refers to the data types defined in a SQL definition set named mySQLDef:

Name	Base Type
firstname	CHAR(255)
lastname	CHAR(255)

### To use an SQL-type definition set

1. Create a SQL script.
2. Reference the SQL definition set in the PROCEDURE using the TDV resource path and name.

The SQL script below uses the SQL definition set named mySQLDef.

```

PROCEDURE callSQLDef(OUT Name VARCHAR (512))
BEGIN
  DECLARE FirstName /users/composite/admin/mySQLDef.firstname;
  DECLARE LastName /users/composite/admin/mySQLDef.lastname;
  SET FirstName = 'myFirstName';
  SET LastName = 'myLastName';
  SET Name = CONCAT (CONCAT(TRIM(FirstName), ' '), (TRIM(LastName), '
CALL Print (Name); -- prints to the console
END
  
```

- Execute the script to see the result.

## Using an XML Definition Set

The procedure used in this section uses an XML definition set named `XMLLib_Composite`, which has the following XML schema and elements:

```
<?xml version="1.0" encoding="UTF-8"?>
<xs:schema elementFormDefault="qualified"
  targetNamespace="http://www.compositesw.com/services/webservices/system/admin/resource"
  xmlns:ns="http://www.compositesw.com/services/webservices/system/admin/resource"
  xmlns:xs="http://www.w3.org/2001/XMLSchema"
  >
  <xs:simpleType name="Location">
  <xs:restriction base="xs:string"/>
  </xs:simpleType>
  <xs:complexType name="Address">
  <xs:sequence>
  <xs:element name="street" type="ns:Location"/>
  <xs:element name="number" type="xs:integer"/>
  <xs:element name="suite" type="xs:integer"/>
  <xs:element name="phone" type="xs:integer"/>
  <xs:element name="fax" type="xs:integer"/>
  </xs:sequence>
  </xs:complexType>
  <xs:element name="CompositeAddress" type="ns:Address"/>
</xs:schema>
```

The procedure described here supplies values to the elements in the XML schema in the definition set `XMLLib_Composite` ([Note: The type elements defined in the `wsdltest` definition set like `TradePriceRequest` and `TradePrice` are also referenced., page 308](#)).

### To use an XML-type definition set

- Create a SQL script by right-clicking at an appropriate location in the resource tree and selecting `New SQL Script`, typing a name for it, and clicking `OK`.
- Type the following script in the `SQL Script` panel of the script editor:

```
PROCEDURE ScriptComposite(OUT CompanyAddress /shared/sources/definitionSets/XMLLib_Composite.
"{http://www.compositesw.com/services/webservices/system/admin/resource}Address")
BEGIN
set CompanyAddress = '<ns:CompositeAddress
xmlns:ns="http://www.compositesw.com/services/
  webservices/system/admin/resource">
  <ns:number>2655</ns:number>
  <ns:street>Campus Drive</ns:street>
  <ns:suite>Suite 200</ns:suite>
  <ns:city>San Mateo</ns:city>
  <ns:zip>94403</ns:zip>
  <ns:phone>650-277-8200</ns:phone>
```

```

<ns:fax>650-227-8199</ns:fax>
</ns:CompositeAddress>';
END

```

3. Execute the script to see the result.

## Using a WSDL Definition Set

You can use a WSDL definition set in a procedure or a view. The example here shows how a WSDL definition set can be used in a procedure.

### To use a WSDL definition set in a procedure

1. In Studio, define and save a WSDL definition set.

This example uses a WSDL definition set named wsdctest.

2. Create or open a procedure.
3. Reference the WSDL definition set in the PROCEDURE using the TDV resource path and name.

- The SQL script below uses the SQL definition set named mySQLDef.

You can drag and drop the definition set resource from the Studio resource tree, causing the full name to appear in the procedure text panel. Refer the *TDV Reference Guide* for more details on the SQL Script parameters.

For example, if you reference the wsdlttest WSDL definition set shown above, you would reference it in a procedure as shown in this example, where it is used for both input and output parameters.

```

PROCEDURE procaroundgetquote(IN ticker /shared/shared/wsdlttest.
"(http://example.com/stockquote.xsd)TradePriceRequest",
OUT stockdetails /shared/shared/wsdlttest.
"(http://example.com/stockquote.xsd)TradePrice")
BEGIN
  Declare stockSym VARCHAR;
  Declare sDetails VARCHAR;
  Declare sPos INT;
  Declare sPrice VARCHAR;
  call /shared/shared/testextractstockticker( ticker, stockSym );
  call /shared/shared/restexample/getquote( stockSym, sDetails );
  set sPos = position( ', ' IN sDetails );
  set sPrice = substring( sDetails, sPos + 1,
                        position( ', ' IN
                        substring( sDetails, sPos + 1, length( sDetails ) - sPos
  call print(sPrice);
  set stockdetails = concat( concat( '<stockquote.xsd:TradePrice xmlns:stockq
',
                                concat( concat( '<Price>', sPrice, '</Price>' ) ),
                                '</stockquote.xsd:TradePrice>'
  );
END

```

SQL Script Parameters Caching Info

**Note:** The type elements defined in the wsdlttest definition set like TradePriceRequest and TradePrice are also referenced.



# Triggers

---

This topic describes how to define triggers that cause an action to be performed under specified conditions.

- [About Triggers, page 309](#)
- [Creating a JMS Event Trigger, page 314](#)
- [Creating a System Event Trigger, page 315](#)
- [Creating a Timer Event Trigger, page 318](#)
- [Creating a User-Defined Event Trigger, page 320](#)
- [Creating Email Alerts, page 322](#)

## About Triggers

A *trigger* is a resource that initiates a specific system activity to be performed when specified conditions occur. Triggers use a JMS event, a system event, a timer event, or a user-defined event to initiate specific system actions like:

- Execute a procedure
- Gather statistics
- Re-introspect data sources
- Send an email

Triggers can be scheduled to be performed periodically or can occur based on specified conditions. The triggering conditions can cause actions without requiring user interaction. When you create a trigger, it appears in the Studio resource tree.

Triggers provide the following benefits:

- One user can set multiple schedules (using separate triggers) on one resource.
- Many users with appropriate privileges can share the same schedule on a resource.
- Users can define their own events to trigger several actions asynchronously.
- Tasks and actions can be triggered in response to a system event, such as a request failure or the status of a data source.
- Procedures can be executed without sending notifications.

- Views and procedures can be executed and the results can be sent to one or more recipients.

### Condition Types for a Trigger

This section describes the trigger condition types that Studio supports: JMS events, system events, timer events, and user-defined events.

- **JMS Event**—Enables the firing of an action based on the receipt of a JMS message on the specified queue or topic connection. The firing of the trigger is contingent on the match with the particular selector property specified using SQL condition syntax.
- **System Event**—Enables the firing of an action based on any system-generated event. User tasks can listen for such events. Two APIs—`GetEnvironment` and `SetEnvironment`—are available at `/lib/util/`, and can be called at any time to listen for a system-generated event.

When you specify System Event as the condition type for your trigger, the system provides a dynamic list of all available events for you to select from. The following System Events can be used for a trigger.

System event	When triggered or generated
CacheRefreshFailure	Triggered when a cache fails to refresh.
CacheRefreshSuccess	Triggered when a cache refresh is performed successfully.
ClusterServerConnected	Generated when a cluster node is connected.
ClusterServerDisconnected	Generated when a cluster node is disconnected.
ClusterServerShunned	Generated when a cluster node fails to send a heartbeat signal to the cluster timekeeper and has been shunned (temporarily excluded) from the cluster.

System event	When triggered or generated
DataSourceDown	<p>Generated when a data source connection is lost. Data source connections are tested in any of the following cases:</p> <ul style="list-style-type: none"> <li>• Studio restart tests all data sources</li> <li>• New data source, configurations, and connections</li> <li>• Resource execution checks connection status</li> <li>• Committing/rolling back a transaction</li> </ul> <p>All reports of a data source being in DOWN status generate an event regardless of whether that data source was reported as down previously.</p>
DataSourceUp	<p>Generated when a data source connection is re-established. Data source connections are tested in any of the following cases:</p> <ul style="list-style-type: none"> <li>• Studio restart tests all data sources</li> <li>• New data source, configurations, and connections</li> <li>• Resource execution checks connection status</li> <li>• Committing/rolling back a transaction</li> </ul> <p>A Data Source Up event is generated only when the data source is first connected or when the status is changed from DOWN to UP.</p>
ErrorsSpike	Generated when errors pass a predetermined number.
FailedLoginSpike	Any ten failed sign-in attempts within a ten minute period generate a FailedLoginSpike event.
MetricRestoreFailure	Generated when the metrics are trying to be restored, but they fail.
MetricsBackupFailure	Generated when the metrics backup fails.
MetricsPersistentFailure	Generated when metrics data fails to persist.
MetricsTruncationFailure	Generated when the truncation of metrics data fails.
RequestFailure	<p>Generated when a request results in failure.</p> <p>Whenever any SOAP call or SQL execution is not accepted, produces an exception, or results in an error, this event is logged. This event is generated when closing any unsuccessful request.</p>

System event	When triggered or generated
RequestInactive	Generated when a request is inactive. A request is considered inactive when it has no incoming or outgoing byte change beyond a configurable number of minutes. The value of the inactivity period is a server configuration parameter that can be configured using <b>Request Inactive Time</b> . By default there is no setting for the inactivity time.
RequestRunForTooLong	Generated when: <ul style="list-style-type: none"> <li>• Enable All Events is set to true.</li> <li>• Request Run Time is enabled.</li> </ul>
RequestsSpike	Generated when requests pass a predetermined number.
ResourceLock	Generated when resource locks are set on a resource so that only one person can modify the locked set.
ResourceUnlock	Generated when a resource is unlocked so that any user with sufficient rights and privileges can edit it.
ServerStart	Event is generated when TDV starts.
ServerStop	Event is generated when TDV stops.
StatisticsGatheringFailure	Event is generated when an attempt to gather statistics on a data source fails.
TransactionFailure	Event is generated on any transaction failure.
UserLogin	Event is generated when user logs in to TDV.
TableCreate	Event is generated when table is created using DDL..

Making a trigger based on a system event does not enable a disabled event. All system events are enabled by default, but if they are disabled they require a manual server configuration change to enable them. For more information, see the *TDV Administration Guide*.

Triggers cannot enable a disabled data source.

- **Timer Event**—Lets you schedule periodic timed trigger events. Actions that can be timed to start are: executing a procedure, gathering relevant data from a data source for query processing, re-introspecting a data source, or sending email with the results of a procedure/view execution.

To set a timer event, you define the start time, optionally specify a period or window of daily or periodic activity, and set the frequency of the trigger

refresh to get the wanted periodicity. Triggers can be set to begin operation in the future and end after a predefined activity period.

You can optionally specify a recurrence restriction. If Recurrence Restriction is enabled, the trigger fires only on the selected days of the week and during the time window specified by the Start and End times, subject to the following rules:

- If Start and End time are identical, no time restriction is applied.
- If End time is greater than Start time, the trigger is restricted to fire only within the time window starting at Start time (inclusive) and ending at End time (inclusive).
- If End time is less than Start time, the trigger is restricted to fire only within the time window starting at End time (inclusive) and ending at Start time on the next day (inclusive).
- User Defined Event—Utilizes a built-in procedure named GenerateEvent which is available at /lib/util/. This procedure can be called at any time to insert a user-defined event into the trigger system. You can use this functionality for letting an ongoing procedure call GenerateEvent to trigger a wanted action asynchronously.

See [Condition Pane, page 620](#) for more information about the options for each condition type.

### Action Types for a Trigger

Executing a procedure, gathering statistics on a data source, re-introspecting a data source, and sending email are the *trigger action types* that can be triggered for certain conditions.

- Execute Procedure—Lets you specify a procedure to be executed without sending any notification.
  - Exhaust output cursors—If the procedure is a SQL script that contains a PIPE cursor, and if the pipe needs to fully execute and load all rows to complete execution of a trigger (for example, to email a result set) checking this box forces the trigger to wait until all the rows are buffered and read before completing. If you leave this unchecked, the trigger returns while the pipe is buffering, cutting off the buffering of the pipe.
- Gather Statistics—Lets you specify a data source whose data statistics are to be gathered.
- Reintrospect Data Source—Lets you specify a data source to be re-introspected.

- Send email—Lets you specify a procedure or view to be executed, and send the results through email to one or more specified recipients.

See [Action Pane, page 621](#) for more information about the options for each condition type.

## Creating a JMS Event Trigger

These steps describe how to configure a JMS event trigger.

### To create a JMS event trigger

1. If not already done, configure a JMS connector with a queue or topic connection factory for use with TDV. See the *TDV Administration Guide* for more information.
2. Right-click where you can add a new resource in the resource tree, and select New Trigger.
3. In the Input window, supply a name for the trigger, and click OK.
4. In the trigger editor that opens on the right, enable the trigger by selecting the Enable Trigger check box.
5. For Condition Type, select JMS Event.
6. In the Condition pane, enter values in these fields:

Field	Description
Connector	The name of your JMS connector (containing the configuration for initial context factory, JNDI Provider URL, and Queue Connection Factory) as it appears on the CONNECTOR MANAGEMENT page in Web Manager.
Destination	The name of the connection factory destination (queue or topic).
Selector	A JMS message selector allows a client to specify, by header field references and property references, the messages it is interested in. Only messages whose header and property values match the selector are delivered. For example, a selector condition using SQL WHERE clause syntax might look like: 'uname'='admin'

What it means for a message not to be delivered depends on the MessageConsumer being used.

- A message selector matches a message if the selector evaluates to true when the message's header field values and property values are substituted for their corresponding identifiers in the selector.
  - A message selector is a String whose syntax is based on a subset of the SQL92 conditional expression syntax. If the value of a message selector is an empty string, the value is treated as a null and indicates that there is no message selector for the message consumer.
7. Specify the action type and the options for the action as described in [Action Types for a Trigger, page 313](#) and [Action Pane, page 621](#).
  8. On the trigger **Info** tab, specify the trigger properties. See [Getting Information about a Resource, page 44](#) for all fields except Maximum Number In Queue which is described below and works different for JMS triggers:
 

**Maximum Number In Queue**—For JMS triggers, this field is always set to 0 by the TDV server and you cannot change it. This is done to indicate that each JMS trigger can hold at most one message in memory at a time until it has been fully processed before receiving another pending message from the JMS server. That is, no message queuing is done inside TDV.
  9. Save the trigger. If the Save option is not enabled, select File > Refresh All to refresh the resources and enable the Save option.

## Creating a System Event Trigger

There are many system events that can be set as conditions for a trigger action. The APIs—GetEnvironment and SetEnvironment—that are available in /lib/util/ can be called at any time to listen for a system-generated event.

These steps describe how to create a sample procedure, create the system event trigger, and then test the trigger.

### To create a sample procedure to call GetEnvironment

1. Within Studio, create a sample SQL script procedure, named CallsGetEnvironment as follows:

```
PROCEDURE CallsGetEnvironment()
BEGIN
  DECLARE tpath VARCHAR(4096);
  DECLARE tname VARCHAR(4096);
  DECLARE ttype VARCHAR(4096);
  DECLARE tvalue VARCHAR(4096);
  DECLARE result VARCHAR(4096);
```

```

CALL GetEnvironment('TRIGGER_PATH', tpath);
CALL GetEnvironment('TRIGGER_EVENT_NAME', tname);
CALL GetEnvironment('TRIGGER_EVENT_TYPE', ttype);
CALL GetEnvironment('TRIGGER_EVENT_VALUE', tvalue);
SET result = CASE
    WHEN (ttype IS NULL) THEN 'NULL'
    ELSE ttype
END||' trigger '||CASE
    WHEN (tpath IS NULL) THEN 'NULL'
    ELSE tpath
END||': '||CASE
    WHEN (tname IS NULL) THEN 'NULL'
    ELSE tname
END||' = '||CASE
    WHEN (tvalue IS NULL) THEN 'NULL'
    ELSE tvalue
END;
CALL Log(result);
END

```

When this procedure is executed by a system event, the results are written out to the log.

### To create a system event trigger

1. Right-click where you can add a new resource in the resource tree, and select New Trigger.
2. In the Input window, supply a name for the trigger, and click OK.
3. In the trigger editor that opens on the right, enable the trigger by selecting the Enable Trigger check box.
4. Select System Event from the drop-down list in the Condition Type section.
5. Select a system event from the System Event Name drop-down list on the right.
6. For Action Type, select the type of action to be triggered from the drop-down list.

Field	Description
Execute Procedure	To see how it works, specify the path to the procedure <code>CallsGetEnvironment</code> in the Action section. Select Exhaust output cursors, if the procedure is a SQL script that contains a PIPE cursor.
Gather Statistics	To see how it works, select the data source <code>/shared/examples/ds_orders</code> as the data source to be scanned.



Field	Description
Reintrospect Data Source	To see how it works, select the data source /shared/examples/ds_orders as the data source to be re-introspected.
Send E-mail	To see how it works, specify the path to the procedure CallsGetEnvironment in the Action section.

7. In the **Action** section, enter the options for the action type. The options are described in the section [Action Types for a Trigger, page 313](#) and [Action Pane, page 621](#).

For example, if you want email notifications sent, type and confirm the email addresses of the recipients to receive notification, as needed. You can specify a list of email addresses in the address fields by separating each one with a comma (,) or semicolon (;).

8. Click the Info tab.
9. Specify the Maximum Number In Queue field to the maximum number of times this trigger is to be fired if multiple periods have elapsed while a recurrence restriction prevents the trigger from firing. Most triggers should fire only once when the next available active operation window, but there might be cases when more than one trigger action should be initiated at the next opening of the recurrence restriction. This number should not be negative.

10. Save the trigger.

If the Save option is not enabled, select File > Refresh All to refresh the resources and enable the Save option.

### To test your system-event trigger

1. Select CacheRefreshFailure as the system event name in the Condition panel.
2. Select Send E-mail as the Action Type.
3. Specify the path to CacheRefreshFailure in the Resource Path field.
4. Refresh the cache of a broken view.

The specified mail recipients receive email notification and the result of running the path to procedure CallsGetEnvironment is written to the log.

## Creating a Timer Event Trigger

This section describes how to create a timer event trigger.

### To create a timer event trigger

1. Right-click in the location where you want to add a new trigger resource in the resource tree, and select New Trigger.

Only valid trigger locations, like within My Home or Shared, offer the option to create a new trigger.

2. In the New Trigger window, supply a name for the trigger and click OK.

The trigger editor opens on the right.

3. Enable the trigger by selecting the Enable Trigger check box.

The Enable Trigger check box can be set to enable or disable the trigger at any time. Just save the trigger to set a changed value.

4. For Condition Type, select Timer Event.

5. In the Condition section, specify the schedule for the trigger. You set a timer event trigger to execute one time or repeat it at intervals based on minutes, hours, days, weeks, months, or years and specify the recurrence as follows:

- a. To schedule the event to be executed one time, select Exactly Once and skip directly to the Start on section to schedule when the trigger is to be fired.
- b. To schedule a periodic event, select Periodic, specify the refresh frequency (Refresh every), and select the time unit from the drop-down list.
- c. To schedule a periodic event, also specify the date and time for the first execution using the Start on (date) and at (time) fields.

The date and time entered specify the moment of the first triggering event. For example, if a daily event is set for 11:55 AM three days in the future, it runs at 11:55 AM in three days and then every day at the same time thereafter.

The date and time also mark the beginning of the Refresh every period. For example, if you specify Refresh every 1 hour, and you specify 9:35 AM in the Starting at section, a firing condition occurs at thirty-five minutes past the hour every hour from 9:35 AM onward.

If any recurrence restriction is in effect), the trigger can only *fire and initiate an action* within the time range and on the selected day(s). The actual firing of

an action is independent of the period you specify; that is, queuing a firing does not change when the next firing condition will be met.

- d. Optionally, check **Enable for the Recurrence Restriction (Optional)** and check days of the week and a time range to restrict trigger operation to a time window on specified days of the week.

By default, no recurrence restriction is in effect, and so a scheduled trigger fires whenever the specified period has elapsed. No recurrence restriction is in effect if every day of the week is selected and the start and end time are the same.

The recurrence restriction window begins a period during which a trigger fires and initiates the specified action. If the trigger conditions are met outside of the restricted window, then the trigger queues a firing event for the next recurrence restriction start time. The actual number of firing events allowed in the queue is configurable. See [Getting Information about a Resource, page 44](#).

If the trigger should be restricted to firing within a specific window of operation:

- Specify the days on which the trigger can fire.
- Specify the **Start** and **End** time when the trigger can fire.

With **Enable** checked, the trigger fires only on the selected days of the week and during the time window specified by the **Start** and **End** times, subject to the following rules:

- If **Start** and **End** time are identical, no time restriction is applied.
- If **End** time is greater than **Start** time, the trigger is restricted to fire only within the time window starting at **Start** time (inclusive) and ending at **End** time (inclusive).
- If **End** time is less than **Start** time, the trigger is restricted to fire only within the time window starting at **End** time (inclusive) and ending at **Start** time of the next day (inclusive).

More complex scheduling can be created by combining the effects of multiple triggers that can call the same actions with different scheduling parameters.

**Note:** If you check **Enable** in the **Recurrence Restriction (Optional)** section but you do not check any day of the week, the trigger does not have any valid firing period and is effectively disabled regardless of other settings.

- e. If the TDV Server is to be a member of a clustered group of servers, then check **Only once per cluster** to avoid multiple actions being triggered simultaneously from every TDV Server instance.
6. For **Action Type**, select the type of action to be triggered from the drop-down list.

7. In the Action section, enter the options for the action type. The options are described in the section [Action Pane, page 621](#).

Select Exhaust output cursors, if the procedure is a SQL script that contains a PIPE cursor.

For example, if you want email notifications sent, type and confirm the email addresses of the recipients to receive notification, as needed. You can specify a list of email addresses in the address fields by separating each one with a comma (,) or semicolon (;).

8. Click the Info tab. In the Maximum Number In Queue field in the Queue Properties section, specify the maximum number of trigger firings to queue if multiple periods have elapsed while a recurrence restriction prevents the trigger from firing.

Most triggers should fire only once within the next available active operation window, but there might be cases when more than one trigger action should be initiated at the next opening of the recurrence restriction. This number should not be negative.

9. Save the trigger.

If the Save option is not enabled, select File > Refresh All to refresh the resources and enable the Save option.

## Creating a User-Defined Event Trigger

When creating a user-defined event trigger, you first need to create a user-defined event that can function as a condition for a trigger action. Then you create the user-defined event trigger. Finally, you test the trigger.

Triggers are created like other TDV resources, but they cannot be published.

User-defined events are generated when the built-in procedure GenerateEvent (at /lib/util/) is called with an event name and value as its arguments.

User-defined event triggers execute once per cluster. Timer-based triggers can be designated as being cluster-aware and they fire on all cluster nodes on which the user-defined event is generated.

### To create a user-defined event

1. Create a SQL script procedure named CallsGenerateEvent to call GenerateEvent, as in the following example:

```
PROCEDURE CallsGenerateEvent()
BEGIN
    CALL GenerateEvent('runAREport', '');
```

END

This procedure calls `GenerateEvent`, which in turn creates a custom event with the name `runAReport`. Whenever this procedure is executed, `GenerateEvent` inserts the custom event named `runAReport` into the trigger system. The custom event is available for you to specify as a User Defined Event Name in the Condition section of a user-defined event trigger.

### To create a user-defined event trigger

1. Right-click where you can add a new resource in the resource tree, and select New Trigger.
2. In the Input window, supply a name for the trigger, and click OK.
3. In the trigger editor that opens on the right, enable the trigger by selecting the Enable Trigger check box.
4. Select User Defined Event from the drop-down list in the Condition Type section.
5. In the User Defined Event Name field, supply a name for the event.

You can use a regular expression, for example, `run*`, to match more than one similar user-defined event name. For this example, you would supply the name `runAReport`.

6. For Action Type, select the type of action to be triggered from the drop-down list.
7. In the Action section, enter the options for the action type. The options are described in the section [Action Pane, page 621](#).

Select Exhaust output cursors, if the procedure is a SQL script that contains a PIPE cursor.

For example, if you want email notifications sent, type and confirm the email addresses of the recipients to receive notification, as needed. You can specify a list of email addresses in the address fields by separating each one with a comma (,) or semicolon (;). Click the Info tab. Specify the Maximum Number In Queue field to the maximum number of times this trigger is to be fired if multiple periods have elapsed while a recurrence restriction prevents the trigger from firing. Most triggers should fire only once when the next available active operation window, but there might be cases when more than one trigger action should be initiated at the next opening of the recurrence restriction. This number should not be negative.

8. Save the trigger.

If the Save option is not enabled, select File > Refresh All to refresh the resources and enable the Save option.

### To test your user-defined event trigger

- Run the procedure CallsGenerateEvent that was created as described in [Creating a User-Defined Event Trigger, page 320](#).

## Creating Email Alerts

You can trigger email notifications for TDV actions or events.

**Tip from an expert:** The following configuration parameters are left over from functionality that does not send email alerts: Email Addresses for CC, Enable Email Events, Email Addresses.

### To enable email alerts

1. Open and log in to Studio.
2. From the Administration menu, choose Configuration.
3. Navigate to Server > Configuration > E-Mail.
4. Set values for the following:

Configuration Parameter	Description of Value	Example
From Address	Email address that you want to appear in the From line for alerts.	meg@queenbeesknees.net
SMTP Host Name	Name of the email server host.	javamail.queenbeesknees.com
Maximum number of rows included in email attachment.	If set to 0, there is no restriction on the size of the email attachment.  If set to a value greater than 0, the value is used as the maximum number of rows allowed for the attachment.	0

5. Save and exit the Configuration window.
6. From the Studio resource tree, right-click and select New Trigger.

7. Name and enable it.
8. Set the type of event that you want to trigger the alert. For example, a system event such as a cache refresh or data source going down. For information on how to set the different types of triggers, see the *TDV User Guide*. Choose System Event to collect information for typical TDV events including, Metrics collection, caching actions, and request spikes.

Typical Event Areas	System Event Name
Metrics Alerts	MetricsPersistentFailure
	MetricsTruncationFailure
	MetricsBackupFailure
	MetricsRestoreFailure
	StatisticsGatheringFailure
Caching	CacheRefreshFailure
	CacheRefreshSuccess
Cluster Management	ClusterServerJoined
	ClusterServerConnected
	ClusterServerDisconnected
	ClusterServerShunned
Data Source Management	DataSourceDown
	DataSourceUp
Request Management	RequestFailure
	RequestInactive
	RequestRunForTooLong
	RequestsSpike
	TransactionFailure
Resource Management	ResourceLock
	ResourceUnlock
Errors and Login Management	ErrorsSpike
	FailedLoginSpike

Typical Event Areas	System Event Name
Server Management	ServerStart ServerStop
Trigger Management	TriggerStart TriggerEnd TriggerFail

9. Select the Action Type of Send E-mail.
10. Specify a Resource path. For example, /shared/examples/ds\_orders/tutorial/customers.
11. Type the email addresses for which to send the email alerts. For example, meg@queenbeesknees.net.
12. Type a meaningful Message Subject.
13. Type a meaningful Message Body.
14. Save the trigger.



# Publishing Resources

---

This topic describes publishing of TDV-defined resources. You can publish almost any object that you create in TDV, including views and procedures.

- [About Publishing Resources, page 326](#)
- [About the TDV DDL Feature, page 327](#)
- [About the OData Feature, page 328](#)
- [Accessing REST-Based Web Services Using JSON, page 338](#)
- [Publishing Resources \(Creation, Access, and Deletion\), page 339](#)
- [Publishing Resources to a Database Service, page 340](#)
- [Publishing Resources to a Database Service with OData, page 342](#)
- [Configuring DDL for a Data Service, page 343](#)
- [Configuring TEMP Table Space for a Data Service, page 345](#)
- [Publishing Resources to a Web Service, page 346](#)
- [Web Services Security, page 364](#)
- [Security and Privileges on Published Resources, page 368](#)
- [Disable OData for Published Data Sources, page 369](#)
- [Unsupported Resource List Limit, page 370](#)

## Updating Published Resources

Published resources are automatically updated if you change their source resource using Studio. Typically you should only add new resources to your published folders.

## About Publishing Resources

Resources are initially defined in a Studio user workspace or in a Studio shared workspace, but they are not available for end-user consumption until they are published. You can publish any type of tabular data (views, data stored in a table in a text file, relational database tables, or LDAP tables) or procedure (SQL scripts, Java procedures, transformations, parameterized queries, and packaged queries). You can also publish an entire data source. The structure of the data source is preserved in the published version.

TDV does not recommend publishing a database table directly. The recommendation is to create a composite view of the table and publish the view.

Any time an original resource is modified, the corresponding published resource reflects the change. Also, you can access and use the data from an original resource through the corresponding published resource.

You can make resources available to client applications by publishing them as Data Services. For quick steps, see [Publishing Resources \(Creation, Access, and Deletion\)](#), page 339.

Resources can be published as:

- Databases—You can create TDV databases, catalogs, and schemas in this container to publish tabular data and procedures. You can create as many TDV databases and schemas as you need. You can query the published tabular data as you would query any normal database.

For details, see [Publishing Resources to a Database Service](#), page 340.

Optionally for database services, you can learn about the following options to decide if you would like to implement them in your environment:

— [About the TDV DDL Feature](#), page 327

— [About the OData Feature](#), page 328

- Web services—You can create Web services within this container. Within a Web service, you can publish tables and procedures as links to the actual resources.

For details, see [Publishing Resources to a Web Service](#), page 346.

Optionally for Web services, you can decide how to manage XML objects for implementation in your environment:

— [Accessing REST-Based Web Services Using JSON](#), page 338

Resources are published to the Data Services node in the resource tree. The Data Services node is a published interface that should be organized for the convenience of the client that needs to access that data.

For details on how client applications can query and consume published resources, see the *TDV Client Interfaces Guide*. Connectors must be defined prior to publishing resources over JMS. See “Configuring TDV Data Connections” in the *TDV Administration Guide*.

## About the TDV DDL Feature

In addition to publishing to a database data service, you can use the TDV DDL (Data Definition Language) feature to manipulate tables in a physical data source. Also included in this topic are:

- [Managing Data Type Mappings for the TDV DDL Feature, page 327](#)
- [TDV DDL Limitations, page 328](#)
- [Netezza DDL Creation Limitations, page 328](#)

When your client application creates a table in a data source, it uses the connections and protocols established with TDV. A created table is immediately added to the TDV resource tree and can be manipulated like any other table object within TDV. TDV DDL CREATE TABLE supports the following features (as supported by the underlying data source):

- Column name specification
- Column type specification (after consulting the capabilities framework to determine type mapping appropriate to the data source)
- Column nullability specification
- Primary key specification

If your client application needs to DROP a table, the table is dropped from both the data source and the TDV resource tree directly. No re-introspection of the data source is needed to see the change within TDV.

This feature can be used to improve the performance of queries or reports, because it lets you create and drop temporary tables as needed to optimize actions.

### Managing Data Type Mappings for the TDV DDL Feature

TDV can create tables in a wide variety of data source types, and so TDV consults its capabilities framework to determine the mappings between the data type name in the TDV query and the corresponding data type in the native data source. You can override the data type mappings, or specify new mappings, by defining custom data adapters for TDV. For more information, see [Adding and Removing Data Source Resources, page 76](#).

Based on testing, we recommend that you use the following data type mappings for custom adapters that you intend to use with MicroStrategy.

Database	Custom Data Type Mapping
MySQL with MicroStrategy	FLOAT -> DOUBLE
Oracle with MicroStrategy	DOUBLE -> NUMERIC

### TDV DDL Limitations

- If client applications are open and accessing data, and the temp table containers change, the updated settings might not be visible until the client applications sign in again. Temp tables created before the change are not deleted from the database.
- For data sources that make use of pass through login, active temp tables might not get cleaned up during a TDV Server shutdown. TDV logs all those tables which it cannot clean up in the cs\_server.log file at server startup.

### Netezza DDL Creation Limitations

TDV cannot use DDL to create the following data types in Netezza data source tables:

- BINARY
- BLOB
- CLOB
- IMAGE
- LONG
- LONGRAW
- NCLOB
- NTEXT
- TEXT
- TIMESTAMP
- VARBINARY

## About the OData Feature

OData is a Web protocol that provides JDBC-like access for querying and updating data from a variety of sources, including relational databases, file systems, content management systems and websites. OData allows you to query a data source through the HTTP protocol. Optionally, you can configure transport-level security and authentication methods. TDV uses odata4j to parse OData queries.

TDV supports the reformatting of results, and several system query options. These standard OData syntax options are discussed on the OData website, [odata.org](http://odata.org).

- [OData Support Limitations, page 329](#)

- [OData v4 Support Limitations, page 329](#)
- [OData Features, page 330](#)
  - [Reformatted Results, page 330](#)
  - [System Query Options, page 330](#)
- [OData v4 Features, page 333](#)

### About OData v4

TDV supports OData v4 in addition to the previous version of OData. The new version of OData is available as a separate tab adjacent to the older version. The standard OData v4 syntax options are discussed in the website <http://docs.oasis-open.org/odata/new-in-odata/v4.0/cn01/new-in-odata-v4.0-cn01.html>

Following are the OData v4 features:

- [Supported Operators, page 333](#)
- [Supported Functions, page 334](#)
- [Support for Published Resources, page 336](#)
- [Supported Query options, page 336](#)

## OData Support Limitations

TDV does not support the following features:

- Procedures and resources where a primary key is *not* defined
- OData import functions
- OData navigation links
- OData is-or-is-child-of (IsOf) functions
- \$count
- The resource you want to publish through OData, must have a primary key defined. For details, see [Defining Primary Key for a View or Table in the Indexes Panel, page 156](#).

## OData v4 Support Limitations

Following are the limitations with OData v4:

- Navigation links are not supported.

- OData v4 is not compatible with the previous versions.
- OData v4 service is not supported in streaming mode.

## OData Features

### Reformatted Results

By default in TDV, all resources that are published as database data services are available through OData in the XML-based Atom format. Client interfaces (the applications requesting data) can tell OData to reformat the Atom results to JSON using `$format=json` (instead of the default `$format=atom`) in the client interface definitions. For example:

```
http://services.odata.org/OData/OData.svc/ds_orders?$format=json
```

A client that wants only JSON responses might set the header to something similar to this:

```
GET /OData/OData.svc/ds_orders HTTP/1.1 host: services.odata.org accept: application/json
```

Client applications can choose to support only specific content types, or to support all content types. To accept all content types, the header might look like this:

```
GET /OData/OData.svc/ds_orders HTTP/1.1 host: services.odata.org
```

### System Query Options

You can use options to filter out unqualified records on the OData server side, before the data is returned. This can significantly reduce the amount of data transferred, and improve performance, compared to applying filters using the SQL WHERE clause on the TDV side.

#### Expand Option

The expand option retrieves records and includes their associated objects. For example,

```
http://services.odata.org/OData/OData.svc/ds_orders/?$expand=orders
```

For each entity within the product's entity set, the values of all associated orders are represented in-line.

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/DemoService/Products('?$expand=orders')
```

## Filter Option

The filter option retrieves only records that meet certain criteria. For example, [http://services.odata.org/OData/OData.svc/ds\\_orders/?\\$filter=orderid gt 1000](http://services.odata.org/OData/OData.svc/ds_orders/?$filter=orderid gt 1000)

This request is used for query and return only records whose orderid value is greater than 1000.

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/DemoService/Products('$filter=orderid gt 1000')
```

## OrderBy Option

The orderby option arranges the returned records in the order of a designated entity's values. For example,

[http://services.odata.org/OData/OData.svc/ds\\_orders/?\\$orderby=customerid](http://services.odata.org/OData/OData.svc/ds_orders/?$orderby=customerid)

This request displays records in the order of customerid values.

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/DemoService/Products('$orderby=customerid')
```

## Skip Option

The skip option retrieves records by skipping a specific number of rows. For example,

[http://services.odata.org/OData/OData.svc/ds\\_orders/?\\$skip=2](http://services.odata.org/OData/OData.svc/ds_orders/?$skip=2)

This request returns all records except the first two rows.

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/OData.svc/ds_orders('$ skip=2')
```

## Top Option

The top option retrieves the first *n* records. For example,

[http://services.odata.org/OData/OData.svc/ds\\_orders/?\\$top=4](http://services.odata.org/OData/OData.svc/ds_orders/?$top=4)

This request returns the first four rows.

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/DemoService/Products('$ top=4')
```

## Select Option

The select option retrieves values in the column with the specified name. For example,

[http://services.odata.org/OData/OData.svc/ds\\_orders/?\\$select=shipname](http://services.odata.org/OData/OData.svc/ds_orders/?$select=shipname)

All returned records display only the values in the column named shipname. The other columns display [NULL].

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/DemoService/Products('?$select=shipname')
```

### **Combinations of Options**

You can concatenate system query options by putting ampersands between them. For example,

```
http://services.odata.org/OData/OData.svc/ds_orders/?$filter=orderid gt 1000&$top=2
```

This request return the first two rows whose orderid is greater than 1000.

The corresponding TDV SQL query would be:

```
SELECT * from /shared/OData/ODataDemo/DemoService/Products('?$filter=orderid gt 1000&$top=2')
```



## OData v4 Features

### Supported Operators

Authentication Options	Description	
<b>Comparison Operators:</b>		
eq	Equal	companyname eq 'Able Computing'
ne	Not Equal	companyname ne 'Able Computing'
gt	Greater than	price gt 20
ge	Greater than or equal	price ge 10
lt	Less than	price lt 20
le	Less than or equal	price le 100
<b>Logical Operators</b>		
and	Logical and	Price le 200 and Price gt 3.5
or	Logical or	Price le 3.5 or Price gt 200
not	Logical negation	not endswith(Description,'milk')

Operator	Description	Example
<b>Arithmetic Operators</b>		
add	Addition	Price add 5 gt 10
sub	Subtraction	Price sub 5 gt 10
mul	Multiplication	Price mul 2 gt 2000
div	Division	Price div 2 gt 4
mod	Modulo	Price mod 2 eq 0
<b>Grouping Operators</b>		
()	Precedence grouping	(Price sub 5) gt 10

## Supported Functions

Function	Example
<b>String Functions</b>	
contains	contains(CompanyName,'freds')
endswith	endswith(CompanyName,'Futterkiste')
startswith	startswith(CompanyName,'Alfr')
length	length(CompanyName) eq 19
indexof	indexof(CompanyName,'lfreds') eq 1
substring	substring(CompanyName,1) eq 'lfreds Futterkiste'
tolower	tolower(CompanyName) eq 'alfreds futterkiste'
toupper	toupper(CompanyName) eq 'ALFREDS FUTTERKISTE'

Function	Example
trim	trim(CompanyName) eq 'Alfreds Futterkiste'
concat	concat(concat(City,', '), Country) eq 'Berlin, Germany'
<b>Date Functions</b>	
year	year(BirthDate) eq 0
month	month(BirthDate) eq 12
day	day(StartTime) eq 8
hour	hour(StartTime) eq 1
minute	minute(StartTime) eq 0
second	second(StartTime) eq 0
fractionalseconds	second(StartTime) eq 0
date	date(StartTime) ne date(EndTime)
time	time(StartTime) le StartOfDay
totaloffsetminute s	totaloffsetminutes(StartTime) eq 60
now	StartTime ge now()
mindatetime	StartTime eq mindatetime()
maxdatetime	EndTime eq maxdatetime()
<b>Math Functions</b>	
round	round(Freight) eq 32
floor	floor(Freight) eq 32
ceiling	ceiling(Freight) eq 33
<b>Type Functions</b>	
cast	cast(ShipCountry,Edm.String)

## Support for Published Resources

OData v4 supports

- All published database and webservice resources.
- Published views without a primary key defined.
- Procedures with multiple input and output cursors.
- Supports navigation links of tables/views with defined relationships.

### Examples

#### Call procedure which has parameters.

```
http://dvbu-vdi-002:9400/odata4/webservices/ds/LookupProduct(desiredProduct=1)
```

#### Call procedure which has input cursor

```
<m:value xmlns:m="http://docs.oasis-open.org/odata/ns/metadata"
xmlns:d="http://docs.oasis-open.org/odata/ns/data"
m:type="#Edm.LookupProductReturnType" m:context="http://dvbu-vdi-
002:9400/odata4/webservices/ws$metadata">
<m:parameters>
<d:result m:type="#Collection(Edm.result)">
<m:element>
<d:ProductName>Maxtific 40GB ATA133 7200</d:ProductName>
<d:ProductID m:type="Int32">1</d:ProductID>
<d:ProductDescription>Maxtific Storage 40
GB</d:ProductDescription>
</m:element>
</d:result>
</m:parameters>

</m:value>
```

## Supported Query options

The following query options are supported:

- \$filter
- \$select
- \$orderby
- \$skip
- \$top
- \$count
- \$search

- \$expand
- \$levels

## OData to TDV Data Type Mappings

This section shows the mapping from OData data types to TDV data types.

OData Data Type	TDV Data Type
BINARY	BINARY
BOOLEAN	BOOLEAN
BYTE	CHAR
DATE	DATE
DATETIME	TIMESTAMP
DATETIMEOFFSET	TIMESTAMP
DECIMAL	DECIMAL
DOUBLE	DOUBLE
DURATION	VARCHAR
GEOGRAPHY	VARCHAR
GEOGRAPHYCOLLECTION	VARCHAR
GEOGRAPHYLINestring	VARCHAR
GEOGRAPHYMULTILINestring	VARCHAR
GEOGRAPHYMULTIPOINT	VARCHAR
GEOGRAPHYMULTIPOLYGON	VARCHAR
GEOGRAPHYPOINT	VARCHAR
GEOGRAPHYPOLYGON	VARCHAR
GEOMETRY	VARCHAR

OData Data Type	TDV Data Type
GEOMETRYCOLLECTION	VARCHAR
GEOMETRYLINESTRING	VARCHAR
GEOMETRYMULTILINESTRING	VARCHAR
GEOMETRYMULTIPOINT	VARCHAR
GEOMETRYMULTIPOLYGON	VARCHAR
GEOMETRYPOINT	VARCHAR
GEOMETRYPOLYGON	VARCHAR
GUID	VARCHAR(36)
INT16	SMALLINT
INT32	INTEGER
INT64	BIGINT
SBYTE	TINYINT
SINGLE	DECIMAL(32,7)
STREAM	BLOB
STRING	LONGVARCHAR
TIME	VARCHAR(10)
TIMEOFDAY	TIME

## Accessing REST-Based Web Services Using JSON

JSON data objects, including array objects, would need to be created and any nested array objects need to be present before the results can be transferred. Arrays in JSON require that the data be held in memory, which for extremely large arrays can cause out of memory errors. If there are no arrays, then TDV will stream the data for better performance.

Typically, resources that contain XML data types might involve hierarchical data resulting in JSON arrays. So, you should avoid consuming the data from these resources through Web services using REST with JSON format if the resource you are consuming contains one of the following:

- The type of output parameter, or the column type in the cursor binding in one of output parameters is an XML type that might result in JSON array if the amount of data is large enough to require an array.
- Extremely large amounts of data from an XML formatted object.

For example, the following procedure is likely to perform better if it is consumed through an XML format rather than a JSON format:

```
proc (out MyFavFunct XML)
```

Review the views and procedures that you want to publish to determine if they contain XML types that will result in JSON arrays or cursors with XML data types. Depending on what you find, determine the best way for you to consume your resources.

See [Publishing Resources to a Web Service, page 346](#) for more information about consuming resources using JSON.

## Publishing Resources (Creation, Access, and Deletion)

When selecting names for your data services and resources, consider that special characters can make it difficult or impossible for clients (including Business Directory or Deployment Manager) to display or consume the published resources. For example, Business Directory cannot see the data for a data source with the name “dsInv/publish”.

You can do the following for published resources:

- Access its underlying source as it exists in Studio.
- View the resource content if it is a table or view.
- Rebind to a difference source. See [Rebinding a View, page 165](#) for details.

### To publish resources

1. From the resource tree, select one or more resources that you want to publish.
2. Right-click and select Publish.

3. Select from the list of existing data services or create a new data service:
  - a. Select Databases or Web Services.
  - b. Click Add Composite Service or Add Composite Web Service. Depending on what is selected, the buttons are active or unavailable.
  - c. Type a name for the new data service that you want to use to hold your published resource.
  - d. Click OK. The new data service is created.
  - e. Click OK to save the resource into the new data service.
4. Finish definition of your data service by using the instructions in one of the following sections:
  - [Publishing Resources to a Database Service, page 340](#)
  - [Publishing Resources to a Web Service, page 346](#)

#### **To access the underlying source of a published resource**

1. Expand the published object so that you can see the resources it contains.
2. Double-click the published resource to open it.
3. In the editor that opens on the right, click to open the Info tab.
4. Click Open Source.

#### **To view the contents of a published table or view resource**

1. Double-click the published table or view to open it.
  - Click Show Contents, or right-click at the table or view's name in the resource tree and select Show Contents.

#### **To delete published resources**

- Right click the parent folder or single resources and select Delete.

## **Publishing Resources to a Database Service**

To make tabular data and procedures available for querying and manipulation as a TDV database service, you need to publish them to a container (folder) under Data Services/Databases.



You can create as many TDV databases and schemas as you need, and organize them in multiple folders. The published tabular data can be queried like any normal database.

This section describes general publishing instructions. If you would like to define one of the optional TDV DDL or OData features for your database service, see the following sections:

- [Publishing Resources to a Database Service with OData, page 342](#)
- [Configuring DDL for a Data Service, page 343](#)

### Considerations

If you plan to consume your published data from an Excel spreadsheet, you must publish the data tables using catalogs. For example, create a catalog under Data Service/Databases/<catalog> so that the data from the resources there can be used through an Excel client interface.

When selecting names for your data services and resources, consider that special characters can make it difficult or impossible for clients (including Business Directory or Deployment Manager) to display or consume the published resources. For example, Business Directory cannot see the data for a data source with the name “dsInv/publish”.

### To publish a resource to a database service

1. If necessary, create a folder under Data Services/Databases where you want to publish the resource.
2. Highlight one or more tables, view, or procedure in the resource tree.
3. Select one or more resources, right-click, and select Publish or select Resource > Publish from the Studio menu bar.

The Publish <resource\_path\_and\_name> window appears.

4. Select the folder under Data Services/Databases where you want to publish the resource.

The resource name is displayed in the Name field at the bottom of the dialog.

5. Optionally, type a different name in the Name field—for example, CompositeView\_Published\_As\_a\_DB.
6. Optionally, check Overwrite existing published resources of the same name.
7. Click OK.

The resource now appears in the resource tree in the folder where you published it.

## Publishing Resources to a Database Service with OData

You can use OData to publish resources to a database service.

You can use multiple columns for filtering a published OData resource by creating a unique index for the resource and then selecting two or more columns as index columns.

### To publish resources for a database service and define OData options

1. Follow the instructions in [Publishing Resources to a Database Service, page 340](#).
2. Open the database service that you created (at the level right below Data Services/Databases).

The database service opens on the OData panel.

Views or tables published through OData require a primary key. If a primary key does not exist, you must create one. For details, see [Defining Primary Key for a View or Table in the Indexes Panel, page 156](#).

The list of endpoint Service URLs of the OData producers is exposed. There is one producer endpoint for each data source, catalog, or schema in the published database that contains table links.

3. In the Transport Level Security section of the OData panel, select from the following options.

TLS Option	Description
Enable SSL/TLS	Allows access to OData endpoint through the HTTPS protocol with SSL/TLS to secure data over the network. You must check this option to access either of the next two options. This option is checked and dimmed (unavailable to clear) after Require SSL/TLS and/or Validate Client Certificate is checked.
Require SSL/TLS	When this is checked, HTTP access is disabled, and access to OData endpoints must use HTTPS.
Validate Client Certificate	When this is checked, the client must present a certificate to the server during authentication, and the server must validate it.

- In the HTTP Authentication Methods section, select one or more of the options listed in the table.

Authentication Options	Description
Basic	Allows users to present plain-text username and password credentials for authentication.
NTLM	Enables NTLM protocol for authentication of username and password credentials.
Digest	Enables a digest-based protocol for authentication of username and password credentials.
Negotiate	Enables client and server to negotiate whether to use NTLM or Kerberos Protocol (thus making Kerberos available).

- In the Unsupported section, review the list of resources that are not available through OData.  
The Reason column explains why resources are unsupported. Determine if you want to fix any issues that caused them to appear on this list. For example, you could add primary keys to resources that do not have them ([Defining Primary Key for a View or Table in the Indexes Panel, page 156](#)).
- Save your changes.
- Optionally to use multiple columns for filtering, specify one or more columns for filtering, see [Defining Primary Key for a View or Table in the Indexes Panel, page 156](#).

## Configuring DDL for a Data Service

The TDV DDL feature allows TDV to use DDL to directly create or drop tables in a physical data source. On the TDV DDL tab you can specify the path to a relational container (catalog or schema) for DDL submission. The DDL will be submitted by TDV clients (that is by a client that uses JDBC, ODBC, or ADO.net protocols).

Having multiple locations within a data source for the manipulation of data, helps avoid conflicts when several users are attempting to access the same tables. This allows temp table creation in one or more data sources where related query work is being performed. In this way you can take full advantage of the TDV

optimizer's capability to push an entire query down to a database when all joined objects reside in a common data source. Data sources have a variety of proprietary optimizations, so by being able to determine where a query will run, you can determine the most optimal data source for your query to run.

For information on Netezza DDL creation limitations, see [About the TDV DDL Feature, page 327](#).

Data services support the following DDL statements:

- CREATE TABLE AS SELECT
- DROP TABLE

### DDL Studio and User Security Requirements

- The published catalog or schema and the target data source container must already exist and you must have read/write access to the objects to perform the specification creation.
- If the catalog or schema exists, you must have read/write access to the objects to perform the specification creation.
- You must have access to the underlying data source and database container using pass-through or non-pass-through authentication.

### To specify the path to a relational container for DDL submission

1. Follow the instructions in [Publishing Resources to a Database Service, page 340](#).
2. Make sure that the data source where the DDL statements will be run has all the necessary user permission settings so that the TDV and client users will have the ability to execute the DDL statements.
3. Open the database service.
4. Select the Composite DDL tab.
5. Type or browse to the container path where a client might later want to CREATE or DROP tables.

You can create the temporary tables in Oracle, Netezza, SQL Server, Teradata, MySQL, and DB2. Support for creation of other TEMP tables depends on the physical data source where you want to create them.

6. Optionally, if your data source supports it, you can specify more than one location where tables can be created or dropped. These locations are typically called Catalogs or Schemas.
  - a. Type or browse to the Published Container Path.
  - b. Type or browse to the Physical Container Path (as it exists in Studio).
  - c. Add more locations as necessary.
7. Save your changes.

See the *TDV Client Interfaces Guide* for an example of how to configure ODBC and MicroStrategy.

## Configuring TEMP Table Space for a Data Service

Temporary tables come in handy for a variety of business integration tools. The temporary tables allow the tools to store filters for visualizations because of their simplicity. Temporary tables also create space to accommodate DDL capabilities that you might also configure for your data service. Specifically, the temporary tables can streamline the creation and removal of the table for use during a working session.

You can use Studio to configure a location where you would prefer to have temporary tables created for your data services.

You can create the temporary tables in Oracle, Netezza, SQL Server, Teradata, MySQL, and DB2. Support for creation of other TEMP tables depends on the physical data source where you want to create them.

For information on limitations, see [About the TDV DDL Feature, page 327](#).

### To specify the temporary table locations

1. Follow the instructions in [Publishing Resources to a Database Service, page 340](#).
2. Open the database service.
3. Select the Temp Tables tab.
4. Type or browse to the container path where a client might later want to temporary tables.

5. Optionally, if your data source supports it, you can specify more than one location where tables can be created or dropped. These locations are typically called Catalogs or Schemas.
  - a. Type or browse to the Published Container Path.
  - b. Type or browse to the Physical Container Path (as it exists in Studio).
  - c. Add more locations as necessary.
6. Save your changes.

## Publishing Resources to a Web Service

To make tabular data and procedures available for querying and manipulation as a TDV Web service, you need to publish them to a container (folder) under Data Services/Web Services.

You can create as many TDV databases and schemas as you need, and organize them in multiple folders.

This section describes how to publish views and procedures as WSDL (Web Services Definition Language) services. The following topics are covered:

- [About WSDL and Web Service Data Services, page 346](#)
- [Publishing a SOAP Data Service, page 347](#)
- [Publishing a Contract-First WSDL and SOAP Data Service, page 353](#)
- [Moving the Namespace Declaration From Elements to the Soap Header, page 356](#)
- [Publishing a REST Service, page 357](#)

## About WSDL and Web Service Data Services

Web Services Description Language is an XML-based language that describes a Web service. The WSDL is a contract that explains the details of how that service works. A WSDL file specifies how clients can submit input to an operation, and what kind of output clients can expect in return.

Web services are Web-based applications that dynamically interact with other Web applications using an XML message protocol such as SOAP or REST. Web services can be bound to any message format and protocol. The binding profile allows specification of the HTTP transport protocol, literal encoding scheme, and document message style.

## Considerations

For WSDL data services use explicit cursor definition. The cursor should name the column.

When selecting names for your data services and resources, consider that special characters can make it difficult or impossible for clients (including Business Directory or Deployment Manager) to display or consume the published resources. For example, Business Directory cannot see the data for a data source with the name “dsInv/publish”.

## Publishing a SOAP Data Service

This section describes how to add a SOAP 1.1 or 1.2 compliant data service.

### To publish a SOAP data service

1. Select the Web Services node under the Data Services node in the resource tree.
2. Right-click and select New Composite Web Service.
3. In the Add Composite Web Service dialog, type a data service name for your new Web service.
4. Click OK.
5. From the resource tree, open the Web service that you just made.
6. Optionally, publish tables, views and procedures to the Web service.
  - a. Select one or more tables, view, or procedure in the resource tree and right-click.
  - b. Select Publish.
  - c. Optionally, in the Publish window, edit the name to use for the published resource.
  - d. Select the Web service to which you want the resource published.
  - e. Click OK.

If, for example, you published CompositeView to the Web service you just created, and the Web service is still opened to the SOAP panel, it would be updated to display the Web service properties, operations, and parameters.

7. In the Service portion of the screen, type or select values for the following properties.

If a property *requires* a value, a default value is already assigned to it.

Properties	Required	Description
Enabled	Yes	True (the default value) tells the system you want to use the information that you have defined on this tab.
Target Namespace	Yes	Replaces the default value with the location of your SOAP installation.
Port Type Name	Yes	Name of the port.  SOAP Web services are described with WSDL. WSDL defines a Port Type as an abstract collection of operations. Use a WSDL to describe the Web service and create a Port Type entry in the WSDL. The port type name is arbitrary, though it must be a legal QName.
Binding Name	Yes	A unique binding name that can be referenced from elsewhere in the WSDL definition.
Enable Contract First	Yes	The default value is false. Select true to point to your predefined WSDL and WSDL operations. For information on how to create the service, see <a href="#">Publishing a Contract-First WSDL and SOAP Data Service, page 353</a> .
Enable MTOM	Yes	Valid values are true or false. Set to true to enable the use of Message Transmission Optimization Mechanism (MTOM), a method of sending binary data to and from Web services. After it is enabled you must complete the definition of binary parameter types.
Security Policy	Yes	List shows all of the available policies that are defined under localhost/policy/security.
SAML Validator Class	No	Name of the Java class that lets users validate SAML assertions.



Properties	Required	Description
Subject Mapper Class	No	<p>Define a Java class for your SAML content using TDV's extended Java API Subject Mapper, which can be found in:</p> <p>&lt;TDV_install_dir&gt;\apps\extension\docs\com\compositesw\extension\security\SubjectMapper.html</p> <p>Use method <code>samlSubjectToCompositeUser</code> to map <code>samlSubject</code> to an existing TDV user, so that this SAML principal has the same privileges as that user.</p> <p>After you create the Java class, save the JAR file to the &lt;TDV_install_dir&gt;\apps\server\lib folder.</p>
Endpoint URL Path	Yes	The path of the endpoint URL for this Web service. Default is the name (with spaces removed) you used for the Web service.
SOAP11 Context Url Path		The path in which a SOAP object should appear. Associating an object to a certain page on your site.
SOAP12 Context Url Path		The path in which a SOAP object should appear. Associating an object to a certain page on your site.
WSDL URLs		Property heading.
HTTP/SOAP 1.1		The URL of the HTTP SOAP 1.1 WSDL file that can be used to access the operation.
HTTP/SOAP 1.2		The URL of the HTTP SOAP 1.2 WSDL file that can be used to access the operation.
HTTPS/SOAP 1.1		The URL of the HTTPS SOAP 1.1 WSDL file that can be used to access the operation.
HTTPS/SOAP 1.2		The URL of the HTTPS SOAP 1.2 WSDL file that can be used to access the operation.

If you have published views or procedures to this service, you can perform following steps.

- From the upper part of the Operations section, select a Web service table, view, or procedure that is available for use.

9. In the lower part of the Operations section, type or select values for the properties listed in the following table.

Property	Description
Security Policy	Lists all available policies defined under localhost/policy/security.
SOAP Action	Typically, this field is unused. If this value is defined as part of your contract-first WSDL, the value is displayed in this field.
<b>Input Message</b>	
Parameter Style	<p>This required value applies to all parameters.</p> <ul style="list-style-type: none"> <li>• Select WRAPPED when multiple parameters might use the BODY location. The wrapper element is the child of the SOAP BODY and the parameter elements are children of the wrapper element.</li> <li>• Select BARE when exactly one parameter with a location of BODY and its element is the only child of the SOAP BODY. All other parameters of the same direction must be mapped to another location—for example, HEADER.</li> </ul>
<b>Wrapper</b>	
Element Name	<p>Unique name to give to the wrapper element. For example, if you type wrappedOrderParams here, the WSDL XML includes an element:</p> <pre>&lt;wrappedOrderParams&gt; &lt;/wrappedOrderParams&gt;</pre>
Element Type	Row element type.
Message Name	Unique name for the wrapper message.
Part Name	Name of the message part that represents the wrapper element.
Security Policy	Security policy to use on the input message.

Property	Description
<b>Output Message</b>	
Parameter Style	<p>This required value applies to all parameters.</p> <ul style="list-style-type: none"> <li>• Select WRAPPED when there might be multiple parameters that use the BODY location. The wrapper element is the child of the SOAP BODY and the parameter elements are children of the wrapper element.</li> <li>• Select BARE when there is exactly one parameter with a location of BODY and its element is the only child of the SOAP BODY. All other parameters of the same direction must be mapped to another location, for example, HEADER.</li> </ul>
<b>Wrapper</b>	
Element Name	<p>Unique name to give to the wrapper element. For example, if you type wrappedOrderParams here, the WSDL XML includes an element:</p> <pre>&lt;wrappedOrderParams&gt; xxx &lt;/wrappedOrderParams&gt;</pre>
Element Type	Element type of your row element.
Message Name	Unique name to give to the wrapper message.
Part Name	Name of the message part that represents the wrapper element.

10. Repeat for each operation or view you want to define for the Web service.
11. If your operation has parameters, go to the upper part of the Parameters portion of the screen and select a parameter from the list.
12. In the lower part of the Parameters portion of the screen, you can view and edit the properties and values of the parameter you selected in the upper part of the Parameters section.

Property	Description
Name	Name of the parameter. Cannot be edited.
Element Name	Fully qualified name to give to the input parameter, output parameter, or output cursor; or name (relative to the cursor path) to give to the column.

Property	Description
Direction	(Not listed for columns) Indicates the direction of the cursor. Cannot be edited.
Binding Location	<p>When the selected operation is a procedure, you can define binding locations. If the message is BARE, exactly one parameter can use the BODY binding location.</p> <p>The available locations for input are: BODY, HEADER</p> <p>The available locations for output are: BODY, FAULT, HEADER, HEADERFAULT</p>
Row Element Name	<p>(Cursor only) Unique name to give to the row element of the cursor. For example, if you type myFavoriteRow here, the WSDL XML includes an element:</p> <pre>&lt;myFavoriteRow&gt; &lt;/myFavoriteRow&gt;</pre>
Row Type Name	(Cursor only) Type value of this row element.
Cursor Type Name	(Cursor only) Unique name for the type that defines the global cursor element.
MTOM CONTENT TYPE	<p>If the parameter is binary, you should set the parameter values to VALUE_TYPE_BINARY, VALUE_TYPE_BLOB, or VALUE_TYPE_CLOB.</p> <p>The content-type values are available from a list of values. The default is application/octet-stream (a binary file). This header indicates the Internet media type of the message content, consisting of a type and subtype, that is accepted.</p>

13. Repeat for each parameter that is to be defined for the Web service.
14. Save your definition.

## Publishing a Contract-First WSDL and SOAP Data Service

You can make existing WSDL definitions available through TDV by publishing them as a Web service that uses SOAP 1.1 or 1.2. When publishing contract-first WSDL, you start with the WSDL contract, and use TDV to fill out the rest of the contract. In this situation, use TDV to import existing WSDL files by using a definition set. Start with the XML Schema and WSDL contract, and finish by creating the necessary procedure code. The procedure code is created for you by TDV and is saved in the location specified.

**Note:** REST services do not have an associated WSDL contract.

### Behavior of Abstract Contract-First WSDL

When you choose to use the abstract option with your contract-first WSDL, TDV automatically generates your input and output messages for you.

### Behavior of Concrete Contract-First WSDL

When you choose to use the concrete option with your contract-first WSDL, TDV reads and uses the input and output binding messages that you have defined. The bindings that you have defined to control the security and transportation of the messages is retained and surfaced through Studio.

You can specify the port name for the binding.

### To publish a contract-first WSDL and SOAP data service

1. Create a WSDL definition set. See [Creating a WSDL Definition Set, page 304](#). For example, create NewWSDLDefinitionSet under the shared node of the TDV resource tree.
2. Make sure you are logged into Studio as a user with enough rights to publish resources.
3. Select the Web Services node under the Data Services node in the resource tree.
4. Right-click and select New Composite Web Service.  
The Add Composite Web Service dialog opens.
5. For Data Service Name, enter a name for your web service.
6. Click OK.
7. From the resource tree, open the web service that you just made.  
The Web service opens on the SOAP panel.


8. In the Service section, click Enable Contract First and set its value to true.

Select true to point to your predefined WSDL and WSDL operations. After TDV retrieves your WSDL definitions, you must finish defining the WSDL operations using the Studio WSDL Definition Editor.

A new property, Contract, appears below Enable Contract First.

9. Expand Contract.
10. Double-click WSDL Contract under Contract and type the resource path, or browse to your WSDL definition set.

Visible if Enable Contract First is set to true. Type or use the browse button to specify the WSDL definition set that you have defined within TDV.



11. Save your Web service.

Studio reads the WSDL definition set and populates the SOAP panel with the characteristics specified in the definition set.

12. In the Service portion of the screen, type or select values for the following properties:

If the property has a default value, a value is required.

Properties	Description
Enabled	True (the default value) tells the system to use the information that you have defined on this tab.
Target Namespace	Displays the location of your SOAP installation. If your WSDL contract has a target namespace defined, it will be displayed in this field.
Binding Name	A unique binding name that can be referenced from elsewhere in the WSDL definition. This name signifies that the binding is bound to the SOAP protocol format: envelope, header and body.

Properties	Description
Contract	Property heading that is visible if Enable Contract First is set to true.
Contract Style	<p>Visible if Enable Contract First is set to true. Select ABSTRACT or CONCRETE. Use concrete if your WSDL definitions contain bindings that you have defined to control the security and transportation of WSDL messages.</p> <p>If the WSDL that you have selected in the WSDL Contract field does not contain concrete bindings, you will not be able to select the CONCRETE Contract Style.</p>
Service Name	Visible if Enable Contract First is set to true and if Contract Style is set to CONCRETE. Values are populated from the WSDL imported through your definition set.
Port Name	Visible if Enable Contract First is set to true and if Contract Style is set to CONCRETE. Select the port from the list of values. The port does not have to be unique within the WSDL, but it must be unique within the Web Service.
Port Type Name	Visible if Enable Contract First is set to true. Select the port from the list of values. The port does not have to be unique within the WSDL, but it must be unique within the Web Service.
Implementation Folder	Visible if Enable Contract First is set to true. Points to a TDV folder where the implementation procedures are generated. Double-click to edit the location.
Enable MTOM	Valid values are true or false. Set to true to enable the use of Message Transmission Optimization Mechanism (MTOM), a method of sending binary data to and from Web services.
Security Policy	Lists all available policies defined under localhost/policy/security.
SAML Validator Class	Type the name of the Java class that allows users to validate SAML assertions.
Subject Mapper Class	<p>Define a Java class for your SAML content using TDV's extended Java API Subject Mapper, which can be found in:</p> <pre>&lt;TDV_install_dir&gt;\apps\extension\docs\com\compositesw\extension\security\SubjectMapper.html</pre> <p>Use method <code>samlSubjectToCompositeUser</code> to map <code>samlSubject</code> to an existing TDV user, so that this SAML principal has the same privileges as that user.</p> <p>After you create the Java class, save the JAR file to the  <pre>&lt;TDV_install_dir&gt;\apps\server\lib</pre> folder.</p>

Properties	Description
Endpoint URL Path	The path of the endpoint URL for this Web service. Default is the name (with spaces removed) you used for the Web service.
WSDL URLs	Property heading.
HTTP/SOAP 1.1	Displays the HTTP SOAP 1.1 URL that can be used to access the operation.
HTTP/SOAP 1.2	Displays the HTTP SOAP 1.2 URL that can be used to access the operation.
HTTPS/SOAP 1.1	Displays the HTTPS SOAP 1.1 URL that can be used to access the operation.
HTTPS/SOAP 1.2	Displays the HTTPS SOAP 1.2 URL that can be used to access the operation.

- From the upper part of the Operations portion of the screen, select a Web service view or procedure that is available for use.

This portion of the screen is automatically populated with the WSDL operations that were imported or defined in the WSDL definition set. If the definition set changes, you might need to save your Web service to see the latest list of WSDL operations. If you publish views or other procedures to the Contract First Web service, they should automatically appear in the Operations list.

- To edit the Operations and Parameters portions of the screen, see the steps in [Publishing a SOAP Data Service, page 347](#).
- In the lower part of the Parameters portion of the screen, if you have chosen to define a concrete WSDL, you can view some additional properties and values of the chosen parameter.

Element Name and Message Name for concrete WSDLs can be viewed, but not edited, from this Studio editor.

- Save your definition.

## Moving the Namespace Declaration From Elements to the Soap Header

In a published SOAP web service, to move the namespace declaration out of each element and define the namespace in the SOAP header you can use a Studio configuration parameter.



### To toggle the location of the namespace declaration

1. From Studio, select Administration > Configuration from the Studio Modeler toolbar to open the Configuration window.
2. Locate the Declare Namespace in SOAP Envelope Element configuration parameter.
3. Set the value to true for the namespace to be declared once in the header or set it to false to have the namespace defined in each element.
4. Click OK to save changes and close the window.

### For Example

When the value of the configuration parameter is false, each element would have something like this:

```
<soap-env:Envelope xmlns:soap-env="http://schemas.xmlsoap.org/soap/envelope/">
<soap-env:Header>
<ns1:TestSQLScriptCustomevalueOutput
xmlns:ns1="http://tempuri.org/">custom</ns1:TestSQLScriptCustomevalueOutput>
</soap-env:Header>
```

And if the value of the configuration parameter is changed to true, then it is declared once as a namespace in the SOAP header

```
<soap-env:Envelope xmlns:soap-env="http://schemas.xmlsoap.org/soap/envelope/" xmlns:ns1="http://tempuri.org/">
<soap-env:Header>
<ns1:TestSQLScriptCustomevalueOutput>custom</ns1:TestSQLScriptCustomevalueOutput>
</soap-env:Header>
```

## Publishing a REST Service

This section describes how to add a REST-compliant data service. The configuration steps are optional.

- [Configuration Options for Publishing a REST Service, page 357](#)
- [Publishing a REST Data Service, page 359](#)

### Configuration Options for Publishing a REST Service

This setting determines whether to enclose an XML output parameter with a wrapper element in a TDV REST Web Service when the parameter is a generic XML type.

### To configure XML output parameter wrapper elements

1. From the Administration menu, choose Configuration.
2. Search for or navigate to the Generic XML REST Output Parameter Wrapper parameter.
3. Set the value to False to exclude the wrapper element, or set the value to True to include the wrapper element.
4. Stop and restart the TDV server to ensure that the parameter value change is recognized.
5. Make sure that the procedure that you define has a variable of data type 'XML'.

### For Example

Assume that the Output parameter for the following code snippet is cust\_data and that the data type is a generic XML type.fl

```
<ns1:cust_addr>
<mail_addr>
...
</mail_addr>
</ns1:cust_addr>
```

Set the Generic XML REST Output Parameter Wrapper parameter to true, to obtain output similar to:

```
<cust_data>
<ns1:cust_addr>
<mail_addr>
...
</mail_addr>
</ns1:cust_addr>
</cust_data>
```

If you do not want the parameter name wrapper in your output, set the configuration parameter to false. For example:

```
<ns1:cust_addr>
<mail_addr>
...
</mail_addr>
</ns1:cust_addr>
```

## Publishing a REST Data Service

### To publish a REST data service

1. Select the Web Services node under the Data Services node in the Studio resource tree.
2. Right-click and select New Composite Web Service.
3. For Data Service Name, enter a name for your Web service.
4. Click OK.
5. From the resource tree, open the data service that you just created.  
By default, the SOAP tab is displayed.
6. Optionally, publish views and procedures to the Web service:
  - a. Select one or more tables, view, or procedure from the resource tree, and right-click.
  - b. Select Publish.
  - c. In the Publish window, type the name to use for the published resource.
  - d. Select the Web service to which you want the resource to be published.
  - e. Click OK.
7. Select the REST tab.
8. In the Service portion of the screen, type or select values for the following properties.  
If the property has a default value, a value is required.

Property	Required	Description
Enable	Yes	True (the default) tells the system you want to use the information defined on this tab.
Target Namespace	Yes	Replace the default value with the location of your REST installation.
Service Name	Yes	The name to give your service.

Property	Required	Description
Enable SSL/TLS	Yes	<ul style="list-style-type: none"> <li>Require SSL/TLS — True/false</li> <li>Require Client Certificate — True/false</li> </ul> <p>SSL uses digital certificates, trusted certificate authority (CA), and encryption keys.</p> <p>When this is set to true, HTTPS/JSON and HTTPS/XML endpoints URLs are added to the Property list in the lower part of the Operations section.</p>
JSON Context Url Pat		Default value is /json.
XML Context Url Path		Default value is /xml.
JSON Format	Yes for JSON	<ul style="list-style-type: none"> <li>JSON Package Name — Default name of your JSON service. The input and output data use this package name.</li> <li>Use Parameter Name of Procedure— If true, a JSON object name with the format of parameter will be the same as the original name defined in the procedure. The default value is false. If false, the format is:  <code>&lt;package name&gt; + '!' + &lt;procedure name&gt;+&lt;parameter name&gt;</code> </li> <li>Validate XML Schema Definition Set - The default value is true. This option works in streaming mode with XML/JSON conversion and validate JSON response structure with XML definition set for XML values, will get empty or part of data if validation fails. Set this option as "false" still could get correct Json response data.</li> <li>Wrapped Cursor—If true, a JSON row object is added as a wrapper of the cursor output, for tables and procedures.</li> <li>Wrapped Table—If true, the table output is wrapped with an output JSON object with a pattern of:  <code>&lt;package name&gt; + '!' + &lt;table name&gt; + 'output'</code> </li> </ul> <p>For the wrapped options, the default value is true. Default value is consistent with an XML definition.</p>
Enable HTTP Basic	Yes	Valid values are true or false. Set to true to enable a method to provide a username and password (when making a request) that results in a string encoded using a Base64 algorithm.

Property	Required	Description
Enable HTTP NTLM	No	Used to enable NTLM authentication over HTTP.
Enable HTTP Negotiate	No	Used to enable Kerberos and Active Directory authentication over HTTP.

- From the upper part of the Operations section, select a Web service view or procedure that is available for use.  
If you publish a new view or procedure to the Web service while this window is open, you might need to close and reopen this window for it to appear in the list.
- In the lower part of the Operations section, type or select values for the properties listed in the following table.

Property	Description
HTTP Method	Select the verb associated with the procedure, for example GET, POST, PUT, or DELETE. Depending on the choices you have made for the operations field, these options might already be defined.
Operation URL Path	Specify the operation URL path as defined for your operation. Follow endpoint URL guidelines to configure your values. You can use brace tags.  You can specify a portion of the endpoint URL to be used in each Web service module. In a published WSDL file, the URL defining the target endpoint address is found in the location attribute of the port's soap:address element.

### Input Message

- |                 |   |
|-----------------|---|
| Parameter Style | <p>Use this field to determine the shape of the input argument or message. This value applies to all parameters.</p> <ul style="list-style-type: none"> <li>Select WRAPPED when there might be multiple parameters that use the BODY location. The wrapper element is the child of the REST BODY and the parameter elements are children of the wrapper element.</li> <li>Select BARE when exactly one parameter has a location of BODY and its element is the only child of the REST BODY. All other parameters of the same direction must be mapped to another location—for example, HEADER.</li> </ul> |
|-----------------|---|

### Wrapper

Property	Description
Element Name	Unique name for the wrapper element. For example, if you type wrappedOrderParams here, the WSDL XML includes an element: <code>&lt;wrappedOrderParams&gt; &lt;/wrappedOrderParams&gt;</code>
Element Type	This is the type value of your row element.
<b>Output Message</b>	
Parameter Style	The value applies to all parameters. <ul style="list-style-type: none"> <li>• Select WRAPPED when there might be multiple parameters that use the BODY location. The wrapper element is the child of the REST BODY and the parameter elements are children of the wrapper element.</li> <li>• Select BARE when there is exactly one parameter with a location of BODY and its element is the only child of the REST BODY. All other parameters of the same direction must be mapped to another location, for example, HEADER.</li> </ul>
<b>Wrapper</b>	
Element Name	Unique name to give to the wrapper element. For example, if you type wrappedOrderParams here, the WSDL XML includes an element: <code>&lt;wrappedOrderParams&gt; &lt;/wrappedOrderParams&gt;</code>
Element Type	This is the type value of your row element.
<b>Endpoint URLs</b>	
HTTP/JSON	Displays the HTTP/JSON endpoint URL for this operation.
HTTPS/JSON	Displays the HTTPS/JSON endpoint URL for this operation. Present only if Enable SSL is true in the Service section of this panel.
HTTP/XML	Displays the HTTP/XML endpoint URL for this operation.
HTTPS/XML	Displays the HTTPS/XML endpoint URL for this operation. Present only if Enable SSL is true in the Service section of this panel.

11. Save your settings.

12. Repeat the steps in [Publishing a SOAP Data Service, page 347](#) for each operation or view you want to define for the Web service.
13. If your operation has parameters, go to the Parameters portion of the screen and select a parameter from the upper list.
14. In the lower part, type or select values for the following properties for input or output parameters.

Property	Resource Type	Description
Name	All	Name of the parameter. Cannot be edited.
Row Element Name	Table View	Fully qualified name to give to the input parameter, output parameter, or output cursor; or name (relative to the cursor path) to give to the column.
Row Type Name	Table View	(Cursor only) Type value of this row element.
Cursor Type Name	Table View	(Cursor only) Unique name for the type that defines the global cursor element.
Element Name	All	Can be NULL. The default value of the Element Name field specifies the schema of the REST message that is encrypted. This procedure can be used to encrypt the REST message body.
Binding Location	Procedure	<p>When the selected operation is a procedure, you can define binding locations. If the message is BARE, exactly one parameter must use the BODY binding location.</p> <p>The available locations for input are:</p> <p style="padding-left: 40px;">ENTITY (not available for GET), QUERY, HEADER</p> <p>The available locations for output are:</p> <p style="padding-left: 40px;">ENTITY</p>
Query	Procedure	<p>The parameter-name part of a query string. The query argument can accept NULL values. For example, the following query arguments are both valid:</p> <ul style="list-style-type: none"> <li>• <code>http://localhost:9410/json/goody/data?name_arg={name_arg_value}</code></li> <li>• <code>http://localhost:9410/json/goody/data</code></li> </ul>

Property	Resource Type	Description
Default Value	Procedure	Optional. Default value to use for the parameter if a parameter value is not passed through the request.
Nullable	Procedure	Whether this field is allowed to have no value. True specifies that the parameter can be passed to the server with no value. Without a value for the parameter, all data is returned from the query.
Element Name	Procedure	Can be NULL. The default value of the Element Name field specifies the schema of the REST message that is encrypted. This procedure can be used to encrypt the REST message body.
Direction	All	Indicates the direction of the input parameter, output parameter, or output cursor. Cannot be edited.

15. Repeat the steps for each parameter to be defined for the Web service.

16. Save your definition.

### Accessing the Published REST Services

TDV provides Open API compliant specifications for all the published REST services. To access this tool, open TDV Studio and click on Help -> Published REST Web Services menu item. You can also access the specification using the url: <http://localhost:9400/rest/api-docs/webservice.html>

Using this tool, the users can get the response schema and verify that it is as expected.

**Note:** The users can only see the published REST services that they have READ privileges for.

## Web Services Security

TDV offers Web service security at two levels: transport-layer level and message level. Secure Web services are published by TDV using Web Services Security (WSS). TDV enables signing of messages with digital certificates to identify the source of the message, and encryption of the message for secure delivery to the client.

- [Supported Web Service Security Standards, page 365](#)
- [Using a Predefined Security Policy for a Web Service, page 366](#)



- [Creating and Using a Custom Security Policy for a Web Service, page 367](#)

## Supported Web Service Security Standards

The following security policies, in the form of XML files, are provided for Web service clients.

**Note:** The transport level security policies (http basic and https basic) can be applied to a SOAP Web service, but they do not prevent an anonymous user from invoking the Web service. When using the basic security policies or when creating a custom security policy, consider this security issue.

Transport or Standard	System Security Policy	Description
HTTP	Http-Basic-Authentication.xml	Policy that requires a username and password when making a request.
HTTP	Http-Negotiate-Authentication.xml	Policy that enables Kerberos authentication.
HTTP	Http-NTLM-Authentication.xml	Policy that enables NTLM authentication.
HTTP	Http-UsernameToken-Digest.xml	Policy that validates against a UsernameToken header encrypted using a nonce value.
HTTP	Http-UsernameToken-Plain.xml	Policy that validates against a UsernameToken header. The password can be in plain text.
HTTPS	Https-Basic-Authentication.xml	Policy that requires a username and password when making a request.
HTTPS	Https-ClientCertificateRequire.xml	Policy that requires client certificates.
HTTPS	Https-UsernameToken-Digest.xml	Policy that validates against a UsernameToken header encrypted using a nonce value.
HTTPS	Https-UsernameToken-Plain.xml	Policy that validates against a UsernameToken header. The password can be in plain text.
SAML	Sam11.1-Bearer-Wss1.1.xml	Method in which the bearer assertion is used to facilitate single sign-on to the web browser.

Transport or Standard	System Security Policy	Description
SAML	Sam11.1-HolderOfKey-Wss1.0.xml	Method that establishes a correspondence between a SOAP message and the SAML assertions added to the SOAP message.
SAML	Sam11.1-SenderVouches-Wss1.1.xml	Subject-confirmation method that enables an attesting entity to vouch for the identity of a subject to a party that trusts the sender.

The following legacy WSS standards are supported:

- OASIS Web Services Security: SOAP Message Security 1.0 Standard 200401, March 2004
- Username Token profile V1.0
- X.509 Token Profile V1.0

The TDV Server accepts certificate formats such as X.509 and JKS so that keys and message signatures do not need to be converted to ASCII before sending.

The TDV pipeline implementation allows SAML and Kerberos tokens to be passed through to message destinations, but TDV Server does not directly process or use SAML and Kerberos tokens.

WSS incorporates security features in the header of a SOAP message, and works in the application layer to help ensure end-to-end security for SOAP messages.

WSS UsernameToken SOAP header validation is independent of the message-security pipeline; the message security pipeline cannot process these contents.

Transport Layer Security (TLS) is supported to ensure message integrity and confidentiality through HTTPS, reducing performance overhead. If the messaging needs to pass through a proxy server, however, TLS should not be used without special handling considerations.

## Using a Predefined Security Policy for a Web Service

Security policies for Web services require a definition using the security protocol of your choice. TDV provides a generic editor that you can use to type your security policy, or you can import security policy files from anywhere in your network. Predefined and custom security policies populate the list of security policies available for defining a SOAP Web service.

After defining your policy, you can use the policy in your new or existing SOAP Web services. For more information, see [Publishing a SOAP Data Service, page 347](#).

**Note:** The transport level security policies (http basic and https basic) can be applied to a SOAP Web service, but they do not prevent an anonymous user from invoking the Web service. When using the basic security policies or when creating a custom security policy, consider this security issue.

### To use a TDV security policy

1. Open Studio.
2. Expand localhost/policy/security/system.
3. Review the list of predefined policies under system and determine the policy to use.

For descriptions of the available policies, see [Supported Web Service Security Standards, page 365](#).

4. Open a published SOAP Web service.

For more information, see [Publishing a SOAP Data Service, page 347](#).

5. Select the SOAP tab.
6. Left-click in the Value column next to Security Policy in the Services or the Operations part of the SOAP tab and choose one of the predefined or custom security policies from the drop-down list.
7. Save your changes.

## Creating and Using a Custom Security Policy for a Web Service

Security policies for Web services require a security protocol definition. You can import security policy files, or define a custom policy using the generic editor that TDV provides.

### To create a custom security policy within TDV

1. Open Studio.
2. Expand localhost/policy/security/user.

To review the security policies that TDV provides, expand localhost/policy/security/system.

3. Right-click on user and select New Policy.
4. Type a name for the security policy.

5. The security policy editor opens in the workspace pane on the Policy tab.
6. Type or import your security policy.

To import your security policy, click Insert from File and browse to the file.

7. Edit the policy as needed.
8. Optionally, click Format the Policy to formatted it according to XML standards.
9. Optionally, add annotations to the policy on the Info tab.
10. Open a published SOAP Web service.
11. Save the new policy.

If your policy definition is invalid, your security policy is created, but the invalid code is not saved. To validate what code was saved for a security policy, close the editor and reopen your policy from the resource tree.

For more information, see [Publishing a SOAP Data Service, page 347](#).

12. Navigate to the SOAP tab.
13. Left-click in the Value column next to Security Policy in the Services or the Operations part of the SOAP tab and choose your custom security policies from the drop-down list.
14. Save your changes.

## Security and Privileges on Published Resources

Using a published resource requires appropriate access privileges on both a published resource and the original resource. A published resource has its own READ and WRITE privileges to let you manipulate it in Studio, but it does not have its own run-time privileges (EXECUTE, SELECT, INSERT, UPDATE, DELETE). You can set up privileges for the published and shared areas in Studio to suit the needs and restrictions of your environment. For more information on how to set up various privileges, refer to the *TDV Administration Guide*.

Privileges on objects in the Data Source are evaluated only at the time of introspection or later when a FETCH is called during statement execution. So if privileges on an object in the data source are lowered after introspection, the error will not be caught until actual statement execution.

Column-based security privileges are set up the same way as for any other object exposed through TDV. If you restrict access to a view in the published layer, the shared area, and in the introspected data source, the column would have the same restrictions. Similarly if you mask the data in a column for a view, that data is masked in the same way for the published data.

How resource security and privileges work for a given TDV environment can vary. It is best to test several scenarios to make sure that you can access resources as expected. You can publish a table as a database, as a view through a web service, or as a view through a legacy web service, so you should check all scenarios.

When you run a `SELECT *` from an external client, the likely results are:

- An error message states that you do not have appropriate privileges on a column in your query.
- You get a result that contains **ONLY** the columns that you have privilege to see.
- The columns for which you do not have privileges have all `NULL` values.

You can control which of these outcomes occurs using a configuration parameter.

### **Controlling the Outcome of Trying to Access a Column without Permissions**

You can control which of the outcomes occurs using a configuration parameter.

#### **To control what is returned for a column for which the user lacks appropriate permissions**

1. From the Studio main menu, select Administration > Configuration.
2. In the Configuration window, navigate to Server > Configuration > Security > Enable Exception For Column Permission Deny.
3. Set this parameter to true if you want to raise an exception when column-level permissions are missing.
4. Set or leave this parameter set to false, if you want columns for which the user does not have permissions to contain `NULL`s or not be returned at all.

## **Disable OData for Published Data Sources**

You can globally disable OData for all published data sources.

**To disable OData for published data sources**

1. From the Studio main menu, select Administration > Configuration.
2. In the Configuration window, locate the Enable OData Services parameter.
3. Set this parameter to false to disable OData for published data sources.
4. Click Apply and OK to save the setting and exit the configuration dialog.

## Unsupported Resource List Limit

You can set a display limit on the number of resources that are not supported for OData Service.

**To set this limit**

1. From the Studio main menu, select Administration > Configuration.
2. In the Configuration window, locate the Show Limit of Unsupported Resource List parameter.
3. Set the value of this parameter. The default value is 100.
4. Click Apply and OK to save the setting and exit the configuration dialog.

# Exploring Data Lineage

---

This topic describes how to display and explore the data lineage from the data sources through to the published resources defined in TDV.

- [About Data Lineage, page 371](#)
- [Displaying Data Lineage, page 374](#)
- [Working with the Data Lineage Graph, page 376](#)
- [Lineage Information for Different Resource Types, page 387](#)

## About Data Lineage

When you work with resources in Studio, there are often many relationships and dependencies between resources. A composite view, for example, depends on things like data sources and procedures which might then depend on a different data source. Other views might reference the view and thus be dependent on it. Security policies, triggers, and other resources might be dependencies. Understanding these interdependencies can be useful in analyzing where data comes from, how it is derived, and how it is used.

To help you understand resource dependencies, Studio provides a data lineage graph that supports TDV modeling and data visualization capabilities. The TDV data lineage feature helps you:

- Trace where data originates—From data sources through published resources, you can trace which specific data sources contribute to each column.
- Understand how data is used and/or transformed—You can determine how the data is used or transformed by TDV resources and which data contributes to the published resources.
- Discover the impact of change and analyze dependencies—If you delete or rename a resource, the data lineage graph for related resources graphically indicates which dependent resources are impacted.

You can obtain the data lineage for all resource types, but lineage for these resources can be especially useful:

- Data sources
- Tables
- Composite views
- Models
- Procedures
- Definition sets
- Published services
- System resources

See [Lineage Information for Different Resource Types, page 387](#) for what is displayed for each resource type along with examples.

### **Determine Where Data Comes From**

The data lineage graph helps you discover:

- What data sources contribute to each column? The data lineage graph helps you understand how many systems a view is hitting and if more data is requested, where TDV gets it.
- What are the platforms for each data source? This can help with optimizations like push down, data ship, and caching.
- How many records are pulled from each data source? Combine some of the query plan functionality with data source lineage to help with data ship optimizations.

### **Determine How Data Is Used**

For any defined data source, you can open a data lineage graph that shows all TDV resources that use that data. You can then expand the resources in the lineage graph to see the columns that are participating in the lineage.

### **Determine How Data Is Transformed**

When data is modified by procedures or transformed, the data lineage graph can help you trace the resources involved and how the changes are propagated. From the data lineage graph, you can easily open the editor for any of the resources to discover exactly what the changes are. For example, you can:



- See that a projection is concatenated in a prior view, then CAST to a date, then used in a GROUP BY clause.
- See that a column is used in a JOIN or is used in a filter.
- See that a column is used in aggregate or analytical function.

## Analyze Changes and Dependencies

The data lineage graph helps you determine:

- What will be affected by a proposed change (rename, deletion, addition) to a column or resource? Upstream references are important in this use case. This includes what calls/references the column might need to also be changed (if for example a rename of the column is performed). Also important is where the column is published since that impacts external systems that could break with a change.
- How published resource/columns are provided to a consuming application and debug any issues by analyzing the downstream dependencies back to the originating system.
- What resources you need to have privileges to because of the resource dependencies. See “About Managing Dependency Privileges” in the *TDV Administration Guide* which says that a user/group must have the privileges to access all dependencies. The lineage graph can help you investigate the resources to which you need privileges.

## Lineage Panel Buttons and Controls

The following table lists the unique controls in the **Lineage** panel and what they do.

Label	Use to...
Show Detail	Display the definition of the resource in a new panel beneath the resource lineage graph. This button does not appear on the <b>Lineage</b> panel when it is opened from within a resource editor.
Save to File	Open a dialog box to save the dependencies in a file. See <a href="#">Exporting Lineage Reports to a Comma-Separated-Values File</a> , page 385.
Hide/Show Dependencies	A toggle button that hides or shows dependencies for a selected resource when enabled. By default, dependencies are displayed.
Hide/Show References	A toggle button that hides or shows references for a selected resource when enabled. By default, references are displayed.

Label	Use to...
Hide/Show Cached Tables/Views	A toggle button that hides or shows cached tables and views for direct lineage. By default, cached tables and views are displayed.
Show/Hide Indirect Links	A toggle button that shows or hides WHERE/GROUP BY/FROM and other indirect links when enabled. By default, indirect links are hidden.

## Displaying Data Lineage

You can display the data lineage for most TDV resource types. The kinds of interdependencies displayed depend on the resource type as illustrated in [Lineage Information for Different Resource Types, page 387](#).


### To display data lineage

1. Select a resource in the resource tree.
2. Open the data lineage panel by:
  - Choose **Open Lineage** from the **File** menu.

Or

  - Right-click and choose **Open Lineage** from the popup menu.

Studio displays the lineage for the selected resource including all resource dependencies and all reference resources. This example shows the data lineage for the ViewSales example view:



The data lineage graph shows:

- Where the data originates.
- What types of resources are dependences and references.
- What resources the current resource depends on.
- What resources reference the current resource.
- How a resource is derived from other resources.
- What resources are impacted, if any. Impacted resources are indicated with an icon. See [Impacted Resources, page 49](#).
- Circular references, if any.
- See which resources have security policies. The security content is not displayed but can be viewed if you have the necessary credentials.

See [Working with the Data Lineage Graph, page 376](#) for how to use the lineage graph.

## Working with the Data Lineage Graph

The data lineage panel gives you a relatively large area in which to graphically view all of the dependencies and dependent resources. See [Lineage Panel Buttons and Controls, page 373](#) for the purpose of the various buttons and controls in the data lineage panel.


You can navigate and explore the relationships and resource dependencies as follows:

To ...	Do this...
Change the focus to a different resource and display its lineage.	Double-click a resource or use the right-click menu. See <a href="#">Changing the Resource Focus, page 377</a> for more information.
Expand and collapse what is displayed.	Use the expand and collapse buttons to see a resource's contents. See <a href="#">Changing What Is Displayed, page 378</a> .
Filter the visible columns	Use the funnel button on the view title bar. See <a href="#">Filtering the Visible Columns, page 379</a> .
Go back to a previous data lineage display.	Use the navigation arrow buttons or select a resource in the history drop list. See <a href="#">Using the History Feature, page 382</a> for more information.
Open a resource's editor in another panel.	Right-click the resource and choose <b>Open</b> .
Get quick information about a resource.	Hover over the resource to display a popup. See <a href="#">Getting Resource Summary Information, page 379</a> for more information.
Get details about the resource definition.	Click the <b>Details</b> button. Displays the resource definition in the Detail beneath the lineage graph. See <a href="#">Getting Resource Details, page 380</a> for more information.
Print the lineage in a regular size or poster print.	Click the <b>Print</b> button. See <a href="#">Printing the Lineage Graph, page 383</a> for more information.
Discover impacted resources.	Impacted resources are indicated with a warning icon. You can hover over the resource to get more information. See <a href="#">Impacted Resources, page 49</a> for more information.

To ...	Do this...
Refresh the graph.	See <a href="#">Refreshing the Lineage Graph, page 383</a> for more information.
Export lineage information to a .csv file	See <a href="#">Exporting Lineage Reports to a Comma-Separated-Values File, page 385</a> .

## Changing the Resource Focus

When you view a lineage graph, the resource on which the lineage graph is based is displayed with a blue title bar. From this graph, you can change the focus to another resource to get more information about the dependencies and relationships.



### To change the resource focus

1. Open the lineage for a resource.
2. Change the focus by either of these:
  - Double-click any resource in the graph to view its lineage.

Studio displays the lineage for the selected resource. Its title bar is blue and the lineage panel tab shows the name of the new resource.

**Note:** The history list is updated and you can return to any previous lineage display.

- Right-click any resource and choose **Open** to open the resource's editor in a new tab.

## Changing What Is Displayed

The toolbar buttons let you change what information is displayed on the lineage graph as described in these sections:

### Expanding and Collapsing the Lineage Graph

- Use the **Expand All** button display column details.
- Use the **Collapse All** button hide column details.

The default is expanded.

### Hiding and Showing Dependencies

- Use the **Hide/Show Dependencies** button to hide or show dependencies.

The default is to show dependencies.

### Hiding and Showing References

- Use the **Hide/Show References** button to hide or show references.

The default is to show references.

### Hiding and Showing Cached Tables and Views


- Use the **Hide/Show Cached Tables/Views** button to hide or show cached tables and views.

The default is to show cached tables and views within the direct path of lineage.

### Hiding and Showing Indirect Links

- Use the **Hide/Show Where/Group By/From and other Indirect Links** button to hide or show indirect links which are references in a view to a column by a WHERE, GROUP BY, ORDER BY, FROM, HAVING, or other non-SELECT clause.

The default is to hide indirect links. The following example shows four indirect links that reference specific columns.




## Filtering the Visible Columns

You can filter the columns that are visible to a select group or hide/show them all.

### To filter the visible columns

1. In the Lineage panel, click the funnel button on the title bar of the selected view.




2. Select one of the filter options:
  - Show All—displays all of the columns in the view.
  - Hide All—Displays no columns in the view.
  - Visible Columns—Select or uncheck the columns to be displayed. Note that the visible columns are listed in alphabetical order which might not match the order in the display.

## Getting Resource Summary Information

You can obtain summary information about any resource in the lineage graph. You can tell the resource type by the icon next to its name.

### To display resource summary information

1. Hover your mouse over the resource.
2. Studio displays a tooltip with information about the resource.



This is the same information displayed in the resource tree tip when you hover over a resource.

You can also right-click any resource and choose **Open** to open the resource's editor in a new tab.

## Getting Resource Details

You can get detailed information about any resource in the lineage graph. For example, for tables you can display the data types for each column. For views, you can view the SQL that defines the view.


You can tell the resource type by the icon next to its name.

### To display resource details

1. Open a lineage graph.
2. Optionally, select any resource in the lineage graph.



3. Click the **Show Detail** button.




4. Optionally, select a different resource to display its details in the same tab.  
The type of information displayed depends on the resource type:

Resource Type	Details Provided
Data source	Resource path in TDV.
Script	Code that defines the script.
Table	Column data types.
Transformation	Code that defines the transformation.
View	SQL that defines the view. A selected column is highlighted in yellow.

For example, when you double-click a view to display its columns, the columns and their relationships are displayed and the **Detail** panel shows the

SQL that defines the view. If you select a column, then the references to the column are highlighted in yellow as shown in this example:




## Using the History Feature

When you change the resource focus, Studio adds the previous focus to the history list so that you can easily return to a previous view. This history list is saved with the resource and can be used again if you reopen the resource's lineage graph.

### To display a previously viewed lineage graph

1. Open the lineage graph for a resource.
2. At the top right corner of the resource graph, click the drop-down arrow next to the path for the current resource.



3. Select the path for the resource you want to be the central focus.  
Studio displays the resource graph that was previously viewed.

**Note:** You can also use the **Navigate Backward** and **Navigate Forward** arrow buttons to step through the lineage graphs.

## Refreshing the Lineage Graph

The lineage graph displays what is currently saved to the TDV Server. If you make changes and save them, you can update the lineage graph. The print **Preview** dialog lets you control the size of the print, crop it, print the graph as a poster, add a title, and add a footer.

**Note:** If you have unsaved changes when you open a lineage graph, Studio displays a warning message to alert you. If you do not want to see these messages, you can turn this feature off using the Studio **Options** dialog; uncheck the **Warn before data lineage calculation when resource editor is saved** option on the **Warnings** tab.

### To refresh the lineage graph


1. Display the resource lineage graph.
2. If necessary, save any changed resources involved in the lineage graph.
3. Click the **Refresh** button.

## Printing the Lineage Graph

Studio lets you print the lineage graph and provides various ways to control the printed output like creating a large poster print, adjusting the orientation and margins, and adding a title and a footer.

### To print a lineage graph

1. Display the resource lineage graph.
2. Click the **Print** button.



**Note:** If your lineage graph is especially large, you can create a poster print of it using the **Options** button.

3. Use the buttons at the top control the printed output as follows:

Use...	To...
Page	Change the orientation between portrait and landscape and to adjust the margins.
Print	Print the model diagram using your standard print dialog.
Zoom In	Zoom in on the print image. This does not increase the size of the image on the page.
Zoom Out	Zoom out on the print image. This does not decrease the size of the image on the page.
Zoom amount	Select a setting from the drop-down list.

Use...	To...
Options	<p>Displays a Print Options dialog with three tabs:</p> <ul style="list-style-type: none"> <li>• General tab options let you create a large poster-style print of the model diagram by dividing the model into sections that can be pieced together. <ul style="list-style-type: none"> <li>Poster Rows—divides the image vertically into the number of rows entered and displays how it would appear on that number of pages if printed.</li> <li>Poster Columns—divides the image horizontally into the number of columns entered and displays how it would appear on that number of pages if printed.</li> <li>Add Poster Coordinates—prints the location of each subsection of the model diagram so that you can figure out how the sections go together.</li> <li>Clip Area—Two options are provided: Graph enlarges the model image as much as possible within the margins; View increases the blank space around the model image.</li> </ul> </li> <li>• Title tab options let you specify a title for the printed model. <ul style="list-style-type: none"> <li>Text—Specify the title you want to appear at the top of the model diagram.</li> <li>Titlebar Color—Click to select the color of the title bar which will appear behind the title text.</li> <li>Text Color—Click to select the color of the title text.</li> </ul> </li> <li>• Footer tab options let you specify a footer for the printed model. If you are printing the model poster style, the footer will span the pages appropriately. You can specify text, footer and text color.</li> </ul>

## Exporting Lineage Reports to a Comma-Separated-Values File

All of the information represented in the tree view and the graph view of the dependency report can be exported to a comma-separated-value (csv) file.

### To export dependency reports to a csv file

1. Display the resource lineage graph.
2. Make sure that the lineage graph has the resource focus that you want.

The lineage report in the csv file is based on the current resource which is shown with a blue title bar.

**Note:** It does not matter if the lineage graph is expanded or collapsed. Column information is included in the exported file, regardless. If you hide

dependencies or references in the lineage graph, they are not included in the exported file.

3. On the lineage button toolbar, click the **Save To File** button.
4. In the **Save** dialog, navigate to the location where you want to save the information.
5. Name the file that will contain the dependency information.
6. Click **Save**.
7. Open the file in Excel or other similar application.

The lineage report contains one row for every connecting line in the lineage graph. A connecting line represents a dependency or reference. The information for each dependency or reference is as follows:

SourcePath	SourceType	SourceColumnName	ReferenceByPath	ReferenceByType	ReferencedByColumnName
The path to source	The source type: TABLE, DATA_SOURCE, PROCEDURE, MODEL, and so on	For column dependencies, the name of the column.	The path to the reference.	The resource type: TABLE, DATA_SOURCE, PROCEDURE, MODEL, and so on	For column references, the name of the column.

## Sample lineage information:

A	B	C	D	E	F
1	Source Type	Source Column Name	Referenced By Path	Referenced By Type	Referenced By Column Name
amples/CompositeView	TABLE		/shared/My Sample Model	MODEL	
amples/ViewSupplier	TABLE		/shared/examples/CompositeView	TABLE	
amples/ds_inventory/suppliers	TABLE		/shared/examples/ViewSupplier	TABLE	
amples/ds_inventory	DATA_SOURCE		/shared/examples/ds_inventory/suppliers	TABLE	
amples/ds_inventory/inventorytransactions	TABLE		/shared/examples/ViewSupplier	TABLE	
amples/ds_inventory	DATA_SOURCE		/shared/examples/ds_inventory/inventorytransactions	TABLE	
amples/ds_inventory/purchaseorders	TABLE		/shared/examples/ViewSupplier	TABLE	
amples/ds_inventory	DATA_SOURCE		/shared/examples/ds_inventory/purchaseorders	TABLE	
amples/ViewSales	TABLE		/shared/examples/CompositeView	TABLE	
amples/productCatalog_Transformation	PROCEDURE		/shared/examples/ViewSales	TABLE	
amples/ds_XML/productCatalog.xml	TREE		/shared/examples/productCatalog_Transformation	PROCEDURE	
amples/ds_XML	DATA_SOURCE		/shared/examples/ds_XML/productCatalog.xml	TREE	
amples/ds_orders/orderdetails	TABLE		/shared/examples/ViewSales	TABLE	
amples/ds_orders	DATA_SOURCE		/shared/examples/ds_orders/orderdetails	TABLE	
amples/ds_orders/cache_status	TABLE		/shared/examples/ds_orders	DATA_SOURCE	
amples/ds_orders	DATA_SOURCE		/shared/examples/ds_orders/cache_status	TABLE	
amples/ds_orders/cache_tracking	TABLE		/shared/examples/ds_orders	DATA_SOURCE	
amples/ds_orders	DATA_SOURCE		/shared/examples/ds_orders/cache_tracking	TABLE	
amples/ViewOrder	TABLE		/shared/examples/CompositeView	TABLE	
amples/ds_orders/orders	TABLE		/shared/examples/ViewOrder	TABLE	
amples/ds_orders/orders_cache	TABLE		/shared/examples/ds_orders/orders	TABLE	
amples/ds_orders	DATA_SOURCE		/shared/examples/ds_orders/orders_cache	TABLE	
amples/ds_orders	DATA_SOURCE		/shared/examples/ds_orders/orders	TABLE	
amples/ds_orders/orderdetails	TABLE		/shared/examples/ViewOrder	TABLE	
amples/ds_orders/customers	TABLE		/shared/examples/ViewOrder	TABLE	
amples/ds_orders	DATA_SOURCE		/shared/examples/ds_orders/customers	TABLE	
amples/ViewSupplier	TABLE	SupplierName	/shared/examples/CompositeView	TABLE	SupplierName
amples/ds_inventory/suppliers	TABLE	ContactName	/shared/examples/ViewSupplier	TABLE	SupplierContactName
amples/ds_inventory/suppliers	TABLE	SupplierName	/shared/examples/ViewSupplier	TABLE	SupplierName
amples/ds_inventory/suppliers	TABLE	SupplierID	/shared/examples/ViewSupplier	TABLE	SupplierID
amples/ds_inventory/inventorytransactions	TABLE	TransactionID	/shared/examples/ViewSupplier	TABLE	TransactionID


## Lineage Information for Different Resource Types

You can obtain the lineage information for most resource types. The information is displayed graphically in the resource lineage graph. The relationships and connection between different resources can be especially useful. Also, you can change the resource focus to navigate between resources and understand their relationships.


This table illustrates examples of the lineage information that is displayed for many resource types (listed in alphabetical order).

**Resource Type**      **Description and Example**


**TDV Web service**      Displays all resources on which the Web service depends and all dependent published resources. For example:




**Data source (.csv)**      Displays all resources that depend on the selected .csv data source. For example:




**Data source (relational)**      Display all resources that depend on the selected relational data source. Example:









**Data source (XML)**      Displays all resources that depend on the selected XML data source. For example:



**Definition Set**      Displays all resources that depend on the selected definition set. For example:






Resource Type	Description and Example
Hierarchical resource	<p>Displays the data source on which the resource depends and all resources that depend on the selected hierarchical resource. For example:</p> 
Model	<p>Displays all resources on which the selected model depends. For example:</p> 
Policy	<p>Displays all resources that depend on the selected policy. For example:</p> 
Procedure (Script)	<p>Displays all resources on which the procedure depends and all resources that reference the script. For example:</p> 
Published resource	<p>Displays all dependencies for the selected resource. For example:</p> 
Table	<p>Display the parent data source and all resources dependent on a table and its individual columns. Example:</p> 

**Resource Type**      **Description and Example**


**Transformation (XQuery)**      Displays the resources on which the XQuery transformation depends. For example:




**Transformation (XSLT)**      Displays the dependencies and references for the XSLT transformation. For example:



**View**      Displays the dependencies, references, and cached tables/views for a view (by default). For example:



You can also toggle the indirect links button to view the references to columns in a view's WHERE, GROUP BY, HAVING, FROM, or other non-SELECT clauses as shown here:



# TDV Caching

---

Caching makes a copy of frequently accessed data and stores it for quicker, more convenient access. The following topics are covered:

- [Overview of TDV Caching, page 392](#)
- [Cache Requirements and Limitations, page 409](#)
- [Setting Up Caching, page 417](#)
  - [Caching Transaction Results of a Procedure, page 418](#)
  - [Caching to the Default Database Target, page 418](#)
  - [Caching to a File Target, page 420](#)
  - [Pre-Creating Caching Objects for Database Caching, page 421](#)
  - [Caching to a Single-Table Database Target, page 423](#)
  - [Creating a Multiple Table Cache on a Database Target, page 425](#)
  - [Enabling Cache Data Storage to Multiple Data Sources, page 429](#)
  - [Setting Up Native \(Bulk\) Caching Options, page 431](#)
  - [Setting Up the Parallel Cache Option, page 443](#)
  - [Enabling JDBC-Only Cache Loading, page 444](#)
  - [Canceling a Cache Refresh that Is Using Native or Parallel Loading, page 445](#)
- [Defining Cache Refresh Behavior, page 445](#)
- [Cache Maintenance, page 460](#)
  - [Indexing Your Cache, page 460](#)
  - [Managing Configuration Changes and Cache Behavior, page 462](#)
  - [Displaying the Dependencies of a Cached View, page 463](#)
  - [Displaying the Dependencies of a Cache Policy, page 464](#)
- [Caching Tips from an Expert, page 466](#)
  - [Destroying a File or Default Cache, page 466](#)
  - [Managing Cache Status Table Probe Row Conflicts, page 466](#)
  - [Managing Unresponsive Cache Tables, page 467](#)
  - [Managing Open Connection Threads, page 468](#)


## Overview of TDV Caching

TDV caching is a feature that can improve the responsiveness of data access in your enterprise. Caching features can help you quickly build data caches that complement data virtualization and improve reporting. Working within TDV and Studio, you can access data and metadata from across data repositories, whether they be applications, databases, or data warehouses. You can then use TDV to create data caches. From the data caches, you can consume the cached data for client activities such as data analysis.

TDV caching is a feature of TDV and uses the Studio user interface. TDV caching is delivered with TDV, and contains all of the software needed to implement TDV caching in your IT environment.

- [TDV Caching Concepts, page 393](#)
- [How Does TDV Caching Work?, page 400](#)
- [TDV-Created Caching Objects, page 405](#)
- [What Incremental Caching Options Are Available in TDV?, page 407](#)
- [About Native and Parallel \(Bulk\) Caching, page 408](#)
- [Cache Status and Events Reporting, page 409](#)

The following illustration provides a simplified representation of caching with TDV.



## Key Features and Benefits of Caching Data

Many business applications are being developed and deployed on multi-tier environments involving browser-based clients, web application servers, and databases. These applications require data on demand. Caching is an effective way to achieve high scalability and performance. Caching provides:

- Reduced impact on operational data stores.
- Redirection of reporting and analytic queries to cache data stores, eliminating their impact on the performance of OLTP systems.
- Improved performance of TDV requests.
- Materialization of intermediate results (expensive to compute) boosting the performance of requests that depend on them.
- More flexibility.
- The opportunity to move cached data result sets to systems that provide optimal processing and analysis.

## TDV Caching Concepts

This section introduces many of the concepts associated with TDV caching. Becoming familiar with these concepts can help you determine if you want to use caching and which TDV caching options might work best for you.

- [What Is a Cache?, page 394](#)
- [Why Use Caching?, page 394](#)
- [When Should You Configure Caching?, page 394](#)
- [What Types of Caching Are Available?, page 394](#)
- [What is a Full Refresh Versus an Incremental Refresh?, page 395](#)
- [What Are the Incremental Caching Options?, page 395](#)
- [What TDV Resources Can I Cache?, page 396](#)
- [What Cache Storage Options Are Available?, page 396](#)
- [What Is a Cache Target?, page 396](#)
- [What Refresh Options Are Available for a Cache?, page 397](#)
- [What is a Cache Policy?, page 397](#)
- [When Does Cache Data Expire and Get Removed From the Cache?, page 398](#)
- [What is Cache Versioning, Transaction Integrity, and When Are Old Cache Contents Cleared Out?, page 399](#)

- [Can Caches Be Exported and Imported?, page 399](#)
- [How Does Error Handling Work for Resources that use Cache Policies?, page 399](#)
- [How Does Error Handling Work for Resources with Individually Defined Cache Refresh and Expiration Schedules?, page 399](#)

## What Is a Cache?

A *cache* is a location that holds a copy of frequently accessed data that is otherwise expensive to retrieve or compute.

## Why Use Caching?

Data caching is an important data design option that provides a valuable way to replicate data or store data closer to where it is consumed, to enhance application performance. Caching can also reduce the impact of resource-intensive queries being run against database tables by distributing the workload over several storage locations. Instead of running the same query multiple times to return the same result set, you can use a cache to store the results, and then reuse them.

## When Should You Configure Caching?

If direct queries to the database are resulting in performance that is causing noticeable delays in data retrieval, it might be time to consider data caching.

## What Types of Caching Are Available?

TDV has designed several caching options so you can create caches that meet your needs. Among these options are:

- Full refresh caching—All data in the cache is retrieved when a cache refresh action is initiated.
- Incremental refresh caching—Only data that has changed is retrieved and updated in the cache when a cache refresh action is initiated.
  - Pull-based incremental caching—The incremental cache refresh action is initiated by a request from the consuming client application. This method could be considered on-demand.
  - Push-based incremental caching—The incremental cache refresh action is automatically initiated as defined during configuration of the option. The data in the cache is refreshed regardless.

Additional enhancements, available through your database vendor, worth considering for caching include:

- Native loading features such as FastLoad
- Parallel caching feature that partitions the cache data and then runs parallel processes to load the data into the cache target

### What is a Full Refresh Versus an Incremental Refresh?

You can also have your cache data refresh happen incrementally or in full. A full refresh would retrieve the data in the cache in its entirety, include data that changed since the last cache refresh and any data that is unchanged. With an incremental cache update, only data that is changed (newly added, modified, and deleted) is updated in the cache when the refresh action runs.

On the Caching tab under the Advanced options, you can select one or the other for your cache. If you require a push-based incremental refresh, there are several special required configuration steps that are explained in [Push-Based Incremental Caching, page 575](#).

### What Are the Incremental Caching Options?

TDV provides for two methods of incremental caching. The updates to the cache can be propagated using one of the following two modes:

- Pull-Based Incremental Caching

Pull-based incremental caching can be set up using the TDV caching mechanism with two scripts. With pull-based incremental caching the user or client application must make a request for their copy of the cache to be synchronized with the centralized cache copy. This asynchronous method or cache data update can improve cache loading times because after the initial data is loaded into the cache each subsequent load is only updating the cache with the smaller data changes. For more information on pull-based incremental caching, see [Setting Up Pull-Based Incremental Cache, page 455](#).

- Push-Based Incremental Caching

Push-based incremental caching can be set up using the native TDV caching mechanism, plus the TDV Change Management Service (CMS), to configure a Central Event Server. This synchronous method of cache data update enforces cache consistency across all copies of the cache data. To protect the data in the incremental cache, you can configure the TDV server to back up the primary Central Event Server. To keep transactional semantics from differing between the sources and the caches, changes in the source are captured and applied to all affected views. For more information on push-based incremental caching, see [Setting Up Push-Based Incremental Caching for Oracle, page 460](#).

## What TDV Resources Can I Cache?

Caching lets you store data generated from a view, table, or procedure from across data sources. Table objects include tables, views from data sources, and TDV views. Procedure objects include SQL scripts, parameterized queries, and XML transforms.

## What Cache Storage Options Are Available?

A storage option determines the location and some of the behavior associated with a cache. A cache can be stored as a:

- **Default**—Cache data is stored in a TDV determined database location.
- **Automatic**—Cache data is stored in a TDV determined structured file location.
- **Single Table**—Cache data is stored in a user determined structured database location.
- **Multi-Table**—Cache data is stored in a user determined database location in a user determined number of caching tables.

For single table caching, several snapshots (a picture of your data taken at a point in time) of data is stored in the same physical table. Because several snapshots are stored in the same table, index on the cached data is less effective. With the multi-table cache option, TDV uses several physical tables for each cached resource so that each snapshot is stored in its own table. This feature can increase the speed of deleting old cache data and indexing the newly cached data. Multi-table caching is primarily meant for caches that contain a substantial amount of data which is retained for a long time. For details about setting up this type of caching, see [Creating a Multiple Table Cache on a Database Target, page 425](#).

## What Is a Cache Target?

A cache target is a file, database table, or multiple database tables used to store data for a specified period of time.

For a data source to be a cache target, it must conform to the prerequisites specified in [Cache Requirements and Limitations, page 409](#). While it is possible to have the same cache resource act as both source and target, it is more common to have them be different. Data from multiple resources cannot share cache target tables.



Consider what cache target is most suitable for the type of data to cache and how you want to interact with it. For example, a cache target might not support important data types in the source. Review the [Cache Requirements and Limitations, page 409](#). Also check the Cache Data Type Mapping section of the *TDV Reference Guide*.

## What Refresh Options Are Available for a Cache?

TDV cache data refresh is highly configurable. You can use the standard scheduling tools available through the TDV Studio UI, or you can define custom refresh behavior. The following standard refresh options are available:

- According to a policy—Reusable cache policies can be used to define cache refresh schedules. The policies can be used to define the refresh options for tables, views, and procedures.
- Immediately—Refreshes the cache immediately when a TDV user opens the Caching tab and clicks Refresh Now.
- One Time Only—Allows you to schedule a specific date and time for the cache to be refreshed once.
- Periodic—Allows you to define a regular recurring cache refresh action.
- Custom—You can also define SQL scripts, Java programs, or web services that control and define cache refresh behavior. For example, you could write a custom Java program that would initiate a cache refresh if an email was sent to a particular email address with a well formatted subject line. For more information on defining custom refresh behavior, see [Refreshing and Clearing Your Cache Programmatically, page 448](#).

Modifying the query of the view (or table) that you have caching defined on does not automatically update the cache. You must execute a refresh or wait for the next scheduled refresh cycle to get the correct result set.

## What is a Cache Policy?

Cache policies define cache refresh and expiration schedules. After a cache policy is defined, it can be used to control the refresh and expiration schedules of Studio resources that you want to cache.

Because the same refresh and expiration schedules can be set for resources in your cache, data consistency and accuracy can be improved for the applications accessing the cached data. For example, if you have an application that relies on cached data for the ORDERS table and the ORDERDETAILS table, you can use a cache policy to make sure that their caches are refreshed at the same time.

Cache policies also enhance cache performance. With cache policies TDV can calculate the optimal cache load strategy for performance because the list of resources that are part of the cache refresh action for a given policy are well known.

With cache policies, cached data consistency is all or nothing. If one of the resources included in the cache policy fails during refresh action, all of the caches are rolled back to the previous successful snapshot of data. For this reason, cache policies and incremental caching are not supported for use together.

### When Does Cache Data Expire and Get Removed From the Cache?

A cache refresh is used to create or update the cache contents. Depending on how you have configured your cache determines how the data from a previous refresh expires and potentially gets removed from the cache.

Expired cache versions are not deleted until all transaction holds using that version are completed or rolled back.

Typical expiration schedules are:

- Never—Keep the current and all previous data snapshots in the cache.
- Periodic—Allows you to define a regular recurring cache expiration time. For example, after a specified number of weeks or years.
- According to Custom Criteria—You can control cache data refresh and clearing by defining custom SQL scripts, Java programs, or web services.

You can also control whether the cache data clears:

- Immediately—Clear the cache using the **Clear Now** button. This marks the old cached version of the data as expired so that new requests cannot use it; then the system initiates a background task to clear the expired cache version when it is released.
- On Failure—Selecting this option would clear the cache if a refresh fails. This option allows access to previously cached data during a refresh.
- Before the Refresh—Selecting this option would automatically clear the cache before starting a refresh. Any clients attempting to read from the cached data must wait for the new data. Forces all new requests to use the new cache version, marks the older cached version as expired but not actually cleared, and new requests for the cached resource must use the latest data provided by the cache refresh.
- Periodically At Expiration Time—On cache expiration, if a time is defined in the Expiration Schedule portion of the screen, the old cache data is cleared out.

- According to Custom Criteria—You can control cache data refresh and clearing by defining custom SQL scripts, Java programs, or web services.

## **What is Cache Versioning, Transaction Integrity, and When Are Old Cache Contents Cleared Out?**

TDV cache versioning preserves transaction integrity by maintaining old cache versions until existing transactions are completed. Expired cache versions are not deleted until all transaction holds using that version are completed or rolled back. Even when you manually initiate cache clearing, that action only marks the old cached version as expired so that new requests cannot use it; then the system initiates a background task to clear the expired cache version when it is released.

TDV can be configured to gracefully handle long-running cache refreshes by retaining all previous cache data snapshots, which preserves usability of the data while a cache is actively being refreshed in the background.

To preserve read consistency, long-running queries that use data from a cached view are allowed to complete computations with the original cached view that it was using at the time the cache refresh started.

## **Can Caches Be Exported and Imported?**

All of the cache information that you define within TDV can be exported and reimported into TDV. Using the TDV export functionality can be an effective way to manage your TDV development work. If done routinely, it can provide a valuable rollback snapshot of your work.

## **How Does Error Handling Work for Resources that use Cache Policies?**

If a cache refresh is initiated by a cache policy and it fails at any point before completion, all the caches are rolled back to the last successful snapshot.

## **How Does Error Handling Work for Resources with Individually Defined Cache Refresh and Expiration Schedules?**

If the data sources providing the data to be cached or the data source used to store the cached data fail during the refresh, the cache is marked as failed or stale depending on whether the previous snapshot is available.

If the TDV server fails during the refresh the cache is marked as failed or stale when the server is restarted.

For caches that perform a full refresh, if the server dies in the middle of a refresh, the refresh attempt is marked as Failed on server restart. Any partial data is eventually processed by the garbage collector.

For caches that perform incremental refreshes, if the server dies in the middle of a refresh, the cache status is marked as DOWN when the server is restarted.

## How Does TDV Caching Work?

TDV caching options and how caching works for the different TDV resources are worth understanding before choosing one over the other. This section covers the following topics:

- [How Does Table and View Caching Work?, page 400](#)
- [What Is Procedure Caching?, page 401](#)
- [What Is Transaction Result Caching for Procedures?, page 403](#)
- [How Does Caching Data in a Cluster Environment Work?, page 404](#)

## How Does Table and View Caching Work?

Within TDV, it is possible to configure caching for views and tables. A `SELECT *` is run against the view or tables and every row returned is placed into the cache. Because of this:

- The cache will be as large as the output set of the table or view.
- All requests to that view or object come from the cache after its first load.

You can create a view based on the data or object that you want to cache. You could then later limit the data that is included in the cached view for performance reasons.

TDV caching is best used for materialized views under any of these conditions:


- A view requires substantial execution time.
- The data does not change significantly within a given period.
- The data source should be protected from excessive usage.

For view caches, if a query references a cached view, and the cache is not loaded, it starts a refresh and the query is blocked until the cache is loaded.

In the following example, `Sales_Table` is an Oracle table, and the `UK_Sales_View` is a TDV view of that table. If you cache at the table level, all 10 million rows and 15 columns are selected from `Sales_Table` and put into the cache. However, if you cache the *view*, the view projects only three columns and has a `WHERE` clause that limits the result set to 100,000 rows.

The WHERE clause and the SQL in the UK\_Sales\_View are pushed to the Oracle database for processing. Only 100,000 rows and three columns are extracted from Oracle, sent over the network, and placed in the cache. This is 500 times less data for the same result. The cache is smaller, the refresh is quicker, and there are fewer loads on both the Oracle database and the network during the refresh.

In the following example, Composite\_view joins a file, an Oracle table, and an SAP table. Report\_proc uses Composite\_view and pushes a predicate against it. Because File\_1 does not support pushes, the predicate requires a full scan of File\_1 and SAP\_Table\_1 each time, slowing performance with the joins and the fetches. If Composite\_view is cached, the join is performed only once.



## What Is Procedure Caching?


Tabular results from procedure-based resources can be cached by TDV. Procedures with one or more input parameters can have many variants (unique sets of input parameters) and return different result sets based on those input variants. More than one result set from the same procedure can also be cached.

To track variants, the input parameter values are converted to a string to compare for uniqueness. If this string exceeds 255 characters, the procedure call is not cached. Instead, it is executed as if caching was disabled.

For example, Proc\_1 has one input parameter (A, an integer) and returns a result set. Proc\_1 can be called for different values of A. The caching mechanism executes the procedure and stores the result set for each unique set of input parameters (in this case, integer A). If two variants are in the cache, one with A= 1 and another with A = 2, and Proc\_1 is called with A equal to 1 or 2, there is a hit on the variant and the corresponding cached result set is returned.

If Proc\_1 is called with a variant that is not currently cached, like A = 3, a “cache miss” occurs, and the procedure is executed with A = 3. The result set is directly returned to the caller, and both the variant and the result set are written to the cache. If proc\_1 (3) is called again prior to expiration of the result set, where A = 3, the cached result set is returned immediately.

Because there can be many variants, it might not be possible to store them all. By default, the maximum number of stored variants is 32, but you can change the value in the Maximum number of procedure variants field in the Advanced section of the Caching panel. If the cache is full, the least recently used variant is swapped out for the latest variant.



The following procedural resources can be cached:

- Java procedures
- Packaged query procedures
- Parameterized SQL procedures
- Physical stored procedures that are introspected
- SQL script procedures
- Transformation procedures—basic, streaming, XSLT, and XQuery
- Web service operations

The procedure caching process uses one storage table for each output cursor and an additional storage table for any scalar outputs. For example, a procedure with two INTEGER outputs and two CURSOR outputs would use three tables:

- One for the pair of scalars
- One for the first cursor
- One for the second cursor

If a procedure has input parameters, the cached results are tracked separately for each unique set of input values. Each unique set of input parameter values is called a variant.

For example, a procedure with an INTEGER input parameter would have separate results cached for inputs of 1, 3, and 5, or whatever value. A procedure with two INTEGER input parameters would have separate results cached for inputs (1,1), (1,2), and (x,y).

**Note:** A procedure cache that uses non-null input parameters must be seeded with at least one variant from a client application other than Studio, for the Cache Status to change from NOT LOADED to UP. Using the Refresh Now button does not change the status of a cache that is not loaded. Even if procedure caching configuration is correct, the status does not show that it is loaded until a client seeds the cache.

When a procedure cache is refreshed, all the cached variants already in the table are refreshed. If no variants have yet to be cached, then nothing is refreshed or only the null input variant is refreshed. You can refresh a procedure cache from Studio or using the RefreshResourceCache procedure. (See the *TDV Application Programming Interfaces Guide*.)

## What Is Transaction Result Caching for Procedures?

Transactional result caching is available for procedures. For each unique set of input parameter values, the caching data is collected one time. When transaction result caching is enabled, results are captured in memory the first time the procedure is run during any transaction; additional calls to the procedure with the same input parameters return the cached data. Transaction result caching has no refresh, clear, status, or tracking available.

Transaction result caching is useful in the following scenarios:

- The TDV procedure is run against every row in a query.
- The SQL Script logic inherently requires enough processing time to make the entire query's cumulative execution time unacceptable.
- The results from the TDV procedure performs lookups against a table whose data changes frequently.

Results of calls to the SQL script are stored in memory, and later calls with the same parameters return data from the cache if the data exists there, or execute the SQL script and store that variant in memory.

In Transaction Result Caching:

- Data cached for the transaction persists only for the duration of the transaction.

- Transactional cached information is stored in memory.

For example, consider the following two TDV resources. Each call to lookup requires a SQL lookup to a table. If the composite view returns 1,000,000 rows without Transaction Result Caching, there are 1,000,000 database queries performed by lookup. If transaction processing is enabled and field1 does not contain unique data, each result and input combination is stored temporarily in memory. When a duplicate field1 value is returned, TDV returns the previous result value in memory for that input. All the values are discarded when the transaction ends.

Composite View	Lookup SQL Script
SELECT lookup(field1) result, field2, field3 FROM largeTable	PROCEDURE lookup(IN iVal INTEGER, OUT resVal INTEGER) BEGIN DECLARE c CURSOR; OPEN c AS SELECT fl FROM largeSlowLookupTable WHERE lookupVal = iVal; FETCH c INTO resVal; CLOSE c; END;

To enable transaction result caching, check the “Execute only once per transaction for each unique set of input values” check box in the Transaction Options section of the Info tab for any procedure.

## How Does Caching Data in a Cluster Environment Work?

Running TDV server in a cluster environment, whether the TDV Active Cluster or any other clustered environment, you can cache data.

When the TDV server is running in a cluster and the cache is in Default Cache or Automatic mode, each server keeps a separate copy of cached data on its local file or database system, and no sharing of data is performed.

When the server is running in a cluster and the cache is in single table or multi-table mode with an identified data target, all servers in the cluster access the same data target for cache information. In addition, the servers cooperate to ensure that a minimum number of refreshes occur. For example, if two servers both need to refresh the data in a cache, only one of them performs the refresh, and then both servers use the updated data.

**Note:** The use of the File-Cache data source or other file-based data sources is not recommended when in a cluster. The use of network-mounted files is also not recommended because the file data sources do not support file locking.



In a cluster environment, any attempt to refresh a cache uses the TDV cache status table to determine if any other refreshes are in progress. If no others are in progress, the refresh starts and all other servers are notified to reread the TDV cache status table (for information on what the cache status table is, see [TDV-Created Caching Objects, page 405](#)). If a refresh is already in progress, the server contacts the server that is currently refreshing and waits for that refresh to complete.

In a cluster environment, an attempt to clear a cache marks the cache data for clearing in the TDV cache status table. The background task to actually delete the data contacts other cluster members to determine what cache keys are no longer in use so the task can safely remove only rows that no server in the cluster is accessing. After the clear task completes, all other servers are notified to reread the TDV cache status table.

A scheduled refresh in a cluster relies on the trigger system cluster feature to ensure that triggers are processed only the appropriate number of times. File cache schedules are configured to fire separately on each server. Database cache schedules are configured to fire only once per cluster. You can create trigger resources, instead of using the schedule options provided on the Caching panel, to control this behavior. (See [Triggers, page 309](#).)

## TDV-Created Caching Objects

This section provides an overview of some of the key objects created to facilitate TDV caching. Depending on how you set up your cache, the following objects are created either by TDV or by you. If you decide to use the automatic storage type selection, the names of the objects are set by TDV. If you choose any of the other options you can name the tables anything you want. TDV suggests using names that are easy for you to identify as cache data, cache tracking, and cache status.

### Cache Status

The status table (or file) is used to track which views and procedures currently have cached data stored, when they were last refreshed, and so on.

Each Studio data source used as a caching target must have its own status table.

### Cache Tracking

The tracking table (or file) is used to track the tables, views, and procedures that are using a particular cache target. It is also used to track what tables in the cache target are in use.

Each Studio data source used as a caching target must have its own tracking table.

## Cache Data

The name of the object you want to store cached data for is appended with cache. These are the file or database tables that will hold the cached data. Resources cannot share the same data cache.

## The cachekey Column


The cachekey column is a way to uniquely identify a particular snapshot of cached data. TDV uses it to determine what data in the cache to return for a query request from an application, to determine cache versioning, transaction integrity, and when old cache records are ready to be cleared out. If you decide to use some of the more advanced caching options, you can use the cache key in your custom scripts to drive caching actions such as syncing cache data to a cache copy on request.

The cache data table, for most caching options, has a cachekey column that contains a unique integer identifier. The cache status table identifies the cachekey value that is associated with current data or with specific parameter input variants for procedures.

The cache key is a unique number generated for each cached result set. For most caching configurations, it is the only caching table column automatically generated by the TDV Server.

Because the cache key is a unique integer for each snapshot of data, it can be useful for indexing, when defining pre- and post-refresh action scripts, or when defining scripts for incremental caching. Because the cache key is used often to filter data, it should be the first column of the index when indexing the cache table.

For multi-table caching, the cachekey column is not in the target table, but it is in the cache status table to support leader election, garbage collection, cluster communication, and for consistent cache status.



The cache metadata tables contain some abbreviated values. For example:

Metadata Values	Meaning	Description
A	active	Cache is loaded.
I	in progress	Cache is currently refreshing.
F	failed	The loading of the cache failed for some reason.
C	cleared	Cache has been cleared.
K	key	A special value used to indicate the key row in the table.

## What Incremental Caching Options Are Available in TDV?

After initial cache loading, incremental caching improves caching performance by only *updating* the cache, rather than *reloading* it, to reflect changes in the data source. Resources are incrementally maintained as highly available and responsive caches that are kept in sync with real-time data in the data source. TDV's incrementally maintained caches provide the authenticated and authorized end-user client with synchronized data services ready with data results on demand. The following two options are available:

- [Pull-Based Incremental Caching, page 407](#)
- [Push-Based Incremental Caching, page 407](#)

### Pull-Based Incremental Caching

Pull-based incremental caching can be set up using the TDV caching mechanism with two scripts. With pull-based incremental caching the user or client application must make a request for their copy of the cache to be synchronized with the centralized cache copy. For more information on pull-based incremental caching, see [Setting Up Pull-Based Incremental Cache, page 455](#).

### Push-Based Incremental Caching

Push-based incremental caching can be set up using the native TDV caching mechanism, plus the TDV Cache Management Service (CMS), to configure a Central Event Server. If you have subscribed to notices from objects that store data in an incremental cache, subscribed clients are notified whenever the result sets are updated. For more information on push-based incremental caching, see [Setting Up Push-Based Incremental Caching for Oracle, page 460](#).

## About Native and Parallel (Bulk) Caching

Native cache loading is designed to enhance caching performance loading the cache. The Enable Cache Loading and Enable Parallel Loading Studio configuration parameter controls whether native caching is enabled or disabled. By default, the native cache loading is enabled.

When a single-source, pass-through view is cached, native cache loading might be supported.

There are several ways to tune the performance associated with data caching. If you have set up caching performance configurations for native and parallel caching options, TDV determines which option is ideal.

If native and parallel caching options cannot be used to move the data, TDV attempts to use JDBC to do the cache loading.

The following cache loading options are supported by TDV:

- INSERT/SELECT statements
- Bulk load with the LOAD utility
- Bulk load with bcp, utility (bcp.exe)
- Bulk load with external tables
- Bulk load through database links
- Bulk load using the Bulk Load utility
- Parallel cache load

When the native caching option can be performed within the same data source, that is the source of the cache data and the target for the cache data reside in the same database or schema, and the data source supports INSERT/SELECT statement, the cache loading will use INSERT/SELECT statement. With the INSERT/SELECT statement method of native caching, almost all data types are supported.

If the INSERT/SELECT statement cannot be used for native caching, TDV tries to use the mechanism that the target data source supports. These options vary by database type.

Target Database Type	Bulk Load Facility	Notes
DB2	LOAD utility	
Microsoft SQL Server	bcp.exe utility	The bcp.exe path must be specified in TDV.

Target Database Type	Bulk Load Facility	Notes
Netezza	external tables	Additionally, if DISTRIBUTE can be used to get more performance gains through parallel processing, it is used.
Oracle	Database Links	Requires a database link configuration in Oracle database and a link name in the definition of the TDV cache target data source.
PostgreSQL including Greenplum	COPY command	
Sybase IQ	LOAD_TABLE statement	Requires configuration of iAnywhere and DSN.
Teradata	FastExport and FastImport	
Vertica	Bulk Load utility	

## Cache Status and Events Reporting

Cache status is reported in Studio on the Caching panel for the resource, and on the Cached Resources console in the Manager.

The server event log is set to log all cache events by default. These events can be seen on the Events console in the Manager. They can also be found in the events log files and in the SYS\_EVENTS system table. The logging levels for these events can be set in the Manager Configuration panel (under TDV Server > Events and Logging), as with all other supported events.

## Cache Requirements and Limitations

Data caching has many important requirements and limitations to consider. This section describes:

- [Supported Data Sources for Caching, page 410](#)
- [Supported Cache Target Storage Types, page 410](#)
- [Privileges and Caching, page 415](#)
- [Caching Limitations, page 416](#)

- [Native \(Bulk\) Caching DDL Creation Limitations, page 417](#)

## Supported Data Sources for Caching

TDV caching supports most of the data sources (including adapters) supported by the TDV Server. For the current list of supported data sources in TDV, see the *TDV Installation Guide* or *TDV Installation and Upgrade Guide* for your version of TDV.

## Supported Cache Target Storage Types

Your cached data can be stored in database tables or as a file. Database caching lets you store result sets in a database so that further manipulations of the result set can be performed in dramatically less time. If any of the cached results are to be used by other views, or be filtered or sorted, then the cache should be stored in a database.

Data from one resource can be cached into one or more cache targets, but multiple resources cannot use the same cache target.

Cached resources are best stored in tabular form. The schema of the resource data must match the schema of the selected data source table. The cache database can have more columns than the source, but the data types of the columns must match. DDL can be generated to create a caching table that matches your view or procedure output.

File storage options are ideal when the results are not sorted or filtered for use in other views. File caches do not store index information, nor do they allow you to push SQL logical operators and filters to the data source. Because there is no index information, any selection of a subset of a view requires loading the cached view into memory for a row-by-row scan. SQL operations are executed on the cached data within TDV memory.

**Note:** If you build additional queries on large file cache views, significant memory will be required for a full table scan.

TDV supports the following as cache targets:

Cache Target	TDV Support	Parallel Cache Target Support	Native Cache Target Support	Notes
Amazon Redshift	Active	Active	Active	
Apache Hive 2.x	Active		Active	

Cache Target	TDV Support	Parallel Cache Target Support	Native Cache Target Support	Notes
File	Active	Active		Typically best for demonstrations or caching of a few hundred rows.
Google BigQuery	Active	Active	Active	
Greenplum 4.1	Active	Active	Active	
Greenplum 4.3	Active	Active	Active	
HSQLDB 2.2.9	Active	Active		
IBM DB2 LUW v10.5	Active	Active	Active	Native load with insert and select, and DB2 Load are supported.
Microsoft SQL Server 2008	Active	Active	Active	The DBO schema must be selected and introspected as a resource prior to attempting to cache data.
Microsoft SQL Server 2012	Active	Active	Active	The DBO schema must be selected and introspected as a resource prior to attempting to cache data.
Microsoft SQL Server 2014	Active	Active	Active	The DBO schema must be selected and introspected as a resource prior to attempting to cache data.
Microsoft SQL Server 2016	Active	Active	Active	The DBO schema must be selected and introspected as a resource prior to attempting to cache data.
Microsoft SQL Server 2019	Active	Active	Active	The DBO schema must be selected and introspected as a resource prior to attempting to cache data.

Cache Target	TDV Support	Parallel Cache Target Support	Native Cache Target Support	Notes
MySQL 5.1	Active	Active	Active	
MySQL 5.5	Active	Active	Active	
Netezza 6.0	Active	Active	Active	Native load with insert and select is supported. Parallel cache processing is achieved using the native DISTRIBUTE syntax.  Procedure caching is supported.
Netezza 7.0	Active	Active	Active	Native load with insert and select is supported. Parallel cache processing is achieved using the native DISTRIBUTE syntax.  Procedure caching is supported.
Oracle 10g	Supported			Native load with INSERT and SELECT is supported. Native load with DB link is not supported.
Oracle 11g and 11g R2	Active	Active	Active	
Oracle 12c	Active	Active	Active	
Oracle 19c	Active	Active	Active	
PostgreSQL 9.1	Active	Active	Active	Bulk load is supported.  Native loading is supported when the source and target are the same database. If not then Parallel loading is used.



Cache Target	TDV Support	Parallel Cache Target Support	Native Cache Target Support	Notes
PostgreSQL 9.2.3	Active	Active	Active	Bulk load is supported. Native loading is supported when the source and target are the same database. If not then Parallel loading is used.
SAP HANA SPS 09	Active	Active		
Snowflake	Active	Active	Active	
Sybase ASE 12.5	Active			
Sybase ASE 15.5	Active			
Sybase IQ 15.2	Active		Active	
Teradata 13	Active		Active	Supported, but with limitations. If source and target tables are co-located within the same Teradata instance native loading (using INSERT/SELECT statements) will be used, else bulk loading using Teradata FASTLOAD will be attempted.
Teradata 13.10	Active		Active	Supported, but with limitations. If source and target tables are co-located within the same Teradata instance native loading (using INSERT/SELECT statements) will be used, else bulk loading using Teradata FASTLOAD will be attempted.

Cache Target	TDV Support	Parallel Cache Target Support	Native Cache Target Support	Notes
Teradata 14.10	Active		Active	Supported, but with limitations. Might require Teradata 15 driver.  If source and target tables are co-located within the same Teradata instance native loading (using INSERT/SELECT statements) will be used, else bulk loading using Teradata FASTLOAD will be attempted.
Teradata 15	Active		Active	Choose tables For Caching is not supported.  If source and target tables are co-located within the same Teradata instance native loading (using INSERT/SELECT statements) will be used, else bulk loading using Teradata FASTLOAD will be attempted.
Teradata 16.20	Active		Active	Choose tables For Caching is not supported.  If source and target tables are co-located within the same Teradata instance native loading (using INSERT/SELECT statements) will be used, else bulk loading using Teradata FASTLOAD will be attempted.
ComputeDB	Active	Active	Active	

Cache Target	TDV Support	Parallel Cache Target Support	Native Cache Target Support	Notes
Vertica 6.1	Active	Active	Active	Supports the use of native load and parallel cache load together. Native load with INSERT AND SELECT is supported.

Not all caching tables can support data types from all other supported data tables, and so materialized views with certain data types are not compatible for caching at that database. When a data type mismatch occurs, a warning is issued to the developer to prevent further problems.

Not all data sources that could be used for cache storage can support the generation or execution of DDL statements. In some cases, DDL can be generated and presented, but use of an external tool might be required to create the table metadata. In other cases, the DDL is not shown, because it is not applicable.

## Privileges and Caching

Caching is defined in TDV on specific resources, you must have access to a resource to create a cache for it. The user who owns the resource being cached is the user identity that cache refresh and clear operations are run with.

TDV caching typically requires the creation of objects on the data source that is acting as the cache target. To create and delete the data and objects necessary for caching with TDV you must have the necessary permissions set up for you in the cache target. Performing a cache refresh or clear requires the READ, SELECT, INSERT, UPDATE, and DELETE privileges on the status table, tracking table, and the data tables. For example, if you use an Oracle database as your caching target, the TDV user that is defining the cache must have privileges on the Oracle database to READ, SELECT, INSERT, UPDATE, and DELETE data and objects directly in the database. Those privileges can be granted by explicit assignment, or by membership in a group with those privileges (implicit assignment).

For someone to use the view or procedure that is being cached to the cache target, they must also have privileges granted to access the cache status and data tables. For someone to read from the cache, they must be granted the SELECT privilege on these tables and READ privileges on folders above these tables.

Privileges are managed automatically when using the Automatic mode of caching.

## Caching Limitations

TDV can cache data from many different sources to many different cache targets. Occasionally, there are subtle limitations when dealing with so many systems. For data caching, those limitations are discussed here.

- The view being cached must NOT have a column called cachekey.
- If the cache target does not support a data type available in the source, then any attempt to store the unsupported data type in the cache results in an error. However, it may be possible to cast the unsupported data type to a supported one (for example, cast a BOOLEAN to an INTEGER type) before sending it to the cache target.
- When caching to a table, ARRAY data types are not supported.
- The following resources cannot be cached without being wrapped in a view or procedure:
  - Procedures with no outputs; that is, no data to cache.
  - Procedures with input parameters that require the use of cache policies.
  - XML files that have been introspected.
  - System tables.
  - Non-data sources such as folders, and definition sets.

### Incremental Caching Limitation

Cache policies cannot be used with incremental caching.

### Multi-Table Caching Limitation

Multi-table caching is available for tables and views, not for procedures.

### TDV Native Loading Option Database Link Limitations

For database links, the following data type and function support restrictions exist.

Data Source	Cache Target	Data Types Not Supported	Notes
DB2	Oracle 11g	REAL, GRAPHIC, LONGVARCHAR, TIME, TIMESTAMP, BLOB, CLOB	CAST, AVG, and SUM functions lose precision

Data Source	Cache Target	Data Types Not Supported	Notes
Sybase ASE 15	Oracle 11g	TEXT, IMAGE	AVG, COUNT, MAX, MIN, and SUM functions are not supported.
Oracle 11g	Oracle 11g	BLOB, CLOB AND NCLOB LONGRAW AND LONG	
SQL Server 2008	Oracle 11g	NTEXT, TEXT, DATE, IMAGE  Oracle treats empty strings as NULL values.	

## Native (Bulk) Caching DDL Creation Limitations

When the data source tries to create a table that contains certain data types, some data types are not supported for particular data source and cache target combinations.

Data Source	Cache Target	Data Type Not Supported
DB2	Netezza 5 or Netezza 6	BLOB, CLOB
Sybase ASE 15	Netezza 5 or Netezza 6	TIMESTAMP, BINARY, IMAGE, TEXT, VARBINARY
SQL Server 2008	Netezza 5 or Netezza 6	VARBINARY, TIMESTAMP, BINARY, TEXT, IMAGE, NTEXT
Oracle	Netezza 5 or Netezza 6	BLOB, CLOB, NCLOB, LONG, LONGRAW
Any data source	Vertica	Any data type (BINARY, CHAR, VARCHAR, BLOB, and so on) with length greater than 65000

## Setting Up Caching

This topic describes how to use data caching in TDV to improve performance:

- [Caching Transaction Results of a Procedure, page 418](#)
- [Caching to the Default Database Target, page 418](#)

- [Caching to a File Target, page 420](#)
- [Pre-Creating Caching Objects for Database Caching, page 421](#)
- [Caching to a Single-Table Database Target, page 423](#)
- [Creating a Multiple Table Cache on a Database Target, page 425](#)
- [Enabling Cache Data Storage to Multiple Data Sources, page 429](#)
- [Setting Up Native \(Bulk\) Caching Options, page 431](#)
- [Setting Up the Parallel Cache Option, page 443](#)
- [Enabling JDBC-Only Cache Loading, page 444](#)
- [Canceling a Cache Refresh that Is Using Native or Parallel Loading, page 445](#)

## Caching Transaction Results of a Procedure

The transaction result caching feature can be useful as an alternative to full procedure result caching if the primary need is for transaction isolation instead of storing results for repeated access between transactions. When transaction result caching is enabled, results are captured in memory the first time the procedure is run during any transaction; additional calls to the procedure with the same input parameters return the cached data.

For transactional caching, TDV caching does not directly use memory to store the cached result set, but instead persists to disk or a database. Memory-based tables have been used in Oracle and MySQL to achieve even better performance. When the refresh occurs, the object view or procedure is executed and the result set is written to the cache.

### To enable transaction result caching

1. From the Studio navigation tree, locate and open the editor for the procedure for which you want to cache transaction results.
2. Select the Info tab.
3. Check the Execute only once per transaction for each unique set of input values.
4. Save your changes.

## Caching to the Default Database Target

For the resource being cached, storage depends on the result set output and on retrieval of the entire result set or retrieval of a filtered subset.

For views and tables, the expiration period applies to the whole result set. For procedures, each input variants data has its expiration tracked separately. If used in a cluster environment, each node of the cluster becomes a separate cache view.

If a resource uses a data source that was originally added to TDV Server using the pass-through mode without saving the password, row-based security can affect cache refresh functionality. For details on save password and pass-through login, see [Adding a Data Source, page 70](#).

The default cache is node and fault tolerant.

## Limitations

Cache policies cannot be stored in the default cache database.

### To enable default caching

1. In Studio, open a view or procedure.
2. Select the Caching tab.
3. Click Create Cache.
4. Under Status, select the Enable check box. If you decide to leave it cleared, you can continue to define the cache, but it will not be active until you select the Enable check box.

When a cache is disabled, all existing cache settings are ignored. The view or procedure is used as if caching did not exist. Toggling between the enabled and disabled state does not cause refreshing of the data or resetting of the expiration date for the data.

5. Save your changes.

Several fields will display with non-editable information.

The screenshot shows the 'Caching' configuration window in TDV Studio. At the top, it says 'Status - Last Updated: 02 Jun 2015 16:51:36'. Below this, there are two main sections: 'Status' and 'Storage'. In the 'Status' section, the 'Enable' checkbox is checked. Below it, the status is 'NOT LOADED' with a yellow warning triangle icon. To the right, it shows 'Last load time: Never' and 'Size: 0 Kb'. There is an 'Error:' field and a 'Details' button. In the 'Storage' section, the 'Use Default Cache For Storage' checkbox is checked. Below it, there are three radio buttons: 'Automatic' (selected), 'Single Table', and 'Multi-table'.

The Data Source, Table Schema (Optional), and Table Prefix fields can be used to determine the location of your cached data within localhost.

6. Set cache policy, cache refresh, expiration, Number of Buckets, Drop and Create indexes on load, and advanced options as necessary.

After data is added to the cache tables by click Refresh Now, you can navigate to the cached data source, execute the view where caching is enabled, and review the cached data. By default, the tables are created on the PostgreSQL database that was defined during the installation of TDV.

## Caching to a File Target

If a resource uses a data source that was originally added to TDV Server using the pass-through mode without saving the password, row-based security can affect cache refresh functionality. For details on save password and pass-through login, see [Adding a Data Source, page 70](#).

### To enable caching to a file target

1. In Studio, open a view or procedure.
2. Select the Caching tab.
3. Click Create Cache.
4. Under Status, select the Enable check box. If you decide to leave it cleared, you can continue to define the cache, but it will not be active until you select the Enable check box.

When a cache is disabled, all existing cache settings are ignored. The view or procedure is used as if caching did not exist. Toggling between the enabled and disabled state does not cause refreshing of the data or resetting of the expiration date for the data.

5. Under Storage, specify Automatic to store the cached data in a system-created file accessible through Studio:

`<HostName>/lib/sources/cacheDataSource`

The physical files are stored by default in the TDV Server installation directory at: `<TDV_install_dir>/tmp/cache`

Each cached resource has a cache table in the cacheDataSource data source. The cache table's name contains the resource type (view or procedure) and a system-generated ID.

6. Save the cache settings.



## Pre-Creating Caching Objects for Database Caching

The instructions in this topic are optional and assume that you can create database objects as needed. You will also need to be familiar with the server, schema, and database naming conventions for the database where you are creating these tables. It is suggested that you obtain the documentation for your database of choice. Depending on your corporate policies and procedures, you might have to create the caching objects directly in the database before using Studio to set up caching.

At a minimum, non-file caching requires three tables. One table to hold the cache data, one to hold the cache status, and one to hold the cache tracking information. You can name them anything that is valid according to the constraints of the database where you are creating them. It is suggested that you use names that will be obvious to someone else.

### To pre-create caching objects in a database

1. Determine the optimal database for your cache target.
2. Add that database as a data source within Studio, if it is not there already.
3. Determine whether single or multiple cache tables will be needed.
4. Determine how many caches will be needed, or define a process for their request.
5. Locate and open the tool you want to use to create your database tables.
6. For single table caches create the following table using DDL statements similar to the following for each unique TDV resource for which you want to define a cache. The DDL might need to be altered depending on version of TDV you are using, database type where you are creating the table, TDV resource that you are caching, and whether you want to index the data or not. In the following table, UID stands for user identification. You can name the tables anything you want <table\_data> is used to indicate that you will need to specify the names, data types, and other table creation required metadata for the columns you want to create in that table.

Table	DDL Example
<UID_cache>	<pre>DROP TABLE IF EXISTS 'INV_cache_data'; CREATE TABLE 'INV_cache_data' ( 'cachekey' integer NOT NULL, &lt;table data&gt; )</pre>

7. For multiple table caches, create tables with the following structures for each TDV resource for which you want to define a cache. The DDL might need to

be altered depending on version of TDV you are using, database type where you are creating the table, TDV resource that you are caching, and whether you want to index the data or not.

Table	DDL Example
<UID_cache_status>	<pre>DROP TABLE "QAN"."mm_cache_status";  CREATE TABLE "QAN"."mm_cache_status" (   "clusterid" varchar(40),   "serverid" varchar(255) NOT NULL,   "resourceid" varchar(255) NOT NULL,   "parameters" varchar(255),   "status" char(1) NOT NULL,   "cachekey" number(10, 0) NOT NULL,   "starttime" timestamp(9) NOT NULL,   "finishtime" timestamp(9),   "cleartime" timestamp(9),   "bytes" number(19, 0),   "message" varchar(255),   "bucket" varchar(255),   "incrementalstatus" char(1),   "incrementalmaintenancelevel" varchar(255) )</pre>
<UID_cache_tracking>	<pre>DROP TABLE "QAN"."mm_cache_tracking";  CREATE TABLE "QAN"."mm_cache_tracking" (   "clusterid" varchar(40),   "serverid" varchar(255) NOT NULL,   "resourceid" varchar(255) NOT NULL,   "catalog" varchar(255),   "schema" varchar(255),   "table" varchar(255) NOT NULL,   "createtime" timestamp(9) )</pre>

Table	DDL Example
<UID_cache_data>	<pre> DROP TABLE "QAN"."mm0"; CREATE TABLE "QAN"."mm0" ( &lt;table_data&gt; ); CREATE UNIQUE INDEX "mm0_PRIMARY" ON "QAN"."mm0"("TransactionID" asc) DROP TABLE "QAN"."mm1"; CREATE TABLE "QAN"."mm1" ( &lt;table_data&gt;); CREATE UNIQUE INDEX "mm1_PRIMARY" ON "QAN"."mm1"("TransactionID" asc) DROP TABLE "QAN"."mm2"; CREATE TABLE "QAN"."mm2" ( &lt;table_data&gt;); CREATE UNIQUE INDEX "mm2_PRIMARY" ON "QAN"."mm2"("TransactionID" asc) DROP TABLE "QAN"."mm3"; CREATE TABLE "QAN"."mm3" ( &lt;table_data&gt; ); ... </pre>

8. Re-introspect the data source to make sure that the additional table you have created are available through TDV.
9. Set up your cache and select these tables as the status, tracking and data tables.

## Caching to a Single-Table Database Target

For the resource being cached, storage depends on the result set output and on retrieval of the entire result set or retrieval of a filtered subset. Decide on a storage type for caching the execution result. For information on how TDV cached data types are mapped to data source data types, see “Cache Data Type Mapping” in the *TDV Reference Guide*.

If a resource uses a data source that was originally added to TDV Server using pass-through mode without saving the password, row-based security can affect cache refresh functionality. For details on Save Password and Pass-through Login, see [Adding a Data Source, page 70](#).

### To set up caching to a single table

1. In Studio, open a view or procedure.
2. Select the Caching tab.
3. Click Create Cache.

4. Under Status, select the Enable check box. If you decide to leave it cleared, you can continue to define the cache, but it will not be active until you select the Enable check box

When a cache is disabled, all existing cache settings are ignored. The view or procedure is used as if caching did not exist. Toggling between the enabled and disabled state does not cause refreshing of the data or resetting of the expiration date for the data.

5. Under Storage, select Single Table. The cached data is stored in a specified data source. Type or browse to such a storage data source for the cache target.
6. Use Browse to locate and specify the data source where you want to create the cache table. After you select the data source, its full path is displayed in the Data Source field. For data integrity, each resource that is cached should have its own cache data tables.
7. Click Open Data Source. In the Caching section of the Configuration tab, create (execute the DDL), rename or browse to two tables, one for storing cache status data (Status Table) and the other for storing cache tracking data (Tracking Table).
8. Save the data source panels.
9. Navigate back to the view or procedure with the open Caching tab.
10. Click Browse next to the result field in the Table for Caching section. In the Select cache table for result dialog box, specify a location within the data source to create a table for caching. This location can be the root level of the data source, or a schema. Follow the instructions on the screen to get through the screens that might appear.

For example, when you select a data source, the right side of the screen might say Create Table. When you type a name and click Create, a DDL for result window appears showing the DDL generated by Studio. Click Execute in that window to create the table in the data source. Even though a dialog box might say DDL execution was successful, a Status of CONFIG ERROR plus an Error message may appear on the Caching panel. Click Details for a full description.

11. Save the cache settings. After cache settings are saved, each cached resource appears with a lightning-bolt icon in the Studio resource tree to show that the resource is cached.
12. Optionally, if you would like to have actions happen before or after the cache is refreshed, see [Defining Pre- and Post-Actions for a Full Refresh Mode Cache, page 454](#).
13. If you want to define pull-based incremental caching for your file-based data cache, see [Setting Up Pull-Based Incremental Cache, page 455](#).

14. If you have data type incompatibilities between your view and your data storage type, see “Cache Data Type Mapping” in the *TDV Reference Guide*.

## Creating a Multiple Table Cache on a Database Target

With the multiple table cache option, TDV stores the cache data, from views or tables, in a user specified number of tables. Because the cached data can be stored in different tables, it is possible to:

- Create more effective indexes on the cached data
- Clear old data from the cache faster than with other modes of caching

The multi-table cache option is primarily meant for caches that contain a substantial amount of data which is retained for a long time.

The multi-table feature is designed for multiple cache refreshes. Each refresh populates rows in one table, and because multiple tables are open the performance of caching is improved. Records are not distributed across multiple tables. Multiple tables available for cache refreshes creates a situation where customers accessing data in one of the cached tables does not slow down a refresh action because one of the other cache tables can be used.

If a resource uses a data source that was originally added to TDV Server using the pass-through mode without saving the password, row-based security can affect cache refresh functionality. For details on Save Password and Pass-through Login, see [Adding a Data Source, page 70](#).

Follow the instructions in these sections to use the multi-table cache feature:

- [Configuring Teradata for Use as a Multi-Table Cache Target, page 425](#)
- [Enabling Caching to Multiple Tables, page 426](#)

## Configuring Teradata for Use as a Multi-Table Cache Target

For Teradata, the TDV multi-table option can make use of the Teradata bulk loading FastLoad FastExport functions. You must follow the Teradata documentation for how to set up the FastLoad FastExport features on the Teradata data source and configuring session count. You can then use Studio to complete the configuration of FastLoad FastExport functions.

**Note:** If you are not using Teradata as a cache target, you can skip to [Enabling Caching to Multiple Tables, page 426](#).

### To configure Teradata as the multi-table cache target

1. Open Studio.
2. Select Administration > Configuration.
3. Search for Enable Native Loading and make sure it is set to True.
4. Right-click the data source name in the Studio resource tree and select Open.
5. Select the Configuration tab and under the Connection Information select the Advanced tab.
6. Use the Advanced tab to set values for the following fields.

Field	Description
Enable FastLoad/FastExport for large tables	True means to use Teradata's FastLoad or FastExport utility to speed up query times. Query cardinality is used to decide whether to use Fastpath or JDBC default loading.
FastExport Session Count	The number of FastExport sessions to use for Teradata.
FastLoad Session Count	The number of FastLoad sessions to use for Teradata.

7. Save your settings.

### Enabling Caching to Multiple Tables

When clearing a multi-table cache, TDV first attempts to clear the cache using a TRUNCATE command. If the TRUNCATE command is not supported, a DELETE command is attempted.

#### To enable caching that saves data to multiple tables

1. In Studio, open a view or a table.
2. Select the Caching tab.
3. Click Create Cache.
4. Under Status, select the Enable check box. If you decide to leave it cleared, you can continue to define the cache, but it is not active until you select the Enable check box.

When a cache is disabled, all existing cache settings are ignored. The view is used as if caching did not exist. Toggling between the enabled and disabled state does not cause refreshing of the data or resetting of the expiration date for the data.

5. Under Storage, specify the storage type as Multi-table. Multi-table is a data caching option that creates one table for each cache refresh up to the cache table threshold.  
  
This option requires that you specify a database data source to hold the cache tables and that you have sufficient privileges on that data source to CREATE and DELETE cache objects.  
  
Note: Resources cannot share the same data cache table.
6. Identify a database data source where you have permissions to create and delete objects from the database.  
  
**Note:** File data sources are not valid targets for multi-table caching.
7. Use Browse to locate and specify the data source where you want to create the cache table. After you select the data source, its full path is displayed in the Data Source field.
8. Click Open Data Source. In the Caching section of the Configuration tab, create (execute the DDL), rename or browse to two tables, one for storing cache status data (Status Table) and the other for storing cache tracking data (Tracking Table).
9. Save the data source panels.
10. Navigate back to the view or procedure with the open Caching tab.
11. In the Multi-table section, choose between the alternatives shown in the table.

Field	Description
Create Tables Automatically	Provides selections for indicating a table prefix, number of buckets, and index creation for your required cache objects.
Choose Tables for Caching	Provides a mechanism for you to select predefined cache tables. Your predefined cache tables must adhere to the metadata requirements of the cache tables. For data integrity, each resource that is cached should have its own cache data tables.

12. If you selected Create Tables Automatically, you must make choices in the fields listed in the table.

Fields	Description
Table Catalog (optional)	Depending on how your data source was defined and introspected, you might have one or two levels of folders under the data source in the Studio resource tree. The table catalog refers to the first level of folder under the data source. If your data source contains subfolders, type the name of the first level here. The name is case-sensitive.
Table Schema (optional)	The table schema refers to the second level of folder under the data source. If your data source contains subfolders, type the name of the secondary level here. The name is case-sensitive.
Table Prefix	Prefix to add to the cache tables and any indexes that you want to create. A unique prefix is required.
Number of Caching Tables	<p>Use to indicate the number of snapshots of the cache to keep. Start with a value of 3 and then determine if that number needs to be increased to accommodate your specific caching needs.</p> <p>The number of cache tables needed depends on how often data is cached, how much data is cached, how often refresh occurs, and the longest running transaction that accesses this cache. For example, if the longest running transaction is 4 hours and refreshes happen every hour, you should define at least 4 cache tables. If a cache is to refresh every 2 hours but some transactions run for 6 hours, configure at least 4 cache tables.</p> <p>Each row in cache status table has the name of the cache table containing the snapshot.</p> <p>A cache table is not eligible for garbage collection as long as there is an active transaction that uses it.</p> <p>TDV attempts to detect cache table sharing, but it is your responsibility to ensure that each cache table is used by only one resource.</p>
Create Cache Tables	Runs the DDL to create the tables needed for caching.
Drop indexes before load and create indexes after load	When selected, all indexes listed in Indexes tab of the view are part of the generated DDL and are created. Enabling this check box makes TDV drop indexes before loading data and recreates them after, to improve load time.



13. If you want to have the multi-table caching option to drop and create indexes after the cache loads, select the Indexes tab and review or define an index for the view or table. For information on how to create the index using the tab, see [Defining Primary Key for a View or Table in the Indexes Panel](#), page 156.
14. If you selected Choose Tables For Caching, you must make choices in the following fields:

Fields	Description
Add Table	Use to add additional tables for cache storage.
Table Name	Browse to select or create the table for a multi-table cache. You can also type the resource tree path.  This table must not be used to store data for other caches.

15. Save the cache settings. After cache settings are saved, each cached resource appears with a lightning-bolt icon in the Studio resource tree to show that the resource is cached.
16. Optionally, if you would like to have actions happen before or after the cache is refreshed, see [Defining Pre- and Post-Actions for a Full Refresh Mode Cache](#), page 454.
17. Optionally, if you want to define pull-based incremental caching for your file-based data cache, see [Setting Up Pull-Based Incremental Cache](#), page 455.
18. If you have data type incompatibilities between your view and your data storage type, see “Cache Data Type Mapping” in the *TDV Reference Guide*.

## Enabling Cache Data Storage to Multiple Data Sources

For each eligible data source, you can specify whether you want the cache status and tracking data stored on that data source or on another eligible data source. Typically this type of configuration allows an administrator to manage all the tracking and status tables. When using multiple data sources for caching, the cache tracking and cache storage tables stay together on the same data source.

### Requirements

- The cache data source and the data source that holds the cache status and tracking tables must be owned by the same user.
- The cache policy requires the use of the same cached data source for status and tracking tables.

- System data sources, such as the file cache or default cache) are not eligible to hold the cache status and tracking tables.
- The data source being used as the cache data source is not eligible to hold the status and tracking tables when attempting to enable this solution.

### To enable caching to multiple data sources

1. In Studio, open the data source that you want to use to store the status and tracking tables for your cache. For example, Oracle11.
2. Under Data Source Cache Configuration, select Current data source.
3. For the Status Table and Tracking Table fields, select Browse and browse to existing tables that you want to use or browse and create new tables to hold the data.
4. Save the data source configuration.
5. Open the data source that you want to use to store your cache data. For example, ds\_orders.
6. Under Data Source Cache Configuration, select Select a different data source.
7. Browse to locate and specify the data source where you want to store cache data. For example, Oracle11.
8. Verify that the tables indicated in the Status Table and Tracking Table fields are the ones you want to use.
9. Optionally, open the data source and select other status and tracking tables.  
Click Open Data Source. In the Caching section of the Configuration tab, create (execute the DDL), rename or browse to two tables, one for storing cache status data (Status Table) and the other for storing cache tracking data (Tracking Table).
10. Save the data source configuration.
11. Open the table or view resource for which you want to cache data.
12. Select the caching tab.
13. Select Create Cache.
14. Under Storage, select Single Table or Multi-table.
15. For the Data Source field, Browse to the data source which you want to use to hold the cache data. For example, ds\_orders.
16. Enable the cache.
17. Save the data source configuration.

18. Refresh the which you want to use to hold the cache data. For example, ds\_orders.
19. Enable the cache.
20. Save the data source configuration.
21. To test your configuration, select Refresh Now to populate the cache tables. Open the cache data, cache status and cache tracking tables, validate that each of them contains data and have timestamps that are consistent with the time that you ran the latest cache refresh.

## Setting Up Native (Bulk) Caching Options

The TDV native loading option improves cache performance when:

- The cache source and cache target reside on the same TDV data source resource.
- The cache data is being saved to one of the active cache targets listed in the Native Loading Option column of the table in [Supported Cache Target Storage Types, page 410](#).

The native cache loading options are enabled by default. Native loading makes use of functionality that is inherent to the data source to improve the speed of data movement.

If TDV detects that your data source and your cache data target are on the same TDV data source resource, it determines if a direct SELECT and INSERT is the best way to move data or if one of the configurable native loading options might work faster. Most databases have proprietary data movement functionality that is optimized for that database. For example, all Oracle databases come with database link functionality. That database link functionality can be used to provide cache loading performance gains that are not possible when using the TDV JDBC connections to move data.

If both the native database loading and the TDV cache loading fail, the refresh status is set to failed.

Topics in this section	Performance Option
<a href="#">Configuring TDV Native Loading Option for DB2, page 432</a>	Uses the DB2 LOAD utility.
<a href="#">Configuring TDV Native Loading Option for Microsoft SQL Server, page 434</a>	Uses the bcp utility (bcp.exe) for bulk import and export.
<a href="#">Configuring Native Caching for Netezza, page 437</a>	Uses Netezza external tables.
<a href="#">Configuring Native Caching for Oracle, page 439</a>	Uses database links.
<a href="#">Configuring Native Caching Option for Sybase IQ, page 439</a>	LOAD_TABLE statement.
<a href="#">Configuring Native Caching Option for Vertica, page 443</a>	Uses Bulk Load utility.

## Configuring TDV Native Loading Option for DB2

For DB2, the TDV native loading option makes use of DB2's LOAD utility. The LOAD utility can quickly load or add data to a table where large amounts of data need to move. LOAD can perform significantly faster than IMPORT because LOAD writes formatted pages directly into the database while IMPORT uses SQL INSERTs. Before attempting to use this method, we recommend that you see if using JDBC batch insert options can give you acceptable performance improvements. If you choose to implement the JDBC functionality, you do not need to configure the DB2 LOAD utility, or change any TDV configuration settings.

The DB2 LOAD utility when working with TDV requires that the DB2 command-line utility be run. How it works with TDV varies by platform:

Platform	DB2 Command-Line Utility Name	Execution Details
Windows	DB2CMD.exe	When it runs, a command window pops up, requires a password, and stays active until the upload completes. While the window is open, the password might be visible.

Platform	DB2 Command-Line Utility Name	Execution Details
UNIX	db2	It can be run as a background process.

### Requirements

- The data being loaded must be local to the server.
- Requires advanced DB2 database level configuration

### Limitations

This feature is not valid for:

- Binary and BLOB data types
- Kerberos implementations

### To configure the DB2 LOAD utility to work with TDV for caching

1. Consult the IBM documentation on configuring and using the DB2 LOAD utility.
2. Install and configure all relevant parts of the DB2 LOAD utility according to IBM's instructions for your platform.

The client drivers might need to be installed on all the machines that are part of your TDV environment.

3. Verify the full path to the DB2 command-line utility that you want to use to run the DB2 LOAD utility. For example, locate the path to your DB2 SQL command-line client.
4. Open Studio.
5. Select Administration > Configuration.
6. Locate the Enable Bulk Data Loading configuration parameter.
7. Set the value to True.
8. Click Apply.
9. Click OK.
10. Locate the DB2 Command-Line Utility Path configuration parameter.
11. For Value, type the full directory path to the DB2 command-line program. If there are spaces in the pathname, be sure to enclose the path in double quotes. For example:

"C:\Program Files\IBM\DB2\Tools\Bin\DB2CMD.exe"

12. Click Apply.
13. Click OK
14. Restart your TDV Server.  
 Some configuration parameter value changes are applied while the TDV Server is running, but many of them require a server restart to work correctly.
15. Open Studio and locate the DB2 data source for which you want to enable the bulk load feature.
16. Open the data source editor.
17. Select the Advanced tab.
18. Scroll down to locate the Database Alias (Used For DB2 Load) field.  
 This property is passed on to the DB2 Load to identify the cataloged database.
19. For Value, type the name of the DB2 database. For example: dvbudb21.
20. Save your changes.
21. Refresh your cache.

Temporary files used to support this feature are created in `infl<TDV_install_dir>\...tmp\cacheloading\db2`, all files, data, commands and logs are deleted by TDV after the upload process completes.

### Configuring TDV Native Loading Option for Microsoft SQL Server

For Microsoft SQL Server, the TDV native loading option makes use of Microsoft's bulk import and bulk export (bcp) function.

The bulk import and bulk export functionality available caching for Microsoft SQL Server requires the configuration of the Microsoft bcp utility. When the bulk import and bulk export functionality is used instead of the JDBC functionality, performance is improved. The bcp utility (bcp.exe) is a command-line tool that uses the Bulk Copy Program API. The Microsoft bcp utility performs the following tasks:

- Bulk exports data from a SQL Server table into a data file.
- Bulk exports data from a query.
- Bulk imports data from a data file into a SQL Server table.
- Generates format files.

If you choose to implement the JDBC functionality, you do not need to configure the bcp utility, or change any TDV configuration settings.

When the cache source and target exist on the same SQL Server data source, native loading of cache data using a direct SELECT and INSERT can provide significant performance gains. The feature requires that the value of the Enable Bulk Data Loading Studio configuration parameter be set to True.

When configuring data ship or a cache for Microsoft SQL Server, you can configure the bcp utility and then set up access permissions. Both of these processes are described below.

The configuration steps are similar for caching and data ship, for more information see [Configuring Data Ship for Microsoft SQL Server, page 533](#).

**Note:** In the bcp utility, NULL values are interpreted as EMPTY and EMPTY values are interpreted as NULL. TDV passes the '\0' value (which represents EMPTY) through the bcp utility to insert an EMPTY value into the cache or data ship target. Similarly, TDV passes an EMPTY string ("") to the bcp utility to insert a NULL value into the cache or data ship target.

### To configure the Microsoft bcp utility to work with TDV for caching

1. Verify that the bcp.exe utility has been installed and is located in a directory that you can access. Note the full path to the bcp.exe file.
2. Open Studio.
3. Select Administration > Configuration > Data Sources > MS SQLServer Sources.
4. Select the Microsoft BCP utility parameter.
5. For Value, type the full directory path to the bcp.exe. For example:

C:\Program Files\Microsoft SQL Server\100\Tools\Binn\bcp.exe

6. Optionally to use Windows Authentication, locate and select the DataShip BCP Threshold parameter.  
The default value is 50000. After bcp utility is enabled, if the data shipping cost estimate is 50000 or above, data ship uses the bulk import and export implementation; otherwise JDBC, is used to move the data.
7. Optionally to use Windows Authentication, adjust the value of the DataShip BCP Threshold parameter to values that fit your requirements.
8. Click Apply.
9. Select Administration > Configuration.
10. Navigate to TDV Server > Configuration > Debugging > Enable Bulk Data Loading.

Or, search for 'bulk' using the Configuration Find field.

11. Set the value to True.
12. Click Apply.
13. Click OK.
14. Stop the TDV Server.
15. From the command line where your TDV Server runs, log in as the domain user.
16. Start the TDV Server.
17. You can now complete the setup of your cache data target.
18. Click OK.
19. Optionally, when running with Windows Authentication, on windows, open Services > TDV Server <version> and select Properties.
20. Select the Login On tab, set the This account fields to a domain user who has access to MSSQL instance.
21. Click OK.

### **To set up access permissions for SQL Server for caching**

1. Consult your SQL Server documentation for how to set the SHOWPLAN permissions for the database.
2. For every SQL Server database that will participate in the caching, grant the SHOWPLAN permissions. For example:  

```
GRANT SHOWPLAN
TO <database> [ ,...n ]
```
3. You can now complete the setup in [Caching to a File Target, page 420](#).

### **To tune the TDV caching behavior when Microsoft SQL Server is the cache target**

1. Open Studio.
2. Select Administration > Configuration from the Studio menu bar.
3. Expand the Data Sources > Common to Multiple Source Types > Data Sources Data Transfer.
4. Determine the best value for the Column Delimiter parameter.  
 The default is |.
5. Click Apply.



6. Click OK.

## Configuring Native Caching for Netezza

For Netezza, the TDV native loading option makes use of the Netezza external tables. You must follow the Netezza documentation for how to set up the external tables on the Netezza data source.

For Netezza you have the following configuration choices:

- [Enabling Bulk Load for Netezza, page 437](#)
- [Managing NUL Character in Strings for Netezza, page 438](#)

When the cache source and target exist on the same Netezza data source, native loading of cache data using a direct SELECT and INSERT can provide significant performance gains. The feature requires that the value of the Enable Bulk Data Loading Studio configuration parameter be set to True. For Netezza, the parameter value must also be True to enable bulk loading of data cached from procedures.

XML, BINARY, and VARBINARY are not supported by Netezza, any data type related to these data types will not be added to the Netezza cache.

By default, TDV analyzes the table selected for caching to see if DISTRIBUTE can be used to achieve performance gains through parallel processing of the cache query. All keys and indexes specified on the resource are consulted. This is done to determine if the DISTRIBUTE clause was added to the native DDL used to create the cache target tables. For single-table caching, the cachekey column is also added to the DISTRIBUTE clause. If neither keys nor indexes are specified, DISTRIBUTE ON RANDOM is used.

## Enabling Bulk Load for Netezza

### To enable bulk loading for Netezza

1. Open Studio.
2. Select Administration > Configuration from the Studio menu bar.
3. To tune buffer size for Netezza, expand the Data Sources > Common to Multiple Source Types > Data Sources Data Transfer folder.
4. Determine the best value for the Buffer Flush Threshold configuration parameter.

This parameter controls how many data rows are written to the buffer file before flushing the buffer. The minimum is 1000 and the default is 10000.

5. Click Apply.

6. Click OK.
7. Select Administration > Configuration.
8. Navigate to TDV Server > Configuration > Debugging > Enable Bulk Data Loading.  
Or, search for 'bulk' using the Configuration Find field.
9. Set the value to True.
10. Click Apply.
11. Click OK.
12. You can now complete the setup of your Netezza cache data target.

### **Managing NUL Character in Strings for Netezza**

Optionally, if you need to move data that has NUL characters, you can use the following procedure to determine how those characters are managed by TDV.

When the Ignore Nul Characters in Strings configuration parameter is true, NUL('\0') characters get discarded by Netezza and rest of the String is loaded. When the configuration parameter is false, NUL characters in Strings are not discarded. The default value is false.

#### **To ignore Nul characters in strings**

1. Make sure you have both Modify All Config and Access Tools rights.
2. Log into Studio as the admin user.
3. From the Administration menu, choose Configuration.
4. In the tree pane, navigate to Data Sources > Netezza Sources > Ignore Nul Characters in Strings.
5. Select True.

When set to false, NUL characters in strings are not discarded.

6. Click Apply.
7. Click OK.

This Studio configuration change is not immediately propagated to other open instances of Studio connected with this server.

8. Restart the TDV Server.

## Configuring Native Caching for Oracle

When you want to use Oracle as your cache target, you can finish setup of the TDV native loading option that uses Oracle's database link functionality to provide better caching performance. Additionally, you can define the TDV parallel cache loading option. This feature is supported for Oracle cache targets.

### To set up the native loading option caching data to an Oracle target

1. Make sure that the view that you want to cache:
  - Is a view created from a single TDV data source.
  - Is a view that has a pass-through query that is run (or pushed down) entirely to the data source.
  - The view source can be DB2, Oracle, SQL Server 2008, or Sybase 15.
2. Define database links between your data sources and the Oracle cache target. The database links must be defined using Oracle database tools to directly add the database link using SQL, or by modifying your tnsnames.ora file.
3. Open Studio.
4. Open the Oracle data source that you want to act as your cache target.
5. On the Configuration tab, select the Advanced tab in the Connection Information section.
6. Scroll down and check the Enable Oracle Database Link check box.
7. Type the database link name as you defined it in your Oracle database. The database link path must point to the path of the data that is the source for the cache. Use the Add Database Link button if you want to have more than one database link (to enable caching from multiple sources).
8. Make sure Enable Data Source is checked.
9. Click Add/Remove Resources to open the Data Source Introspection window and find, introspect, remove and view properties of data sources.
 

See [Retrieving Data Source Metadata, page 107](#), for details.
10. Click **Test Connection** to make sure the connection works.
11. Save your changes.

## Configuring Native Caching Option for Sybase IQ

Depending on the platform you are installing to, your steps might vary. These steps do not detail every step as might be required by Sybase, refer to your Sybase documentation for further details.

### To configure Native Cache Loading for Sybase

1. Verify or install a SQL Anywhere Database Client. You can obtain a trial version through the Sybase download site.

If you don't have SQL Anywhere Database Client and don't want to install one on your Unix system, then you can copy the client into `<TDV_install_dir>/sqlanywhere<ver>`, because the SQL Anywhere database client has the drivers that are needed for TDV.

2. Locate the following files in the directory where the Sybase client is installed.
  - `jodbc.jar`
  - `libdbjodbc<ver>.so` for Unix
  - `dbjodbc<ver>.dll` for Windows
3. Copy the files to the locations described in the following table.

OS	Copy <code>jodbc.jar</code> Into	Copy <code>dbjodbc&lt;ver&gt;.dll</code> Into
Windows 64	<code>&lt;TDV_install_dir&gt;\apps\common\lib</code>	<code>&lt;TDV_install_dir&gt;\apps\common\lib\win64</code>
Windows 32	<code>&lt;TDV_install_dir&gt;\apps\common\lib</code>	<code>&lt;TDV_install_dir&gt;\apps\common\lib</code>
UNIX (32 and 64)	<code>&lt;TDV_install_dir&gt;\apps\common\lib</code>	<code>&lt;TDV_install_dir&gt;\apps\common\lib</code>

4. Stop your TDV Server.
5. For Unix, set the global `LD_LIBRARY_PATH` environment variable to point at the SQL Anywhere client libraries folder. TDV uses `LD_LIBRARY_PATH` to find the Sybase Client library. For example, to temporarily set the variable, type:

```
export LD_LIBRARY_PATH=/opt/<TDV_install_dir>/sqlanywhere<ver>/lib<ver>/
```

6. Create an ODBC data source following the guidelines in your Sybase documentation. The following instructions highlight some of the necessary steps depending on your platform.

Platform	Instructions
Unix	<ol style="list-style-type: none"> <li>1. Create an odbc.ini file. We recommend that you create it under &lt;TDV_install_dir&gt;.</li> <li>2. Create a Sybase IQ data source name (DSN) in the odbc.ini file. For work with TDV, the Driver variable is the most important setting, because it points to the SQL Anywhere client that you have installed. For example, data sources named, test1 and test2, would look similar to the following: <pre>##### SybDB@machine64:cat odbc.ini [test1] Driver=/opt/&lt;TDV_install_dir&gt;/sqlanywhere&lt;ver&gt;/lib&lt;ver&gt;/libdbodbc&lt;ver&gt;_r.so host=10.5.3.73 port=2638 uid=dba PWD=password DatabaseName=asiqdemo PreventNotCapable=YES  [test2] Driver=/opt/&lt;TDV_install_dir&gt;/sqlanywhere&lt;ver&gt;/lib&lt;ver&gt;/libdbodbc&lt;ver&gt;_r.so host=10.5.3.74 port=2638 uid=dba PWD=password DatabaseName=asiqdemo PreventNotCapable=YES #####</pre> </li> </ol>

Platform	Instructions
Windows	<ol style="list-style-type: none"> <li>1. Start the ODBC Administrator, select Sybase &gt; Data Access &gt; ODBC Data Source Administrator.</li> <li>2. Click Add on the User DSN tab.</li> <li>3. Select the Sybase IQ driver and click Finish.</li> <li>4. The Configuration dialog box appears.</li> <li>5. Type the Data Source Name in the appropriate text box. Type a Description of the data source in the Description text box if necessary. Do not click OK yet.</li> <li>6. Click the Login tab. Type the username and password. If the data source is on a remote machine, type a server name and database filename (with the .DB suffix).</li> <li>7. If the data source is on your local machine, type a start line and database name (without the DB suffix).</li> <li>8. If the data source is on a remote system, click the Network tab. Click the check box for a protocol and type the options in the text box.</li> <li>9. Click OK when you have finished defining your data source.</li> </ol>
	<ol style="list-style-type: none"> <li>10. On Unix, use the following commands to verify that the DSN is set up successfully:           <pre data-bbox="329 916 582 965">cd sqlanywhere&lt;ver&gt;/bin&lt;ver&gt; ./dbping -m -c "DSN=test1"</pre> <p data-bbox="372 1008 1268 1098">A “Ping server successful” message means that the DSN is working and any application can use the DSN to contact the Sybase IQ through the ODBC Driver.</p> </li> <li>11. On Unix, set the global ODBCINI environment variable to point at the SQL Anywhere odbc.ini file. For example, to temporarily set the variable, type:           <pre data-bbox="329 1187 743 1208">export ODBCINI=/opt/&lt;TDV_install_dir&gt;/odbc.ini</pre> </li> <li>12. Start TDV server.</li> <li>13. Open Studio.</li> <li>14. Open your Sybase IQ data source.</li> <li>15. Select the Advanced tab.</li> <li>16. Scroll to the end of the Advanced tab.</li> </ol>

17. Select and type the following:

Sybase iAnywhere JDBC Driver	Select this check box to enable better performance. This option enables the Sybase IQ specific ODBC LOAD TABLE SQL tool to import data into TDV.
Sql Anywhere Data Source	Enter your ODBC DSN name.

18. Save and close your Sybase IQ data source.

### Configuring Native Caching Option for Vertica

By default, TDV is configured to use Vertica's Bulk Load utility or INSERT/SELECT as the native loading mechanism. There are no TDV configuration parameters that you need to set.

#### Validating that your system is configured to enable native caching

1. Open Studio.
2. Select Administration > Configuration.
3. Search for Enable Native Loading and make sure it is set to True.
4. You can now complete the setup in [Caching to a File Target, page 420](#).

### Setting Up the Parallel Cache Option

TDV provides a parallel caching option that is used to maximize performance of data caching. If cache loading performance gains cannot be realized using the TDV native loading option, you can try the TDV parallel option. This option uses statistics derived from a unique numeric key to create multiple partitions that can be used to load the data using parallel processes.

During parallel loading, the reader and writer work in parallel and are not blocked or waiting for one another. The reader reads the table rows into TDV memory and the writer pushes them into target database. You can have multiple readers and corresponding writers that work on different partitions simultaneously. These parallel threads use JDBC-based read write calls.

#### Requirements

This performance option is available as listed for the Native Cache Target Support column of the table in [Supported Cache Target Storage Types, page 410](#).

It requires some setup beyond TDV configuration parameters. The parallel cache loading option requires that the view that you are caching has:

- One or more user-defined or auto-inferred, simple or composite primary key of numeric or character type.
- For numeric key columns, BOUNDARY cardinality statistics or DETAILED cardinality statistics are needed.
- For character key columns, DETAILED cardinality statistics are needed.

Because partitioning is being determined on the key column, the cardinality statistics help determine how many unique partitions can be loaded in parallel. The number of unique partitions that can be found by the statistics collection determines how many threads can be used to load the data into the cache.

### To configure the TDV parallel option for data caching

1. Open Studio.
2. Open a view in Studio that has had caching enabled.
3. Validate that your view has:
  - One or more user-defined or auto-inferred, simple or composite primary key of numeric or character type.And that for the following special cases you have the required cardinality statistics:
  - For numeric key columns, BOUNDARY cardinality statistics or DETAILED cardinality statistics are required.
  - For character key columns, DETAILED cardinality statistics are required.
4. Follow the steps in [Creating Cardinality Statistics for a View, page 490](#).
5. Save your work.

The next time your cache is refreshed, this cache loading option is attempted.

## Enabling JDBC-Only Cache Loading

If your environment requires that you disable the TDV Native and Parallel Options for cache loading or you need to force the use of JDBC inserts, you need to edit the TDV configuration parameters.



### To enable JDBC-only cache loading for Oracle and Netezza data sources

1. Open Studio.
2. Select Administration > Configuration.
3. Search for the Enable Native Loading parameter and set its Value to False.  
If this parameter is disabled, TDV uses JDBC to perform the inserts into the cache table.  
By default this parameter is enabled. For cache targets saved to Oracle, database links are used. For cache targets saved to Netezza, bulk loading options are used to move data.
4. Select the Enable Parallel Loading parameter and set Value to False.
5. Click Apply.
6. Click OK.

## Canceling a Cache Refresh that Is Using Native or Parallel Loading

You can cancel a cache refresh process for parallel loading or Netezza.

**Note:** For Oracle using native loading, the cache refresh process runs to completion; it cannot be stopped after it is started. TDV cleans up the temporary tables automatically.

### To cancel a cache refresh process for parallel loading or Netezza

1. Cancel the read request process that has started against the source view.
2. For parallel loading processes, you can cancel the parent request or cancel any of the threads to have the job canceled for all threads.

## Defining Cache Refresh Behavior

Cache refresh behavior can be defined to suit your needs. The following topics cover most of the TDV cache refresh behaviors that you can customize:

- [Refresh Owner, page 446](#)
- [Controlling Cache Refresh Behavior for Individual Resources, page 446](#)
- [Controlling Cache Refresh Behavior for Multiple Resources, page 449](#)
- [Defining Pre- and Post-Actions for a Full Refresh Mode Cache, page 454](#)
- [Setting Up Pull-Based Incremental Cache, page 455](#)

- [Setting Up Push-Based Incremental Caching for Oracle, page 460](#)

## Refresh Owner

For Cache Refreshes Started From Studio—TDV always uses the user credentials saved against the data source to perform all runtime cache refresh operations including refresh of the cache data and update of user status in the status table and the internal SYS\_CACHES. This is true also even though you might have pass-through logins enabled.

For Cache Refreshes Started From Triggers—If you have triggers defined that you use to start your cache refreshes, the user that initiates the table refreshes is the user that owns the refresh.

The user that is noted for specific actions within the refresh varies depending on your full TDV environment setup, on how many times you have run the refresh, and on whether you look in the Studio Manager, TDV log files, or your database log files. Implementation of TDV is highly customizable. If you are interested in determining which users are involved in the refresh actions at your site, perform testing and track the results.

## Controlling Cache Refresh Behavior for Individual Resources

Caches can be refreshed immediately or periodically using Studio. Cache policies can be defined to control the cache refresh behavior for several TDV resources. Caches can also be refreshed programmatically. Keeping data in your cache up-to-date ensures that results are correct. When a view or table resource is refreshed, the entire result set is obtained for the object and written to the cache.

Modifying the query of the view (or table) that you have caching defined on does not automatically update the cache. You must execute a refresh or wait for the next scheduled refresh cycle to get the correct result set.

- [Refreshing and Clearing the Cache for One Resource Using Studio, page 446](#)
- [Refreshing and Clearing Your Cache Programmatically, page 448](#)

## Refreshing and Clearing the Cache for One Resource Using Studio

You can use Studio to refresh your cache data immediately, or you can use Studio to configure regularly scheduled refreshes of your cache data.

For views and tables, the expiration period applies to the whole result set. For procedures, each input variants data has its expiration tracked separately.

**Note:** If you have multi-table caching defined, TDV first attempts to clear the cache using a TRUNCATE command. If the TRUNCATE command is not supported, a DELETE command is attempted.

### To define cache refresh and expiration schedules

1. In Studio, open a view or procedure that has had caching enabled.
2. Select the **Caching** tab.
3. Under Refresh Mode, specify the cache refresh mode. Refreshing a cached resource retrieves data from the sources and clears stale data as specified.

You can refresh the cache immediately by clicking Refresh Now.

Option	Description
Manual	<p>The resource owner or an administrator must manually refresh the cache using Refresh Now or programmatically by invoking the RefreshResourceCache procedure. See the <i>TDV Application Programming Interfaces Guide</i>.</p> <p>Any user with the ACCESS TOOLS right who is given appropriate privileges can also refresh the cache manually.</p> <p>If your cache is controlled by a cache policy, using a periodic or programmatic refresh is suggested.</p>
Exactly Once	<p>To refresh the cache just once at a specific time, select, and specify the time to start caching in the set of drop-down boxes in the section labeled <b>Start on</b>. The <b>Hour</b> field accepts a typed entry of <b>0</b>—and when you save the resource, Studio automatically converts the hour to <b>12</b> and <b>AM/PM</b> to <b>AM</b>.</p>
Periodic	<p>To refresh the cache periodically, select <b>Periodic</b> and specify in the <b>Refresh every</b> section how often to execute the resource for caching: every x number of seconds, minutes, hours, days, weeks, months, or years. In the <b>Start on</b> fields, specify the time and date to begin periodic refresh mode.</p>

4. Under Expiration Schedule, select Never expire, or select Expire after and specify the time period. The expiration period applies from the end of a refresh. The Expire after option is disabled if you are using incremental caching.

5. Under Advanced there are a variety of combinations:
  - a. If you select Full Refresh Mode, you can define pre-and post-cache actions, as described in [Defining Pre- and Post-Actions for a Full Refresh Mode Cache](#), page 454.
  - b. If you select Incremental Refresh Mode, you can define pre-and post-cache actions, as described in [Setting Up Pull-Based Incremental Cache](#), page 455.
6. Specify when to clear the cache.

Cache Clears Option	Description
when user clears it manually	Clear the cache only when the Clear Now button, an API call, or on cache expiration (Expire after has been selected in the Expiration Schedule section).
when refresh fails	(For full refresh caching only) Selecting this option would clear the cache if a refresh fails. This option allows access to previously cached data during a refresh.
when refresh begins	(For full refresh caching only) Selecting this option would automatically clear the cache before starting a refresh. Any clients attempting to read from the cached data must wait for the new data.
When load fails	(For push-based incremental caching only) Selecting this option would automatically clear the cache if the loading of data did not complete.
When initial load begins	(For push-based incremental caching only) Selecting this option would automatically clear the cache before starting a refresh. Any clients attempting to read from the cached data must wait for the new data.

7. (For procedures only) Define the maximum number of variants you want stored in the cache from the results of the procedure you are caching. Maximum number of unique set of input parameter values. (Default is 32.)
8. Save the cache settings.

## Refreshing and Clearing Your Cache Programmatically

If you have chosen to programmatically refresh your cached data, you have the following options:

- TDV provides stored procedures that can be used to clear cache contents, initiate a refresh, and change the state of a cache. You can use a SQL Script to call and perform any caching functions.

- Using the TDV trigger function, it is possible to respond to system- or user-generated events that call a procedure to refresh a cache.
- Administrative Web services can be used to define external programs that clear, refresh, enable, and disable the cache.

The following TDV API calls are available for use from SQL Scripts or Java Procedures, or that can be published for use from clients. Each of the following is accessed in Studio under <localhost>/lib/resource:

- ClearResourceCache(path, type)
- CreateResourceCacheKey(path, type, cacheKey)
- LoadResourceCacheStatus(path, type)
- RefreshResourceCache(path,type)
- UpdateResourceCacheEnabled(path, type, enabled)
- UpdateResourceCacheKeyStatus(path, type, cacheKey, status, startTime, message)

For details, see the *TDV Application Programming Interfaces Guide*.

The following Web services are available for use from clients outside the server. They can be accessed in Studio under Data Services/Web Services/system/admin/resource/operations:

- clearResourceCache (path, type)
- getResourceCacheConfig(path, type)
- refreshResourceCache (path, type)
- updateResourceCacheConfig (path, type, detail, cacheConfig)

## Controlling Cache Refresh Behavior for Multiple Resources

Cache policies can be defined to control the cache refresh behavior for several TDV resources. Defining cache policies allows you to reuse cache refresh definitions for multiple TDV resources. The logic inherent to the cache policy behavior manages cache refresh behavior for dependent resources and ensures better data integrity when updated caches for resources that have data dependencies. Keeping data in your cache up-to-date ensures that results are correct. When a view, table, or procedure resource is refreshed, the entire result set is obtained for the object and written to the cache.

Modifying the query of the view (or table) that you have caching defined on does not automatically update the cache. You must execute a refresh or wait for the next scheduled refresh cycle to get the correct result set.

### Multi-Table Cache Refresh Limitations

- If you have multi-table caching defined, TDV first attempts to clear the cache using a TRUNCATE command. If the TRUNCATE command is not supported, a DELETE command is attempted.
- If you schedule a reintrospection of the cache data source at exactly the same time as cache refresh, it might lead to errors. The multi-table cache refresh drops and recreates the indexes during cache refresh so it can appear that indexes are missing.

### To control cache refresh behavior

1. You must follow the instructions in [Defining a Cache Policy, page 450](#).
2. For each resource that you want to have associated with the policy, follow the instructions in one of the following sections:
  - [Assigning Resources to a Cache Policy, page 452](#)
  - [Assigning a Cache Policy to a Resource, page 453](#)

## Defining a Cache Policy

Cache policies define cache refresh and clearing behavior. The cache policies can then be applied to resources that are being cached.

### Cache Policy Limitations

Cache policies are not supported for:

- Procedures with input parameters.
- Pull-based incremental caches when defined on a table or view.
- Push-based incremental caches when defined on a table or view.

### To create a cache policy

1. From the Studio resource tree, expand <host>/policy/cache.
2. Right-click and select New Cache Policy.
3. Name the policy.
4. Click OK.
5. Open the new cache policy.
6. Select the Cache Policy Settings tab. For information about the Resources tab, see [Assigning Resources to a Cache Policy, page 452](#).

7. Select the Enable check box to enable this cache policy. If you decide to leave it cleared, you can continue to define the policy, but it will not be active until you select the Enable check box.
8. Accept the default or specify the data source where you want data about the cache policy to be stored. You can use the Browse button to browse through the Studio resource tree of available data sources.
9. Under Refresh Mode, specify the cache refresh mode. Refreshing a cached resource retrieves data from the sources and clears stale data as specified.  
You can refresh the cache immediately by clicking Refresh Now.

Option	Description
Manual	<p>The resource owner or an administrator must manually refresh the cache using Refresh Now or programmatically by invoking the RefreshResourceCache procedure.</p> <p>Any user with the ACCESS TOOLS right who is given appropriate privileges can also refresh the cache manually.</p> <p>If your cache is controlled by a cache policy, using a periodic or programmatic refresh is suggested.</p>
Exactly Once	<p>To refresh the cache just once at a specific time, select, and specify the time to start caching in the set of drop-down boxes in the section labeled Start on. The Hour field accepts a typed entry of 0—and when you save the resource, Studio automatically converts the hour to 12 and AM/PM to AM.</p>
Periodic	<p>To refresh the cache periodically, select Periodic and specify in the Refresh every section how often to execute the resource for caching: every x number of seconds, minutes, hours, days, weeks, months, or years. In the Start on fields, specify the time and date to begin periodic refresh mode.</p>

10. Under Expiration Schedule, select Never expire, or select Expire after and specify the time period. The expiration period applies from the end of a refresh. The Expire after option is disabled if you are using incremental caching.
11. Optionally, you can define pre-and post-refresh actions. As described in [Defining Pre- and Post-Actions for a Full Refresh Mode Cache, page 454](#).

## 12. Specify when to clear the cache:

Cache Clears Option	Description
when user clears it manually	Clear the cache only when the Clear Now button, an API call, or on cache expiration (Expire after has been selected in the Expiration Schedule section).
when refresh fails	(For full refresh caching only) Selecting this option would clear the cache if a refresh fails. This option allows access to previously cached data during a refresh.
when refresh begins	(For full refresh caching only) Selecting this option would automatically clear the cache before starting a refresh. Any clients attempting to read from the cached data must wait for the new data.

## 13. Save the cache settings.

**Assigning Resources to a Cache Policy**

You can assign one or more resources to a cache policy to have their cache refreshes managed by the same refresh definition. After a resource is assigned to a cache policy and the cache policy is saved, TDV sets the definitions on Caching tab of that resource to those defined by the cache policy. If caching was not enabled for the resource that you assign to the cache policy, it is enabled and the majority of the fields on the Caching tab are dimmed to indicate that they are under the control of the cache policy.

**To associate a resource with a cache policy**

1. Make sure that cache policies have been defined following the instructions in [Defining a Cache Policy, page 450](#).
2. In Studio, open a cache policy.
3. Select the Resources tab.
4. Add resources to the list to be managed by this cache refresh policy in one of the following ways:
  - Select one or more resources from the Studio resource tree and drag them into the Resources text field.
  - Click the green plus button and use the Select Resources dialog to navigate to the resource you want to add.
5. Save your cache policy.



Studio does validation of the policy definitions for the resources in the list and issues messages if there are things you need to fix.

6. Fix resource definitions if prompted by any Studio messages.
7. Save your changes.

## Assigning a Cache Policy to a Resource

Defining cache policies allows you to reuse cache refresh definitions for multiple TDV resources. The logic inherent to the cache policy behavior manages cache refresh behavior for dependent resources and ensures better data integrity when updated caches for resources that have data dependencies. If you did not add the resource to the cache policy on the **Resources** tab, you can follow these steps to associate a specific resource to a cache policy.

**Note:** If you have multi-table caching defined, TDV first attempts to clear the cache using a TRUNCATE command. If the TRUNCATE command is not supported, a DELETE command is attempted.

### Cache Policy Limitations

Cache policies are not supported for:

- Procedures with input parameters.
- Pull-based incremental caches when defined on a table or view.
- Push-based incremental caches when defined on a table or view.

### To associate a resource with a cache policy

1. Make sure that cache policies have been defined following the instructions in [Defining a Cache Policy, page 450](#).
2. In Studio, open a view, table, or procedure that has had caching enabled.
3. Select the Caching tab.
4. Locate the Cache Policy field.
5. Select the cache policy that you want to be used to control cache refresh and clearing behavior for this resource. You can use the Open Policy button to open the policy and review or change its settings as necessary.
6. (For procedures only) Define the maximum number of variants you want stored in the cache from the results of the procedure you are caching. Maximum number of unique set of input parameter values. (Default is 32.)
7. Save your resource.

Note: The **Refresh Now** button appears enabled for each resource that is not associated with a cache policy. If the resource is associated with a cache policy, however, the button will appear disabled.

## Defining Pre- and Post-Actions for a Full Refresh Mode Cache

When caching data, you might want to have actions take place before or after the cache data is refreshed. These pre- and post-actions are available for the automatic, single table, or multi-table caching modes.

For example, before the cache is refreshed you might want to send email notifications that the data is about to be refreshed. After the cache is refreshed, you might want to define or update the indexes associated with the data.

Within Studio, you can define procedures or scripts that have no input or output parameters to act as your pre- and post-actions. They can, however, call other procedures to execute subtasks within the pre-refresh or post-refresh operation.

The pre and post procedures can be a SQL script procedure or a custom Java procedure. They cannot be an XSLT transform or XQuery procedure.

### To define a pre- or post-refresh actions

1. Create a new SQL script or Java procedure using the instructions in [Java Procedures, page 195](#) or [Adding a Custom Java Procedure, page 163](#).

To use an existing SQL script or procedure locate the script or procedure within the Studio resource tree.

2. Make sure that the script or procedure does not have input or output parameters.
3. Evaluate the following TDV API calls for use in Studio under `<localhost>/lib/util`:
  - `GetEnvironment`—Can be used to return one or more of the system properties to your Pull-Based incremental caching SQL script
  - `GetProperty`—Can be used to return one or more of the system properties to your Pull-Based incremental caching custom Java procedure.

4. Review other functions under the lib directory to determine if they can help you achieve the action that you want for your pre- or post-action. Other functions of possible interest might include:
  - CreateResourceCacheKey is used to create a cache key for a given resource.
  - TestDataSourceConnection is used to test to see if a data source's connection is operational.
  - ClearResourceCache(path, type) is used to clear the cache on a resource.
  - UpdateResourceCacheKeyStatus(path, type, cacheKey, status, startTime, message) is used to update the cache key for the specified resource.
  - GetResourceCacheStatusProcedure is used with CreateResourceCacheKey and UpdateResourceCacheKeyStatus to support external cache loading. Returns Cache status information for a given cache key.
5. Save the script or procedure.
6. In Studio, open a view or procedure that has had caching enabled for which you want to assign pre- and or post-actions.
7. Select the Caching tab.
8. Under Advanced, choose Full Refresh Mode.
9. For the Pre-Refresh or Post-Refresh Action fields, or both, specify a procedure that exists in the Studio resource tree and has no parameters.
10. Save the cache settings. After cache settings are saved, each cached resource appears with a lightning-bolt icon in the Studio resource tree to show that the resource is cached.
11. If you have data type incompatibilities between your view and your data storage type, see “Cache Data Type Mapping” in the *TDV Reference Guide*.

## Setting Up Pull-Based Incremental Cache

Pull-based incremental caching can be set up using the TDV caching mechanism with two scripts. With pull-based incremental caching the user or client application must make a request for their copy of the cache to be synchronized with the centralized cache copy. Because you define the scripts used to create and refresh the cache, you can make the scripts as complicated or as simple as your situation requires. Your scripts can be defined using SQL or using custom Java procedures. The procedure must have logic to identify what rows have changed.

This topic covers the generalized steps for creating the scripts necessary for the pull-based method of defining incremental caching and provides the following sample scripts:

- [Pull-Based Incremental Cache Initialization Sample Script, page 458](#)
- [Pull-Based Incremental Cache Refreshing Sample Script, page 459](#)

### To set up pull-based incremental caching

1. Locate or create a reliable and unique identifier within your data source that you can use to determine how data has changed since the last cache refresh. This unique identifier could be a system change number, a log sequence number (LSN), or a TIMESTAMP. Typically the cachekey column can be used to determine what data has been updated.
2. Create a new SQL script or Java procedure using the instructions in [Java Procedures, page 195](#) or [Adding a Custom Java Procedure, page 163](#).

To use an existing SQL script or procedure locate the script or procedure within the Studio resource tree.

3. Make sure that the scripts or procedures for the cache have one VARCHAR output parameter.
4. Evaluate the following TDV API calls for use are in Studio under `<localhost>/lib/util`:
  - `GetEnvironment`—Can be used to return one or more of the system properties to your Pull-Based incremental caching SQL script
  - `GetProperty`—Can be used to return one or more of the system properties to your Pull-Based incremental caching custom Java procedure. Specifically, you can use it to acquire the server ID.

The system caching properties that can be interacted with include:

- `System.CACHED_RESOURCE_PATH`
- `System.CACHED_RESOURCE_TYPE`
- `System.CACHED_RESOURCE_PARAM_KEY`
- `System.CACHE_DATASOURCE_PATH.`
- `System.CACHED_RESOURCE_CACHE_KEY`
- `System.CACHED_RESOURCE_BUCKET_PATH.`
- `System.CACHED_RESOURCE_REFRESH_OUTCOME`
- `System.CACHED_RESOURCE_ERROR_MESSAGE`
- `System.CACHED_RESOURCE_INCREMENTAL_MAINTENANCE_LEVEL`

5. Review other functions under the lib directory to determine if they can help you achieve the action that you want for your pull-based incremental caching. Other functions of possible interest might include:
  - CreateResourceCacheKey() is called to generate a new cachekey value.
  - LoadResourceCacheStatus() is called to inform the server of the in-progress refresh.
  - LoadResourceCacheStatus() is called to inform the server of the newly active data.
  - TestDataSourceConnection is used to test to see if a data source's connection is operational.
  - ClearResourceCache(path, type) is used to clear the cache on a resource.
  - UpdateResourceCacheKeyStatus(path, type, cacheKey, status, startTime, message) is used to update the cache key for the specified resource.
  - GetResourceCacheStatusProcedure is used with CreateResourceCacheKey and UpdateResourceCacheKeyStatus to support external cache loading. Returns Cache status information for a given cache key.
6. Consider using some of the following logic to control caching logic:
  - The status table is queried to find the currently active cachekey. The cachekey is in the row with the server ID, resource path, and status column with value 'A'. The INSERT, UPDATE, and DELETE operations can be performed on the data table using the cachekey as a filter to avoid updating any other keys.
  - Perform INSERTs and other operations to create new rows in the storage table as appropriate, making sure all such rows have the new cachekey value. This should be performed on an independent transaction so it can be committed when done.
  - Perform INSERTs to the status table with the server ID, resource path, cachekey, the status set to 'I', and the starttime set to the current time to indicate an in-progress refresh. This should be performed on an independent transaction so it can be committed immediately.
  - UPDATE all rows in the status table with the server ID and resource path that have status 'A' to have status 'C'. This marks the previous active cache data for clearing. Then UPDATE the row into the status table with the serverID, resource path, and cachekey to set the status set to 'A' and finishtime to the current time. This will indicate that this cache key is the new active one. This should be performed on an independent transaction so it can be committed immediately.
7. Save the script or procedure.

8. In Studio, open a view or procedure that has had caching enabled for which you want to define Pull-Based incremental caching.

**Note:** If your cache objects were created prior to the current version of TDV, you might need to recreate them.

9. Select the **Caching** tab.
10. Under **Advanced**, choose **Incremental Refresh Mode** to enable incremental caching that can be refreshed on demand.

Incremental refresh caching only updates the client version of the caches when the client requests the update.

11. Specify values for the following fields:
  - Initialize the cache using—Specify a procedure or script that exists in the Studio resource tree and has one output parameter. This script will be used to create the initial cache.
  - Refresh the cache using—Specify a procedure or script that exists in the Studio resource tree and has one output parameter. The output parameter should be a of VARCHAR data type.
12. Save the cache settings. After cache settings are saved, each cached resource appears with a lightning-bolt icon in the Studio resource tree to show that the resource is cached.
13. If you have data type incompatibilities between your view and your data storage type, see “Cache Data Type Mapping” in the *TDV Reference Guide*.

### Pull-Based Incremental Cache Initialization Sample Script

The following sample script is used to create the cache table. It has one `IncrementalMaintenanceLevel` output parameter of type VARCHAR.

```
PROCEDURE InitalCache(OUT IncrementalMaintenanceLevel VARCHAR)
BEGIN
  DECLARE cacheKey BIGINT;
  DECLARE maxI BIGINT;

  /* 1. Retrieve cache key from request environment */
  CALL /lib/util/GetEnvironment('System.CACHED_RESOURCE_CACHE_KEY', cacheKey);
  CALL /lib/debug/Log('cachedResourceCacheKey = ' || cacheKey);

  /* 2. Determine initial snapshot level */
  SELECT {option no_data_cache} MAX(i) INTO maxI FROM
  /shared/INCREMENTAL_CACHING/INCR_CACHE_TEST;
  SET maxI = COALESCE(maxI, 0);

  /* 3. Load cache target table */
  INSERT INTO
  /shared/INCREMENTAL_CACHING/incr_cache_test_target
  SELECT {option disable_data_cache}
```

```

cacheKey, S.*
FROM
/shared/INCREMENTAL_CACHING/INCR_CACHE_TEST S
WHERE
i <= maxI;

/* 4. Return incremental maintenance level */
SET IncrementalMaintenanceLevel = CAST(maxI AS VARCHAR);
END

```

## Pull-Based Incremental Cache Refreshing Sample Script

The following sample script is used to request that a local copy of the cache be refreshed with the latest data from the cache table. It has one **IncrementalMaintenanceLevel** output parameter of type **VARCHAR**.

```

PROCEDURE DeltaLoader(OUT IncrementalMaintenanceLevel VARCHAR)
BEGIN
DECLARE cacheKey BIGINT;
DECLARE maxI BIGINT;

/* 1. Retrieve cache key from request environment */
CALL /lib/util/GetEnvironment('System.CACHED_RESOURCE_CACHE_KEY', cacheKey);
CALL /lib/debug/Log('cachedResourceCacheKey = ' || cacheKey);

/* 2. Retrieve incremental maintenance level from request environment */
CALL /lib/util/GetEnvironment('System.CACHED_RESOURCE_INCREMENTAL_MAINTENANCE_LEVEL',
IncrementalMaintenanceLevel);
CALL /lib/debug/Log('cachedResourceIncrementalCacheMaintenanceLevel = ' || IncrementalMaintenanceLevel);

/* 3. Determine next level */
SELECT {option no_data_cache} MAX(i) INTO maxI FROM
/shared/INCREMENTAL_CACHING/QA/db-lab-9/QAN/INCR_CACHE_TEST;
SET maxI = COALESCE(maxI, 0);

/* 4. Refresh cache target table */
INSERT INTO
/shared/INCREMENTAL_CACHING/QA/db-lab-9/QAN/incr_cache_test_target
SELECT {option disable_data_cache}
cacheKey, S.*
FROM
/shared/INCREMENTAL_CACHING/QA/db-lab-9/QAN/INCR_CACHE_TEST S
WHERE
i > CAST(IncrementalMaintenanceLevel AS BIGINT) AND i <= maxI;

/* 5. Update incremental maintenance level */
SET IncrementalMaintenanceLevel = CAST(maxI AS VARCHAR);
CALL /lib/debug/Log('IncrementalMaintenanceLevel for successful run of DeltaLoader script= ' ||
IncrementalMaintenanceLevel);

EXCEPTION
ELSE
--Log the exception
CALL /lib/debug/log('Exception raised in the delta loader script');
CALL /lib/debug/log('Exception is : ' || CURRENT_EXCEPTION.NAME || ' : ' ||
CURRENT_EXCEPTION.MESSAGE);

```

```

--Don't advance the incremental maintenance level on a failure
CALL /lib/util/GetEnvironment('System.CACHED_RESOURCE_INCREMENTAL_MAINTENANCE_LEVEL',
IncrementalMaintenanceLevel);
CALL /lib/debug/Log('IncrementalMaintenanceLevel after exception in DeltaLoader script= ' ||
IncrementalMaintenanceLevel);

END

```

## Setting Up Push-Based Incremental Caching for Oracle

Push-based incremental caching can help to achieve performance gains when using Oracle data sources. Data consumers can pull the latest data from incrementally maintained and synchronized caches that reduce impact on your transaction servers. Because this type of caching requires very specific set-up and configuration, it is described in [Push-Based Incremental Caching, page 575](#).

## Cache Maintenance

Over time your caching needs might change. This section details some of the common cache maintenance topics:

- [Indexing Your Cache, page 460](#)
- [Managing Configuration Changes and Cache Behavior, page 462](#)
- [Displaying the Dependencies of a Cached View, page 463](#)
- [Displaying the Dependencies of a Cache Policy, page 464](#)

## Indexing Your Cache

TDV provides several options for you to index your cached data. Indexing your data can improve performance when certain columns are commonly used for filtering and viewing a subset of the data from the cache. Adding an index can slow the performance of cache refreshes, but can improve the performance of cache result retrieval.

Depending on what cache options you have chosen to implement, different indexing options are available to you:

- For a full refresh type of cache, you can specify scripts to run before and after a cache refresh. You could include logic in each of those scripts to drop and/or create indexes on your cached data.
- For a full refresh cache that uses the multi-table option, you can configure TDV to index your cached data automatically with each refresh. This selection



requires that you provide indexing definitions on the Index tab for the table or view that you are caching.

- For pull-based incremental caching, you can add logic to the incremental caching scripts to define additional indexing behavior.
- For TDV caching options that don't directly support indexing, you can create indexes directly on your cached data using the database tools available for your specific cache target. This solution might also require that you consider what processes might be necessary to ensure that the indexes are still valid after a cache refresh occurs.

Indexing-specific columns in the result set of a cached view yields performance benefits. TDV also provides the ability for you to define a script or procedure that can be used to initiate or update and index on your cached data.

You can filter data going to the cache table using the cachekey column. Because the cachekey column is a unique value for a given cache snapshot, when you write custom scripts to index the cache data, we recommend that you make the cachekey the first column of the index. This is especially true if you have many procedure cache variants and commonly used queries do not return a large subset of rows.

### **To index your cache if full-refresh multi-table caching is enabled**

1. Refer to the instructions in:
  - [Creating a Multiple Table Cache on a Database Target, page 425](#)
2. Make sure that the Indexes tab has the index defined as you need.

For information using the Indexes tab, see [Use Indexes, and Primary and Foreign Keys, to Improve Query Performance, page 496](#).

### **To index your full refresh cache**

1. Refer to the instructions in the following topic:
  - [Defining Pre- and Post-Actions for a Full Refresh Mode Cache, page 454](#)
2. Add logic to manage and define the indexes.
3. Test your performance to ensure that performance goals are reached for cache indexes.

### **To index your pull-based incremental cache**

1. Refer to the instructions in the following topic:
  - [Setting Up Pull-Based Incremental Cache, page 455](#)

2. Add logic to manage and define the indexes.
3. Test your performance to ensure that performance goals are reached for cache indexes.

### **To index your cache data directly on the cache target**

1. Refer to the instructions in the following topic:
  - [Setting Up Caching, page 417](#)
2. Define the indexes using the database tools available for your cache target database type.
3. Determine what other scripts or process changes might be necessary to make sure that the index is still functional after a cache refresh.
4. Test your performance to ensure that performance goals are reached for cache indexes.

## **Managing Configuration Changes and Cache Behavior**

Most changes to the table, view, or procedure that you are caching, or changes to your cache data storage definitions, require that you reevaluate your cache configuration. Certain changes could result in missing cache data, which would result in temporary errors for any application attempting to access the data in the cache. Performing an explicit clear or refresh action following a configuration change is recommended.

The following configuration changes are managed automatically by Studio:

- If you rename an object that you are caching or any of its parent folders, your cached tables are updated.
- If you are using the automatic caching option, Studio drops the old files and creates any necessary new files automatically.


If you change any of the following, be sure to fully reevaluate your caching configuration:

- The storage data source type, physical location, name, number of columns, or the column data types.
- The cache status table physical location, name, or other metadata.
- The number of columns or a column data type definition for the view you are caching.
- The name or number of parameters for a procedure you are caching.

## Displaying the Dependencies of a Cached View

When you are working on a cached view, it is useful to know what resources are involved so you can understand the behavior of the view and the cache. The Lineage panel in Studio shows a resource's dependencies, references, and any associated cache policies. The Lineage panel is also available for cached views.

The Lineage panel displays the view's dependencies on its left and the resources that depend on it on its right. Cache tables are shown in green.



### To display the dependencies and references of a cached view

1. Use one of these methods to open the Lineage panel:

#### Method

Right-click a view that has caching enabled in the resource tree and select Open Lineage.

#### Description

The Lineage panel opens in the workspace to the right. It displays all the resources related to the view in a graphical format. Use this method if the view has lots of objects because the entire workspace is used to display the dependencies and references. This lineage display also allows you to easily navigate the related resources and saves the history of the navigation.

Method	Description
Open a view that has caching enabled and click the Open Lineage Panel toolbar button.	The Lineage panel opens in the lower pane of the view's editor and displays all the resources involved with this view in a graphical format.

- For more information on how to interact with the lineage graph editor, see [Working with the Data Lineage Graph, page 376](#).

## Displaying the Dependencies of a Cache Policy


When you are working on a cache policy, it is useful to know what resources are involved so you can understand the behavior of the cache refresh action. The Lineage panel in Studio shows a resource's dependencies, references, and other data points for the associated cache policy.

### To display the dependencies and references of a cache policy

- Open your cache policy.
- Select the Cache Policy Settings tab.
- Scroll to the Lineage section.
- Click Open Lineage.

The Lineage panel opens in the workspace to the right. It displays all the resources related to the view in a graphical format. Use this method if the view has lots of objects because the entire workspace is used to display the dependencies and references. This lineage display also allows you to easily navigate the related resources and saves the history of the navigation.

Cache tables and policies are shown in green.



5. For more information on how to interact with the lineage graph editor, see [Working with the Data Lineage Graph, page 376](#).

## Managing Import and Export Cache Information

Cache information can be exported and imported to Studio using the export and import windows in Studio or the `backup_export` and `backup_import` command-line syntax.

- [Exporting Your Cache Information, page 465](#)
- [Importing Your Cache Information, page 465](#)

### Exporting Your Cache Information

When exporting your cache information using either the UI or the `backup_export` method is fairly straightforward.

#### To export cache information

1. Identify all of the resources included in the caching environment that you want to export to a CAR file. For example, you might need to export a data source, a view, and one or more cache policies.
2. Export the various items using the Studio Export UI or the `backup_export` syntax.

### Importing Your Cache Information

When importing your cache information using either the UI or the `backup_import` method is fairly straightforward.

#### To import cache information

1. Identify the CAR file that you want to import.
2. Import the CAR using the Studio Import UI or the `backup_import` syntax.  
If your CAR file includes cache policies, import the CAR from the Studio Desktop directory level. Cache policies must be save and used from the `/policy/cache` Studio directory.
3. If necessary, rebind cache resources after importing the CAR.

## Caching Tips from an Expert

- [Destroying a File or Default Cache, page 466](#)
- [Managing Cache Status Table Probe Row Conflicts, page 466](#)
- [Managing Unresponsive Cache Tables, page 467](#)
- [Managing Open Connection Threads, page 468](#)
- [Managing Buckets, page 468](#)
- [Managing Cache Data, page 469](#)

### Destroying a File or Default Cache

Using the Studio Caching tab, there is a way to destroy the file cache or default PostgreSQL database cache. For other cache data sources in use, if the database server is forced to terminate due to a systems problem, then orphaned files could be left on disk.

For single and multi-table database caching, the actions described here will not drop the physical database tables.

#### To destroy a cache

1. Locate and open the resource for which you want to destroy the associated cache.
2. Select the Cache tab.
3. Clear the Enable check box and Save to disable the cache.
4. On the upper right corner of Caching tab, locate the Destroy Cache icon.
5. Click it and click Yes.

The file or tables specific to the resource that you selected are destroyed. However, the metadata associated with the files might continue to display in Studio.

### Managing Cache Status Table Probe Row Conflicts

On very rare occasions when there is a connection issue to the database where the cache\_status table is, the status of a cache refresh can remain in the Probe state. The cache process should only be in the Probe state for a very short period of time, but if there is a disconnect while in that state, the cache can be orphaned in that state until the TDV server is restarted.

TDV has a configuration parameter that can be used to eliminate this situation.

### **To manage caching conflicts**

1. Open the Studio Administration menu Configuration option.
2. Modify the value of the Wait Time For Probe Conflicts configuration parameter.

Adjust the value in seconds to wait for probe row conflicts if necessary. Minimum value is 10 seconds.

3. Save your changes.

## **Managing Unresponsive Cache Tables**

The startup of the TDV Server can be significantly slow if there is a problem when accessing your cache tables. This is caused because the TDV Server process reads all the cache status tables as part of the startup routine.

TDV has a configuration parameter that can be used to eliminate this situation. When it is set to a non-zero value the server attempts to connect to each cache database within the specified timeout (in milliseconds) before performing any further cache status or cache data maintenance.

### **To manage unresponsive cache tables for TDV Server restart**

1. Open the Studio Administration menu Configuration option.
2. Modify the milliseconds value of the Scan Cache Database Connection Timeout on Server Startup configuration parameter.

If set to a non-zero value the server attempts to connect to each cache database within the specified timeout (in milliseconds) before performing any further cache status or cache data maintenance.

Set to a value high enough to work well for your environment and network characteristics. Setting it too low renders caches unusable by TDV.

3. Save your changes.

The setting will take effect on the next server restart.

## Managing Open Connection Threads

The driver properties are used to specify connection timeout settings as required by the specific driver. By specifying the properties that are used by your specific data source, you can avoid situations where connections are left open indefinitely. This will prevent TDV threads from locking up on requests that need to establish a database connection.

Because each database has different connection properties, you will need to become familiar with them to determine which property to set and what values are appropriate for your environment.

### To manage the connection threads

1. Open the data source editor for the data source that has been identified as having connection threads that stay open too long.
2. Open the Advanced tab.
3. Edit the Connection Properties—JDBC Connection Properties to define connection timeout intervals that are appropriate for your environment.

## Managing Buckets

Occasionally when performing a cache refresh, you might encounter a situation where you receive a message stating:

All buckets for the cached resource are in use

Typically this message is displayed because there are several open client connections that are accessing the data in the cache buckets.

### To manage the buckets

1. Open Studio, and open the Studio Manager.
2. Open Sessions.
3. Determine if any client connections are accessing the view which is cached.
4. Determine which of the following options is best for your situation:
  - Wait for the client connections to finish before rerunning the cache refresh.
  - Increase the number of buckets to accommodate concurrency.
5. To modify the Number of Caching Tables defined for your cache, see [Enabling Caching to Multiple Tables, page 426](#).
6. Save any changes you have made.



7. Rerun the cache refresh.

## Managing Cache Data

Once a view or procedure's data is cached, it should be treated like a database table (unordered, unfiltered). When querying the cache table, if the results need to be ordered, a view should be created from the cached view or procedure to apply the ORDER BY. The ORDER BY clause is not preserved after caching. Cached data should be regarded as a materialized table, not as the view or procedure it was created from.



# TDV Configuration Parameters

---

Studio provides configuration parameters that allow modification of values and behavior. The Studio Configuration window provides access to configuration parameters. Default values configure TDV for a development environment where a moderate-size team prepares prototypes for test and later creates a production deployment.

- [Viewing or Editing Configuration Parameters, page 471](#)
- [Finding Parameters in the Configuration Window, page 473](#)

## Viewing or Editing Configuration Parameters

The Configuration window lets you view all of the configuration parameters for TDV.


Special characteristics of parameters are provided in their names or descriptions:

- Configuration parameters with (Current) in their names are read-only and exist only to display current settings.
- Configuration parameters with (On Server Restart) in their names change to your new values only when TDV is restarted.
- Some configuration parameters have descriptions that contain “This value is locally defined. It will not be altered when restoring a backup and will not be replicated in a cluster.” See the *Active Cluster Guide* for more information about replication in a cluster.

### To view or edit configuration parameters

1. For Viewing, make sure you have Access Tools and Read All Config rights. For editing, make sure you have Access Tools and Modify All Config rights.
2. Select Administration > Configuration from the Studio Modeler toolbar to open the Configuration window.

The left panel shows a list of folders indicated by a folder icon. You can expand the folders to view the resource tree of configuration parameters. The right panel displays properties for the currently selected parameter.



3. Click the **Expand All** button to display the full hierarchy of folders and parameters, or click the triangle to the left of a folder name to expand only that folder.

You can click the **Collapse All** button to return the display to the five top-level folders.

4. Select a parameter in the left pane to view its properties in the right pane.  
If the parameter value cannot be changed, its icon is dimmed.

Type	Possible Actions
Choice	Click the radio button indicating the opposite choice.
List	Click add button in the Value area to add a value to the list. Click delete button adjacent to a value to remove it.
Map	Click plus in the Value area to add a key-value pair: one field for a Key, the other field for a Key Value. Click delete button adjacent to a key-value pair to remove it.
Number	Type a new number.
Optional password	Type a password in the Password field and the identical password in the Confirm field. Click Apply or OK to make the password required. The Confirm field returns to blank for the user to type a matching password.
Required password	Type the required password in the Confirm field. The Password Value is a string of asterisks (*) representing the password that has been set.
Text	Type a new string of characters.

5. If you want to show only the parameters that have pending changes, check the second check box from the right under the Search button.  
The check box tooltip says Show only modified files.  
An asterisk (\*) is displayed between a parameter icon and its name if a new value is pending.
6. To apply none, some, or all of the pending changes, do one of the following.

To...	Do This...
Clear the pending change to the highlighted parameter.	Click Reset.
Clear all pending changes.	Click clear.
Apply all pending changes without closing the Configuration window.	Click Apply. The changes are no longer considered pending.
Apply all pending changes and close the Configuration window.	Click OK.
Close the Configuration window without applying any pending changes.	Click Cancel.

## Finding Parameters in the Configuration Window

The Configuration window contains a Find field and Search button to help you find parameters.



The image shows a search interface with a text input field labeled 'Find:' and a button labeled 'Search'.

The Configuration window also contains a parameter-type filter and a toolbar.

**Note:** See also [Viewing or Editing Configuration Parameters, page 471](#).

### To find a configuration parameter and its values

1. Select Administration > Configuration from the Studio Modeler toolbar to open the Configuration window.
2. Use one of the following methods to search for the parameter.

To...	Do This...
Display only parameters of a specific type.	Select that type from the Show Type drop-down list. The Show Type drop-down list is explained earlier in this topic.
Return to displaying all parameters.	Select All from the Show Type drop-down list.
Search by parameter <i>name</i> .	Type part or all of the name in the Find field and click Search.
Search by parameter <i>type</i> .	Select the parameter type from the Show Type drop-down list, or select All to show all types.
Search by parameter <i>value</i> or <i>description</i> .	Check the Search through descriptions instead of names check box.
Display only parameters that have pending changes	Check the Search Only Modified Parameters check box.
Display the full hierarchy of folders and parameters.	Click the Expand All button.
Display only the top-level configuration parameter folders.	Click the Collapse All button.
Display the folders and parameters immediately below a folder.	Click the triangle to the left of the folder, or double-click the folder name.

3. Highlight the parameter to view its properties in the right pane.
4. Click OK or Cancel to close the window.

# Performance Tuning

---

This topic describes ways to fine-tune query execution to enhance performance.

- [About Performance Tuning in TDV, page 475](#)
- [Working with the SQL Execution Plan, page 477](#)
- [Creating Cardinality Statistics for Cost-Based Optimization, page 489](#)
- [Using TDV API Procedures to Refresh or Cancel Resource Statistics, page 496](#)
- [Use Indexes, and Primary and Foreign Keys, to Improve Query Performance, page 496](#)
- [Types of Joins, page 497](#)
- [SQL Join Reordering, page 499](#)
- [Semijoin Optimization Option, page 503](#)
- [Star Schema Semijoin, page 510](#)
- [Using Oracle SQL Optimizer Hints, page 511](#)
- [Tuning Nested Aggregate Function Behavior, page 512](#)
- [Tuning Database Channel Queue Size, page 513](#)
- [Specifying the Fetch Size for Oracle and MS SQL Server, page 513](#)

## About Performance Tuning in TDV

You can tune TDV performance in several ways. Some performance tuning topics are covered in this topic, some elsewhere. The following table summarizes and links to the sections that describe performance tuning.

Tuning Tool	Summary	Topic Reference
Data caching	Saving local snapshots of data can improve the performance of some design tasks. Caching temporarily stores a copy of frequently accessed source data.	<ul style="list-style-type: none"> <li>• <a href="#">TDV Caching, page 391</a></li> </ul>

---

Tuning Tool	Summary	Topic Reference
Generating query execution plans	The execution plan shows how TDV Server plans to execute the SQL for a view. It can help you understand what you might do to enhance query performance.	<ul style="list-style-type: none"> <li>• <a href="#">Working with the SQL Execution Plan, page 477</a></li> <li>• <a href="#">Generating and Displaying a SQL Execution Plan, page 478</a></li> <li>• <a href="#">Execution Plan Nodes in the Tree Panel, page 479</a></li> <li>• <a href="#">Updating the Query Execution Plan, page 486</a></li> <li>• <a href="#">Viewing How Much Data was Processed by a Query, page 487</a></li> <li>• <a href="#">Refreshing All Execution Plan Caches, page 488</a></li> </ul>
Creating cardinality statistics	Cardinality statistics show the distribution of values in a table or view, and estimate the number of rows in the query result. This can help you improve the query plan.	<ul style="list-style-type: none"> <li>• <a href="#">Creating Cardinality Statistics for Cost-Based Optimization, page 489</a></li> <li>• <a href="#">Using TDV API Procedures to Refresh or Cancel Resource Statistics, page 496</a></li> </ul>
Defining indexes, and primary and foreign keys	An index, or a primary or foreign key, can make data easier to find.	<ul style="list-style-type: none"> <li>• <a href="#">Use Indexes, and Primary and Foreign Keys, to Improve Query Performance, page 496</a></li> </ul>
Using joins	Join strategies can significantly affect query performance.	<ul style="list-style-type: none"> <li>• <a href="#">Types of Joins, page 497</a></li> <li>• <a href="#">SQL Join Reordering, page 499</a></li> <li>• <a href="#">Semijoin Optimization Option, page 503</a></li> <li>• <a href="#">Star Schema Semijoin, page 510</a></li> </ul>
Using SQL hints	You can use these when the default behavior of the query optimizer does not result in the best query performance.	<ul style="list-style-type: none"> <li>• <a href="#">Using Oracle SQL Optimizer Hints, page 511</a></li> </ul>



Tuning Tool	Summary	Topic Reference
Using nested aggregates	If a data source does not support nested aggregates, you can improve performance by letting TDV know not to look for them.	<ul style="list-style-type: none"> <li>• <a href="#">Tuning Nested Aggregate Function Behavior, page 512</a></li> </ul>
Using data ship	Data ship optimization analyzes queries to determine if performance can be improved by temporarily transferring a small amount of data to a data source target.	<ul style="list-style-type: none"> <li>• <a href="#">Data Ship Performance Optimization, page 519</a></li> </ul>

## Working with the SQL Execution Plan

TDV provides ways for you to generate and evaluate the execution plans for SQL queries. The execution plan displays characteristics of the overall request, and of each request node, depending on which you highlight. The request hierarchy is displayed on the left (the Tree Panel), and the plan information is displayed on the right (the Details Panel).

When you execute a particular SQL query for the first time, the TDV Server caches the query execution plan so it can reuse it if you resubmit the query later.

Working with the SQL execution plan is described in these sections:

- [Generating and Displaying a SQL Execution Plan, page 478](#)
- [Execution Plan Nodes in the Tree Panel, page 479](#)
- [Execution Plan Query Attributes in the Details Panel, page 482](#)
- [Execution Plan Node Attributes in the Details Panel, page 484](#)
- [Updating the Query Execution Plan, page 486](#)
- [Viewing How Much Data was Processed by a Query, page 487](#)
- [Refreshing All Execution Plan Caches, page 488](#)

You can also explicitly gather and cache the statistics for a query, such as number of rows in each table. The execution plan helps the TDV Server make better decisions about how to process the query. However, if the statistics change, you should regenerate the query plan so TDV uses up-to-date information. See [Creating Cardinality Statistics for Cost-Based Optimization, page 489](#).

## Generating and Displaying a SQL Execution Plan

The SQL execution plan shows how TDV plans to execute a SQL query, both on the overall (request) level and on the level of each query node. Execution plan information can help you enhance query performance.

**Note:** Execution plan and query plan refer to the same thing.

You can display an execution plan in one of two ways:


- For the current query, you can show the execution plan in Studio Modeler.
- For any past query, you can show the query plan in Studio Manager.

By default, Studio opens in the Modeler, the top vertical tab on the left side of the Studio window. To open Studio Manager, click the middle vertical tab.

### To display the SQL execution plan in Studio Modeler

1. Open a query in Studio Modeler.
2. Click Show Execution Plan on the editor toolbar.

The following example shows the execution plan panels for CompositeView.



3. Highlight the view name in the Tree Panel to see details for the overall query in the Details Panel.
4. Highlight a node (SELECT, one of the JOINS, and so on in this example) in the Tree Panel to see details for that node in the Details Panel.

### To display the SQL execution plan in Studio Manager

1. Open Studio Manager by clicking the middle vertical tab along the left side of the Studio window.
2. Select Requests in the navigation pane on the left.
3. Select an SQL query from the list in the Name column.

When you select a query, the Cancel and Show Query Plan buttons become available.

You can expand the Name column to show the first 50 characters of each query text to help identify the query of interest.

4. Click Show Query Plan near the center of the window.

When you highlight a node in the tree panel on the left side, information is provided for that element as described in [Execution Plan Nodes in the Tree Panel, page 479](#).

## Execution Plan Nodes in the Tree Panel

The following table lists the nodes that can appear in the Tree Panel. This panel is displayed at the bottom left of the Studio pane when you click Show Execution Plan. The tree is a hierarchical representation of the query plan.

**Note:** These nodes are also listed in the logged execution plan.

When you select one of these nodes, you see a list of [Execution Plan Query Attributes in the Details Panel, page 482](#).

Node	Functionality
AGGREGATION	Shows plans for aggregate functions that are not part of a GROUP BY clause.
CROSS JOIN	Merges two streams of incoming rows and produces one stream of rows that is the Cartesian product of the two streams.

Node	Functionality
Pre Data Ship Plan	<p>Represents the query execution analysis prior to the shipment of one or multiple nodes to the data ship target. After a data ship is executed, each of the Pre Data Ship Plan nodes state:</p> <p>Execution Status: NOT EXECUTED. This operation was determined unnecessary or was cancelled before any rows were retrieved.</p> <p>The Pre Data Ship Plan nodes are not executed because the query is reworked to execute the operation on the data ship target.</p>
DISTINCT	Removes all incoming duplicate rows.
FETCH	<p>Produces the rows resulting from execution of a query on a data source. The information that can be displayed includes:</p> <ul style="list-style-type: none"> <li>• Estimated rows returned (or “Unknown”)</li> <li>• Data source path, type, and driver name</li> <li>• Data ship target, if data ship is being used</li> <li>• Data ship notes, if any</li> <li>• SQL of the fetch</li> <li>• SAP BW OLAP View runtime notes with estimated rows returned</li> </ul> <p>The FETCH node and the SQL submitted to the data ship target reveals how a query that uses data shipment is rewritten to select data that was shipped into a local temp table to make it available for a collocated operation compared to the operation that was evaluated in the Pre Data Ship Plan.</p>
FILTER	Passes through only the incoming rows that satisfy the filter criterion.
FULL OUTER JOIN	<p>Merges two streams of incoming rows and produces one stream containing the SQL FULL OUTER JOIN of the two streams.</p> <p>Refer to SQL reference materials for a description of FULL OUTER JOIN.</p>
FUNCTION	Shows how a function is executed.
GROUP BY	Reorders the incoming rows so that they are grouped by some criterion. For example, if the rows are grouped by a name, all rows with the same name are combined into a single row.
IN SUBQUERY	Lists a node for an unpushed IN subqueries.

Node	Functionality
JOIN	<p>Merges two streams of incoming rows and produces one stream containing rows that satisfy a criterion that applies to both streams. The information displayed includes:</p> <ul style="list-style-type: none"> <li>• Estimated rows returned (or “Unknown”)</li> <li>• Criterion applied</li> <li>• Algorithm used</li> <li>• Algorithm notes</li> <li>• Estimated left and right cardinality</li> </ul>
ORDER BY	Reorders the incoming rows to satisfy a sorting criterion.
PROCEDURE	<p>Produces rows resulting in the execution of a query or stored procedure call on a data source. The information displayed includes:</p> <ul style="list-style-type: none"> <li>• Estimated rows returned (or “Unknown”)</li> <li>• Location of the SQL statement</li> <li>• Reason for not pushing if that is the case</li> </ul>
RIGHT OUTER JOIN	<p>A right outer join performed as part of a stored procedure.</p> <p>Merges two streams of incoming rows and produces one stream containing the SQL right-outer-join of the two streams.</p> <p>Refer to SQL reference materials for a description of RIGHT OUTER JOIN.</p>
SELECT	<p>Applies functions on the column values of the rows. This node produces the same number of rows that it reads. The information displayed includes:</p> <ul style="list-style-type: none"> <li>• Estimated rows returned (or “Unknown”)</li> <li>• Projection of the SELECT statement</li> <li>• Data ship notes, if any</li> </ul>
UNION	Combines two streams of incoming rows and produces a single stream. The cardinality of produced rows equals the sum of the cardinality of the incoming streams. The order in which the node produces rows is undefined.
CROSS PROCEDURE JOIN	A cross-join performed as part of a stored procedure.

Node	Functionality
FULL OUTER PROCEDURE JOIN	A full outer join performed as part of a stored procedure.
FETCH WITH	Same as FETCH, but containing a specified condition.
UPDATE	Updates a data source, typically a table.
INSERT	Inserts data into a data source, typically a table.
DELETE	Deletes data from data source, typically a table.
MERGE	Merges data into a data source, typically a table. Merge inserts a row if it is not present, and updates a row if it already exists.
WITH SUBQUERIES	Subqueries that are part of WITH clauses.
INTERSECT	
EXCEPT	

## Execution Plan Query Attributes in the Details Panel

The following table lists attributes that can appear in the Details Panel when the overall query (request) is highlighted in the Tree Panel. This panel is displayed at the bottom right of the Studio Modeler pane when you click Show Execution Plan, or of the Studio Manager pane when you click Show Query Plan.

These attributes can also be found in the logged execution plan, although some of them are estimates *before* execution and actual run-time values *after* execution.

Field	Description
Background data source read time	Time spent by background threads in all <a href="#">FETCH, page 480</a> and <a href="#">PROCEDURE, page 481</a> nodes in the execution plan.
Background server processing time	Time spent by background threads in all the nodes (except for <a href="#">FETCH, page 480</a> and <a href="#">PROCEDURE, page 481</a> ) in the execution plan.
Data ship data transfer time	Time required to transfer data from one data source to another.

Field	Description
Elapsed execution time	Amount of wall-clock time that the server used to execute the query. This time is the total of <a href="#">Query initialization time, page 483</a> , <a href="#">Foreground server processing time, page 483</a> , and <a href="#">Foreground data source read time, page 485</a> .
Foreground server processing time	Fraction of the <a href="#">Elapsed execution time, page 483</a> that the server used in the actual execution of the query; that is, the processing time of the nodes in the execution plan. This time does not include the time used to read rows from the data sources. By comparing this time with <a href="#">Foreground data source read time, page 485</a> , you can determine how much time was spent by the server versus the time spent in the data sources.
Peak memory reserved	Peak memory reserved for current request.
Query initialization time	<p>Time the server used to analyze the query, create and optimize an execution plan, rewrite the query, and establish connections (from the pool if pooling is configured) to the data sources.</p> <p>If data ship is involved, time is spent creating a data ship temp table at the data ship target, and shipping the data. With multiple data shipments to multiple temp tables, these tasks are done in parallel by separate threads, and the shipped segment that takes the longest keeps the query initialization time clock running.</p>
Reset count	
Resolved SQL	Fully resolved SQL text.
Rows modified	Number of rows modified by the request.
Rows returned	Number of rows produced by an execution node. If you want to know how many rows were read by the node, look at the returned row counts of the node's children.
Server version	Version of the server software.
Speed up due to concurrency	Estimate of how much faster the query ran because of threading. For example, 100% means the query ran twice as fast with threading.
Submitted SQL	Original SQL text.

## Execution Plan Node Attributes in the Details Panel

The following table lists attributes that can appear in the Details Panel. This panel is displayed at the bottom right of the Studio Modeler pane when you click Show Execution Plan, or of the Studio Manager pane when you click Show Query Plan. When you select a node in the Tree Panel on the left, its attributes are displayed.

The following table lists attributes that can appear in the Details Panel when a node is highlighted in the Tree Panel. This panel is displayed at the bottom right of the Studio Modeler pane when you click Show Execution Plan, or of the Studio Manager pane when you click Show Query Plan.

**Note:** See [Execution Plan Nodes in the Tree Panel](#), page 479, for a list of nodes.

These attributes can also be found in the logged execution plan, although some of them are estimates *before* execution and actual run-time values *after* execution.

Field	Description
Algorithm	Name of the algorithm used by the node; for example HASH JOIN or SORT/MERGE JOIN.
Algorithm notes	More details about the algorithm used.
Background data source read time	For SCAN or PROCEDURE: how much time the child thread spent on reading from the data source.
Background node processing time	For nodes other than SCAN, PROCEDURE, INSERT, UPDATE, DELETE, or MERGE: time spent processing this node by a background thread. This time is zero if the node was processed by a <b>foreground</b> thread.
Base DN	For SCAN.
Candidate keys	For SELECT.
Connection ID	For SCAN.
Criteria	Shows the criteria used by a JOIN, FILTER, GROUP BY, or ORDER BY node. Condition or predicate applied during an operation
Data ship notes	For SCAN or SELECT. A report of the estimated number of rows to be shipped, and the amount of time consumed to get the cost estimate. When a condition blocks the use of data ship, this field usually describes the condition, case, or option that blocked optimization.
Data ship SQL	For SCAN.



Field	Description
Data ship target	For SCAN. Shows where the results of SQL execution will be sent. The presence of Data ship target indicates that data ship will be performed.
Data ship transfer time	For SCAN.
Data source driver name	For SCAN or PROCEDURE.
Data source path	For SCAN or PROCEDURE.
Data source type	For SCAN or PROCEDURE.
Data source write time	For INSERT, UPDATE, DELETE or MERGE.
Estimated left cardinality	Estimated cardinality for the left input in a binary join. Pre-execution (Show Execution Plan button) Details Panel only
Estimated right cardinality	Estimated cardinality for the right input in a binary join. Pre-execution (Show Execution Plan button) Details Panel only
Estimated rows returned	Pre-execution (Show Execution Plan button) Details Panel only. Logged execution plan records actual Rows Returned.
Execution status	If the operation for the node is still running, status can be PARTIAL RESULTS or NOT EXECUTED.
Fetch rows	For SELECT.
Foreground data source read time	For SCAN or PROCEDURE. Fraction of the <a href="#">Elapsed execution time, page 483</a> that the main thread used to read data from the data sources. By comparing this time with <a href="#">Foreground server processing time, page 483</a> , you can determine how much time was spent by the server vs. the time spent in the data sources.
Foreground node processing time	For nodes other than SCAN, PROCEDURE, INSERT, UPDATE, DELETE, or MERGE: fraction of the elapsed time used by the node. This time is zero if the node was processed by a background thread.
Name	
No push reason	Why the node was not pushed to the data source.
Offset rows	For SELECT.

Field	Description
Peak memory reserved	Peak memory reserved for current node.
Peak memory used	Peak memory used for current node.
Procedure join number of invokes	For PROCEDURE.
Procedure type	For PROCEDURE.
Projection	Set of output columns in a SELECT node.
Rows deleted	
Rows inserted	
Rows merged	
Rows returned	
Rows updated	
Runtime notes	
Semi-join criteria	For SCAN.
Semi-join partition count	For SCAN.
SQL	SQL text executed by the node. In a <a href="#">FETCH, page 480</a> or <a href="#">PROCEDURE, page 481</a> node, this field contains the actual data-source-specific query that was pushed.
UniqueIndex	For SELECT.

## Updating the Query Execution Plan

An execution plan is generated the first time a SQL statement is executed, and whenever the query changes. The query execution plan is cached, so if the underlying data or statistics change, it is a good idea to regenerate the execution plan as described below.

A simple way to force a refresh of an execution plan is to add a space to the query. You can also flush the query plan cache for all views by temporarily toggling the Query Plan Cache Enabled key in the TDV Configuration window as described in [Refreshing All Execution Plan Caches, page 488](#).

### To update the query execution plan

1. If statistics have changed on the view, gather statistics as described in [Creating Cardinality Statistics for a View, page 490](#).
2. Regenerate the execution plan using one of these methods:
  - Click Show Execution Plan on the view editor toolbar. (For an OLAP View editor, the button is on the toolbar of the SQL tab.

Or

  - In the Execution Plan panel, click Generate Plan.
3. Optionally, type a value in the Refresh Rate field, to specify a regular interval at which to update the execution plan.

## Viewing How Much Data was Processed by a Query

You can execute a query and determine how much data was processed by each node, and which nodes took the most time in the query execution plan.

Query plans in SQL that call procedures in FROM clauses show the details of what the procedures do (in the PROCEDURE nodes) when you direct the tool to execute and show the statistics.

If Keep Result is selected, the results of the query execution are available in a new Result tab. The data in the tab is available for as long as you keep the resource open in Studio. The query execution ID appears both at the top of the Execution Plan nodes in the left pane and in the Result tab name to help you match statistics and query information to results.

### To view how much data was processed by a node

1. Generate an execution plan.
2. In the Execution Plan panel, select a node in the left pane.
3. Optionally, select Keep Result in the lower right corner of the Execution Plan to view the results of this query in a separate tab.
4. Click Execute and Show Statistics.

Statistics are added to the nodes in the left pane of the Execution Plan.

Each node name is followed by values in parentheses like  $(n)$  or  $(n, m\%)$ , where  $n$  is the number of rows produced by that node, and  $m$  is the percentage of elapsed time that the node used to process the data. If  $m$  is not shown, it is 0.

For example, if the elapsed time was 60 seconds and  $m$  is 20, the node accounted for 12 seconds of the elapsed time ( $20 \times 60$ ). If  $m$  is 0, processing at the node did not contribute to elapsed time—for example, if the node was processed by a background thread and its processing was completed before the rows were needed by the parent node. The  $m$  percentages help determine which nodes to focus on to improve performance.

5. Optionally, set a refresh rate for the execution plan.
6. Optionally, click Refresh Now during the execution of the query.

This updates the statistics being gathered on data sources and tables, which can take a long time for long-running queries.

### For Example

Name:

SELECT

Rows Returned:

220

Estimated Rows Returned:

Unknown

Total execute time which include children time and wait time.:

121.4 msec

Foreground Node Processing Time:

2.5 msec

Peak memory reserved:

4000000

Projection:

orderdetails0.orderid OrderID, orderdetails0.productid ProductID, orderdetails0.discount Discount, orders.orderdate OrderDate, customers.companyname CompanyName, customers.contactfirstname CustomerContactFirstName, customers.contactlastname CustomerContactLastName, customers.phonenumber CustomerContactPhone, productCatalog\_xform.ProductName ProductName, inventorytransactions.transactionid TransactionID, purchaseorders.daterequired DateRequired, purchaseorders.datepromised DatePromised, purchaseorders.shipdate ShipDate, suppliers.supplierid SupplierID, suppliers.suppliername SupplierName, suppliers.contactname SupplierContactName, suppliers.phonenumber SupplierPhoneNumber

Data Ship Notes:

Data Ship Query is not possible. No suitable source scan or ship-to target found.

## Refreshing All Execution Plan Caches

TDV Server caches view-query execution plans. If the view SQL uses data sources with fresh cardinality statistics, you might want to purge and refresh the query plan cache by temporarily changing the Query Plan Cache configuration setting, which forces a one-time regeneration of all execution plans.

### To purge all query execution plans

1. Select the Administration > Configuration menu option.
2. In the Configuration window, select TDV Server > SQL Engine > Caches > Query Plan Cache Enabled.
3. In the right pane, select the False radio button and click Apply.
4. Select the True radio button, click Apply, and click OK.

Or

Refresh a query plan cache by making a minor change to the View SQL or procedure. This forces creation of a new query execution plan.

5. Save the change.

The next execution uses any cardinality statistics available to optimize query plan execution.

## Creating Cardinality Statistics for Cost-Based Optimization

The TDV SQL Query Engine might use statistics gathered from the data sources, when they are available, to create an efficient SQL query execution plan for joins or unions across tables, or to optimize caching. Statistics gathered on tables or views provide the SQL Query Engine with estimates on the table cardinality (the number of unique values or rows) so that optimizations can be applied.

By default, no statistics are gathered for any data source, and statistics storage tables must be created explicitly at the level of the data source to enable selected table and column scans.

Statistical data associated with a data source can be exported and imported with the data source, or you can just back up the configurations.

Any user with Access Tools and Modify All Resources rights, and with READ and WRITE privileges on a data source, can set up the gathering of cardinality statistics on the data source and one or more of its tables.

This section includes:

- [Creating Cardinality Statistics for a View, page 490](#)
- [Creating Cardinality Statistics on a Data Source, page 492](#)

You can consult the system data tables (/services/databases/system/SYS\_STATISTICS) to see the status and the metadata (if you have the Read All Resources right) from both the data source and individual tables.

## Creating Cardinality Statistics for a View

If you intend to use the view for caching, you can collect cardinality statistics for it.

**Note:** You must set up the cache before you define the cardinality statistics gathering profile. See [Setting Up Caching, page 417](#) for more information.

For the TDV parallel option, you must gather statistics for the column that is the numeric simple key for the view. This column should be either the one identified as the primary key column by the execution plan, or the primary key that you have defined using the Indexes tab.

### To collect cardinality statistics for a view

1. From the resource tree, open the view for which you want to collect cardinality statistics.
2. Select the Caching tab.
3. Click Create Cache.

For more information on creating a cache, see [Caching to a File Target, page 420](#).

4. If required by Studio, define the Cardinality Statistics for the data source. For more information, see [Creating Cardinality Statistics on a Data Source, page 492](#).
5. Select the Cardinality Statistics tab for the view.
6. Click Create Statistics.
7. Check Enable to allow use of the gathered table statistics to optimize execution plans.

You do not need to check the Enable check box to *configure* statistics gathering, but you do need to check that box for the optimizer to *use* the statistics. To disable statistics gathering and use of existing statistics, clear the Enable check box and save.

8. Optionally, define cardinality override settings:
  - Minimum Cardinality—The minimum number of returned rows you would expect from a SQL SELECT on this table. Zero (0) is a valid number.
  - Maximum Cardinality—The maximum number of rows the resource could return.
  - Expected Cardinality—Typical number of unique rows returned from this table.

9. Specify the schedule for collecting cardinality statistics: On Cache Refresh or Manual. You can use the Gather Now button at any time.
10. Optional. Set the Statistics Gathering Timeout value.

When the table statistics gathering timeout is set to “-1” the data source statistics gathering timeout is used. A value of 0 (the default) indicates that there is no time limit.

If the statistics processing is already returning data from a full table scan, the timeout setting does not stop processing immediately; instead, the timeout triggers an attempt to make statistical estimates based on the subset of data already returned.

11. Specify your table statistics gathering preferences:
  - None—Do not gather statistics for the table.
  - Use datasource settings—Gather statistics according to the definitions specified for this data source.
  - Gather table boundary statistics—Performs `SELECT COUNT (*)` on each specified table to count its rows.
  - Specify gathering for specific columns—Control statistics gathering column by column.
12. Optionally, select the Specify gathering for specific columns option and then specify column gathering rules and manipulate the values for MIN, MAX, and distinct.
  - a. In the Gathering Rule column, double-click to select one of the first two options in the table below to gather statistics.

Gathering Rule Option	Choose to...
Gather all statistics	Collects all other statistics plus a full table scan of numeric data types to build a histogram. Or, builds a full string index for string data types.  BLOB, CLOB and other data types that yield meaningless statistical data is not configurable for statistical evaluation.
Gather boundary statistics	Collect table boundary statistics and gather minimum and maximum, and count distinct values for numeric data types. For string data types, calculate the number of distinct values for tables with fewer than ten thousand rows.  To reduce the cost of gathering statistics for column boundaries, apply one or more assumptions.
Do not gather statistics	Stop gathering statistics on the column (default).

- b. Use one or more of the following fields to override and avoid processing of statistics in the database.

This can be a valuable way to avoid gathering column boundary statistics and have TDV use the values you specify when the queries are run.

When TDV gathers statistics, it retrieves all data from the source and builds a histogram and string index based on this data. This operation can be expensive, depending on the number of rows and columns, network bandwidth, and so on. If you have limited time for statistics gathering, overriding the values can be useful.

These column values are used to create a uniform distribution at run time for the evaluation of the selections. If a value is specified for a column, statistics are not gathered for that column.

- Minimum Value—An option to override the minimum value for the column.
- Maximum Value—An option to override the maximum value for the column.
- Distinct Count—An option to override the number of distinct values for the column.
- Num of Buckets—An option to increase or decrease the granularity of the statistics.

13. Save your selections.

## Creating Cardinality Statistics on a Data Source

Statistics gathering must be enabled on the parent data source. You create statistics from the Cardinality Statistics tab, which is available for any data source.

**Note:** The data source sign-in and password must be saved to enable statistics gathering.

### To collect statistics on a data source

1. From the resource tree, open a data source.
2. Select the Cardinality Statistics tab.
3. Click Create Statistics.
4. Check Enable to allow use of the table statistics gathered to optimize execution plans.

You do not need to check the Enable check box to configure statistics gathering, but you need to check that box for the optimizer to use the



statistics. To disable statistics gathering and use of existing statistics, clear the Enable check box and save.

5. For Mode, select one of the following:
  - Do not gather statistics—The default setting for all data sources and tables.
  - Gather table boundary statistics—Counts the number of rows in tables, performing a `SELECT COUNT (*)` on each of the specified tables.
  - Gather column boundary statistics—Gets table boundary statistics and gathers the minimum and maximum, and counts distinct values for numeric data types. For string data types, calculates the number of distinct values for tables with fewer than ten thousand rows. The cost of gathering statistics for the column boundary statistics is reduced by application of one or more assumptions.
  - Gather all statistics—Collects all the above, plus a full table scan of numeric data types, to build a histogram. For string data types, also builds a string index.

6. Optionally, set the Number of Threads.

Number of Threads specifies the number of low-priority, query-executing threads allowed on the database and on TDV.

**Note:** Some databases do not tolerate large numbers of threads scanning tables at the same time. TDV also has a thread capacity limit that can cause disk paging when nearing memory thresholds. You can specify a maximum number of threads (without needing a server restart) by selecting Administration > Configuration, and in that window navigating to Server > SQL Engine > Optimizations and setting Max Number of Statistics Gathering Threads In The System to whatever value works in your environment.

7. Set the statistics gathering schedule:
  - Manual—Use Gather Now to gather statistics right away. If your cache is controlled by a cache policy, it is probably better to use a periodic or programmatic refresh.
  - Exactly Once—Requires that you set a day and time in the future to run.
  - Periodic—Statistical collection occurs at timed intervals, such as at an off-peak hour each night.

Frequency of statistics gathering also depends on data volatility. Some tables never change and others change frequently. Gather statistics based on the expected frequency of cardinality and table boundary change.

It is best to use off-peak hours for gathering data source statistics, a process that can use significant resources. You can use multiple threads for data sources that support parallel processing.

8. In the Time-out in minutes field, specify the number of minutes permitted for gathering data from a resource.

A value of 0 or null (the default) indicates that there is no time limit.

If the timeout expires after statistics processing is already returning data, the timeout triggers an attempt to make statistical estimates from the subset of data already returned.

9. Save your selections.
10. Define cardinality statistics gathering option for the table or view that you are interested in by following the steps in [Creating Cardinality Statistics for a View, page 490](#).

TDV supports the NTILE analytical function, which can be run for a given data source to compute statistics. TDV uses this function to generate histograms, capturing the distribution of the values of a given column, within the data source instead of pulling all the data within the TDV server to compute the histograms.

By default NTILE-based statistics collection is disabled. You can enable it by setting the property Disable NTILE-based Statistics Collection to False. This option can be accessed via Server > Configuration > Debugging > Statistics.

Refer to [NTILE, page 90](#) in the *Reference Guide* for the syntax and usage of this analytical function.

## Scheduling Cardinality Statistics Refresh

You can schedule statistics gathering to happen at the best time for you. Use the following procedure, or refer to the steps in [Using TDV API Procedures to Refresh or Cancel Resource Statistics, page 496](#).

### To schedule refreshes of the cardinality statistics

1. Follow the instructions in [Creating Cardinality Statistics for a View, page 490](#) or [Creating Cardinality Statistics on a Data Source, page 492](#).
2. Set the statistics gathering schedules for one of the following:
  - Manual—Use Gather Now for immediate collection of statistics. If your cache is controlled by a cache policy, use a periodic or programmatic refresh.
  - Exactly Once—Requires that you set a day and time in the future to run.
  - Periodic—Statistics collection occurs at timed intervals, such as at an off-peak hour each night.

Frequency of statistics gathering also depends on data volatility. Some tables never change and others change frequently. Gather statistics based on the expected frequency of cardinality and table boundary change.

It is best to use off-peak hours for gathering data source statistics. You can use multiple threads for data sources that support parallel processing.

3. Use the Stats Gathering Timeout field to specify the number of minutes permitted for gathering data from a resource.

A value of 0 (zero; the default) indicates that there is no time limit.

If the timeout expires when statistics gathering is already returning data, the timeout triggers an attempt to make statistical estimates from the subset of data already returned.

4. Save your selections.

## Refreshing Cardinality Statistics

You can schedule statistics gathering and refreshing for a time that is best for you. You can use the following procedure, or refer to the steps in [Using TDV API Procedures to Refresh or Cancel Resource Statistics](#), page 496.

### To refresh cardinality statistics

1. Follow the instruction in [Creating Cardinality Statistics for a View](#), page 490 or [Creating Cardinality Statistics on a Data Source](#), page 492.
2. Set the statistics gathering schedules for one of the following:
  - Manual—Use Gather Now to begin collecting statistics immediately. If your cache is controlled by a cache policy, use a periodic or programmatic refresh.
  - Exactly Once—Requires that you set a day and time in the future to run.
  - Periodic—Statistics collection occurs at timed intervals, such as at an off-peak hour each night.

Frequency of statistics gathering also depends on data volatility. Some tables never change and others change frequently. Gather statistics based on the expected frequency of changes to cardinality or table boundaries.

It is best to use off-peak hours for gathering data source statistics and to use multiple threads for data sources that support them.

3. Use the Stats Gathering Timeout field to specify the number of minutes permitted for gathering data from a resource.

A value of 0 (zero; the default) indicates that there is no time limit.

If the timeout expires but statistics processing is already returning data, the timeout triggers an attempt to make statistical estimates from the subset of data already returned.

4. Save your selections.

## Using TDV API Procedures to Refresh or Cancel Resource Statistics

The following built-in procedures are available for using resource statistics:

- localhost/lib/resource/RefreshResourceStatistics
- localhost/lib/resource/CancelResourceStatistics
- services/databases/system/SYS\_STATISTICS

### To view a detailed procedure description

1. Double-click the procedure to open it.
2. Click the Info tab to display the procedure annotation.

## Use Indexes, and Primary and Foreign Keys, to Improve Query Performance

Indexes can speed up searching or retrieving data from a database table. Identifying indexes and primary keys enable the TDV Query Engine to use logical algorithms for faster, more efficient joins.

Typically, when an index is created for a column, all data in that column is scanned and a data structure (index) is constructed; the index makes the data in that column faster to lookup, although indexing also can slow transactions that insert rows into the tables. The contents of the index are automatically updated whenever the data in a row are modified.

In Studio, the Indexes panel in the view and table editor lets you create metadata labels for indexes and primary keys already present in the data source. In Studio, the Foreign Keys panel in the view and table editor lets you create a definition that uses any foreign keys present in the data source.

TDV does not build a specified data structure, but creates a metadata definition that lets you take advantage of the existing resource's data structure. Queries and joins do not necessarily run faster because of an index. The metadata index and key specifications are not validated, so there is no guarantee that a column marked as a primary key has unique values.

Clients of the TDV Server can benefit from knowledge of indexes and primary keys feature because this information is made available when the data service is published. More sophisticated client programs can generate efficient queries based on column indexes and primary keys.

In some cases, TDV cannot automatically determine what columns of a view are indexed. For example, a column might be a primary key in the base table. But in the view, the value might not qualify as a primary key.

For information on how to create an index for a table or view in Studio, see [Defining Primary Key for a View or Table in the Indexes Panel, page 156](#).

## Types of Joins

Inner and outer joins can use an equality condition (equijoins) or not (non-equi-joins). Most table joins are equi-joins, comparing columns and rows with like values. The nested loop algorithm is used for non-equi-joins.

The following table lists algorithms used and the types of joins that they can be used with.

Algorithm	Inner equi-join	Non-equi-join	Left/right outer join	Full outer join	Semijoin optimization
Hash	yes		yes	yes	yes
Nested Loop	yes	yes	yes	yes	yes
Sort Merge	yes		yes		

TDV uses several algorithms to execute joins on table columns. By default, the TDV query engine attempts to find the best algorithm and join optimization to use for your SQL if none is specified. The Join Properties editor offers the following join algorithm options:

- [Automatic Option, page 498](#)
- [Hash Join Option, page 498](#)
- [NESTEDLOOP Join Option, page 498](#)

- [SORTMERGE Join Option, page 499](#)
- [Semijoin Optimization Option, page 503](#)
- [Star Schema Semijoin, page 510](#)

## Automatic Option

By default, the TDV system automatically optimizes the SQL execution plans for any query, given estimates of left and right cardinality and other statistical information. Automatic is not a join algorithm or a join optimization, but it lets the TDV query engine optimize based on an analysis of the SQL using known database statistics.

You can specify the SQL execution plan explicitly with one of the other options; however, specification of a join option only influences what join algorithm or optimization is first attempted, not necessarily the one ultimately used. If the option specification is incompatible with the data sources or incorrectly specified, the execution plan might change to a compatible join that was not specified.

## Hash Join Option

The HASH algorithm is useful when you are joining tables with large amounts of data. The optimizer uses the inner table to build a hash table on the join key in memory. It then scans the outer table, probing the hash table to find the joined rows.

The HASH algorithm requires only a single pass on each table. It is best used when the inner table fits into available memory.

However, if the hash table does not fit into available memory, the optimizer breaks it into partitions that are written to temporary segments on disk.

If the process is expected to write to disk, you can use the `FORCE_DISK` query hint (described in the *TDV Reference Guide*) to make the process write to disk from the beginning, saving read/write cycles and excessive memory usage.

## NESTEDLOOP Join Option

You can use the NESTEDLOOP algorithm without any data structure information, but it is not inherently optimized for performance. NESTEDLOOP is useful when small subsets of data are joined and the join condition is an efficient way to access the right table.

When the outer (driving) table has numerous rows that force multiple probes of the inner table, the NESTEDLOOP algorithm becomes costly to run.

## SORTMERGE Join Option

The SORTMERGE algorithm is a streaming operator. If both input streams can be ordered given the join criteria and compatibility, the join operator works efficiently and quickly in a small memory footprint.

SORTMERGE can also impose other requirements, such as both sides of the join being ordered. To meet that requirement, ordering must be compatible with the join criteria. For example, consider the following join criteria:

```
ON T1.A = T2.X AND T1.B = T2.Y
```

To perform the SORTMERGE join, the left side has to be put into ascending order by A and B, and the right side has to be put into ascending order by X and Y.

If a side is not ordered or does not have compatible ordering, the query engine automatically checks whether a compatible ORDER BY can be pushed to the data source so that the SORTMERGE join can proceed.

SORTMERGE is not compatible with the SQL when ORDER BY cannot be pushed to the data sources. Ordering must be performed on both sides for a SORTMERGE join.

To prevent the query engine from choosing SORTMERGE over HASH, specify the value of the SORTMERGE option as false, as follows:

```
{option SORTMERGE="false"}
```

## SQL Join Reordering

TDV automatically assesses SQL Join blocks (inner joins and all types of outer joins) to determine suitability for rewriting the SQL join order. A Join block is a set of contiguous joins. The TDV query engine analyzes each join block of the query independently, and attempts to rewrite the query to maximize the number of joins pushed down to data sources. While inner joins can be reassociated without restriction, the TDV query optimizer checks a number of technical rules to determine if it is safe to reorder a block that contains outer joins.

For queries that meet complex criteria, TDV rewrites the SQL join order if it expects that to yield a performance gain. Joins are reordered so that tables from the same data source are performed first, which maximizes push down and makes the query more efficient.

The following examples show how SQL join ordering works.

```
SELECT O10BIN_ID, O100BIN_ID, O1KBIN_ID
FROM /users/composite/test/sources/oracleA/QABIN/O10BIN RIGHT OUTER JOIN
     /users/composite/test/sources/oracle/QABIN/O100BIN
ON O10BIN_NUMBER1 = O100BIN_NUMBER1 INNER JOIN
     /users/composite/test/sources/oracle/QABIN/O1KBIN
ON O100BIN_FLOAT = O1KBIN_FLOAT
```

The query as written would perform first the outer join and then the inner join, because by default joins are left-associative. The plan for this query looks like this:

```
[1] Request #2511
[2] + SELECT (13)
[3] + JOIN (13)
[4] + RIGHT OUTER JOIN (100)
[5] | + FETCH (10) [Oracle2]
[6] | + FETCH (100) [Oracle]
[7] + FETCH (1000) [Oracle ]
```

The numbers in parentheses represent number of rows produced by each operator. The annotations in square brackets are data source names.

The same query could be rewritten like this:

```
SELECT O10BIN_ID, O100BIN_ID, O1KBIN_ID
FROM /users/composite/test/sources/oracle2/QABIN/O10BIN RIGHT OUTER JOIN
      (/users/composite/test/sources/oracle/QABIN/O100BIN INNER JOIN
        /users/composite/test/sources/oracle/QABIN/O1KBIN
       ON O100BIN_FLOAT = O1KBIN_FLOAT)
ON O10BIN_NUMBER1 = O100BIN_NUMBER1
```

The join between the two tables from the same data source is performed first, and the optimizer is able to push down this join to the data sources. The corresponding query plan looks like this:

```
[1] Request #2533
[2] + SELECT (13)
[3] + RIGHT OUTER JOIN (13, 9%)
[4] + FETCH (10, 36%) [Oracle 2]
[5] + FETCH (13, 59%) [Oracle]
```

TDV has to perform only one join. Most of the data is filtered out at the data source, reducing data transfer. TDV performs automatically rewrites join blocks that include inner joins and all types of outer joins.

A join block is a set of contiguous joins. The query engine analyzes each join block of the query independently and attempts to rewrite the query to maximize the number of joins pushed down to data sources. While inner joins can be reassociated without restriction, the optimizer checks a number of technical rules to determine if it is safe to reorder a block that contain outer joins. Cross-joins are not eligible for reordering. Join reordering is not performed if it introduces new cross joins. A join node with hints is not considered for reordering.

A precondition of the join ordering algorithm is that all outer joins can be simplified. Here is an example:

```
SELECT O10BIN_ID, O100BIN_ID, O1KBIN_ID
FROM /users/composite/test/sources/oracle2/QABIN/O10BIN LEFT OUTER JOIN
      /users/composite/test/sources/oracle/QABIN/O100BIN
ON O10BIN_NUMBER1 = O100BIN_NUMBER1 INNER {OPTION SEMIJOIN} JOIN
      /users/composite/test/sources/oracle/QABIN/O1KBIN
```



```
ON O100BIN_FLOAT = OIKBIN_FLOAT
```

The left outer join can be converted to an inner join because the inner join above it has a null-rejecting predicate that applies to the null-filled side of the outer join. The ON clause of the top join rejects any rows produced by the left outer join that have NULL for the O100BIN\_FLOAT column.

The plan for this query looks like this:

```
[1] Request #3040
[2] + SELECT (2)
[3] + JOIN (2)
[4] + JOIN (1)
[5] |+ FETCH (10) [Oracle2]
[6] |+ FETCH (89) [Oracle]
[7] + FETCH (2) [Oracle]
```

This shows that left outer join was converted to inner join but that join reordering did not take place because the join hint implies that the inner join (in the input query) cannot be reordered.

TDV performs the SQL join reordering analysis automatically. Special configurations or SQL options are needed only if you want to enforce SQL processing as it is written because you want table construction or table relationships.

You can join the tables in any order you want. (See [Views and Table Resources, page 133](#).)

### Enforce Join Ordering

You can direct the query engine to follow the order in which you joined the tables. For information on how to specify joins, see [Views and Table Resources, page 133](#).

## Multiple Join Conditions

If the source side has many rows and produces a prohibitively long SQL string on the target side, the TDV query engine deals with it in one of these ways:

- **Partitioned semijoin**—The TDV query engine breaks up the target-side predicate into multiple chunks, and submit one query for each chunk to the target side. This technique applies regardless of whether the ON clause uses conjunctions or is just a single predicate, and regardless of whether the target side SQL is using the IN clause or OR syntax. The partitioned semijoin is also applied to semijoin queries with non-equality conditions.

- Query predicate rewriting—If a join has conjunctions in the ON clause and the target-side data source does not support the row-constructor form of the IN clause, then instead of generating a target side row-constructor form using an IN clause like:

```
(t1,t2) IN ((1,2), (6,3), (8,4),(93,3)...)
```

The TDV Server might generate a predicate with two or more scalar IN clauses like this:

```
t1 IN (1,6,8,93") and t2 IN (2,3,4,3,...).
```

The scalar IN clauses syntax is more compact than the OR syntax, and it reduces the chance of partitioned semijoin and load on the target data source. However, this predicate is not as selective as the OR form, so it could bring more rows into TDV. Because of this trade-off, you can configure the number of rows on the source side that causes the engine to switch from the OR syntax to multiple scalar IN clause syntax.

Consider this more complicated example:

```
SELECT * from DS1.R LEFT OUTER JOIN DS2.T on R.r1 = T.t1 and R.r2 = T.t2
```

In this case, the TDV Server query engine might generate an additional predicate (the row-constructor form of the IN clause) on the T-side that takes the form:

```
(t1,t2) IN ((1,2), (6,3), (8,4), (93,3)...)
```

If the DS2 target supports this form of IN clause query phrasing, it is preferred.

If the data source does not support this form of IN clause, the additional predicate looks like this:

```
(t1=1 and t2=2) or (t1=6 and t2=3) or (t1=8 and t2=4) or ...)
```

The second form is logically identical to the IN-clause form, but if the right side produces many rows, it could generate a long SQL string on the target side, potentially exceeding the capabilities of DS2.

- Pushing left outer joins with multiple predicates—If the query engine can predetermine what is selectable based on an ON clause and a WHERE clause, it pushes the query to the data source. For example:

```
SELECT
O10_Id
O10_CHAR
S_Id
S_CHAR
FROM /users/eg/t1 left outer { option semijoin="false", hash } join /users/sqlsr/5kk
ON O10_Id = S_Id
WHERE O10_Id = 9
```

Here, the WHERE clause predicate is the same as the ON clause predicate, so `O10_Id = 9` can be pushed to the data source, which can dramatically reduce the amount of data returned.

## Semijoin Optimization Option

A semijoin between two tables returns rows from the first table whenever one or more matches are found in the second table. The difference between a semijoin and a conventional join is that rows in the first table are returned at most only once, even if the second table contains two matches for a row in the first table.

This section contains:

- [About the Semijoin Optimization, page 503](#)
- [Semijoin Option Syntax Examples, page 505](#)
- [Setting Semijoin Configuration Parameters, page 505](#)
- [Configuring Your Data Source for the Semijoin Optimization, page 507](#)
- [Using the Semijoin Option, page 508](#)
- [Semijoin with Non-Equality Conditions Scenarios, page 509](#)

### About the Semijoin Optimization


The semijoin optimization reduces the number of rows retrieved from the right-hand side (RHS) by rewriting the FETCH pushed to the second data source using the unique values returned by the left-hand side (LHS). Table cardinalities must be supplied for this optimization.

Inner joins can use the semijoin optimization. Left and right outer joins can use semijoin optimization, but only from the outer side to the inner side. The full outer join is not supported with the semijoin optimization.

You can specify use of the semijoin optimization in the SQL defining the view. When the table cardinalities of source and target sides are known, and when the ratio between the two is favorable, the TDV query engine automatically uses the semijoin optimization.

The semijoin can only be attempted if the right side can be queried as a node that fetches against a data source that supports an IN or an OR clause.

For inner and left outer joins, the semijoin optimization always uses rows from the LHS to constrain the RHS—for example, where LHS is the source side and RHS is the target. For a right outer join the situation is reversed: RHS is the source and LHS is the target.



As another example, consider the tables Employee and Dept and their semijoin.

Employee Name	Empld	DeptName
Harry	3415	Finance
Sally	2241	Sales
George	3401	Finance
Harriet	2202	Production

Dept DeptName	Manager
Sales	Bob
Sales	Thomas
Production	Katie
Production	Mark

The semijoin of the employee and department tables would result in the

Employee joined to Dept Name	Empld	DeptName
Sally	2241	Sales
Harriet	2202	Production

following table.

Consider another query like this:

```
SELECT * FROM DS1.R INNER JOIN DS2.T ON R.r = T.t
```

The usual evaluation would hash the R table expression and then iterate over T table expressions, and do look-ups into the hash table to find matching rows. If the join in the example is such that the number of rows from the R-side is much smaller than the number of rows from the T-side, additional optimization is possible. The rows from R are buffered in TDV, but an additional predicate of the form “t IN (1,6,8,93...)” is added to the SQL generated for the RHS. The values on RHS of the IN clause are all the ‘r’ values from LHS of the join. This additional predicate ensures that TDV retrieves the smallest possible number of rows from the T-side to perform the join.

## Semijoin Option Syntax Examples

Query option hints can be written into the SQL of the query to suggest that the TDV query engine use a semijoin in the query. For example:

```
SELECT column1 FROM table1 INNER {OPTION SEMIJOIN} JOIN table2 ON table1.id = table2.id
```

A query hint, enclosed in curly braces immediately precedes the JOIN keyword.

The default value of OPTION SEMIJOIN is True, so the value of semijoin does not have to be explicitly set. You can also specify something more specific like:

```
... INNER {OPTION SEMIJOIN, PARTITION_SIZE=20} JOIN ...
```

This option forces the semijoin to be partitioned, with each partition having no more than 20 elements.

## Setting Semijoin Configuration Parameters

These server configuration parameters control what the TDV query engine considers a query that can benefit from semijoin optimization.

The cardinality of both sides of a potential semijoin are evaluated, and the side with smaller estimated cardinality is loaded into memory as the LHS. When the cardinality is small enough, one IN clause or an OR expression is created containing all the values in the join criteria from the LHS, which is then added to the SQL sent to the RHS.

Semijoin is limited for databases whose vendors restrict how large a SQL statement or IN/OR clause can be. If the cardinality exceeds specific data source limitations on the size of the IN clause or the OR expression, the query engine creates an execution plan that attempts a partitioned semijoin. The partition breaks the IN list into chunks of 100 or fewer unique values, and multiple queries are executed against the RHS source. If the cardinality is still too large, the system uses the HASH algorithm.

Another restriction is set to keep the LHS from inordinately burdening the join. You can configure the LHS cardinality to determine the row count that trigger an automatic semijoin.

For example, if Max Source Side Cardinality Estimate is 200 and Ratio is 10, a query where source cardinality is estimated at 50 and target at 600 triggers use of the semijoin automatically; a query with source estimate 100 and target estimate 900 does not.

If the TDV query engine can estimate the source side but not the target side, it assumes that the target-side cardinality is large and sets up a semijoin using the value of Max Source Side Cardinality Estimate.

### To set the semijoin parameters using Studio

1. Open the Studio Administration menu Configuration option.
2. Modify the values for the following semijoin server configuration parameters as appropriate.

Parameter	Description
Max Source Side Cardinality Estimate	Put an upper bound on the size of the predicate generated by the source side. If the cardinality estimate is greater than this setting, the TDV query engine does not automatically choose a semijoin.
Min Ratio of Target Cardinality to Source Cardinality	Derive a minimum cardinality of the target to trigger automatic semijoin. For example, if the estimate for the source side is 50 and the ratio is set to 12, the target side must be estimated to be at least 600 rows to trigger use of the semijoin optimization. If the cardinality of the target is not specified, the target cardinality is assumed to be very large.

3. Save your changes.

- Restart the TDV Server.

## Configuring Your Data Source for the Semijoin Optimization

The settings on the Advanced tab for a data source help the query engine determine when to use semijoin optimization.

Consider this example:

```
SELECT * FROM DS1.R INNER {OPTION SEMIJOIN} JOIN DS2.S ON R.r1 = S.s1 AND R.r2=S.s2.
```

Ideally the TDV query engine generates a predicate in the WHERE clause against DS2 that looks like this:

```
(s1, s2) IN ((2,3),(1,5), ...)
```

This is called the row constructor form of IN clause.

If the targeted data source (**DS2** in this example) does not support this type of SQL, the TDV query engine has two options:

- Use the **OR** syntax form and generate a query predicate that looks like the following:

```
(s1=2 and s2=3) or (s1=1 and s2 = 5) or ...)
```

- Use multiple scalar **IN** clauses syntax to generate a query predicate that looks like:

```
s1 IN (2,1, ...) and s2 IN(3, 5,...)
```

The OR syntax is semantically identical to the row-constructor syntax.

The multiple scalar IN clauses syntax is not as selective, and it can result in more rows being brought into the TDV Server for further local processing. The longer the SQL string, the more likely an execution plan has to run a partitioned semijoin. Run multiple statements to retrieve all the data.

### To configure your data source for the semijoin optimization

- Open the data source.
- Open the Configuration tab.
- Select the Advanced tab.

4. Scroll down to set the following parameters.

Field	Description
Max Source Side Cardinality Estimate	Change the number of LHS rows that triggers an automatic semijoin. If the left side cardinality is less than this value, and the product of this value and the Min Ratio of Target Cardinality to Source Cardinality (next row of this table) is less than the estimated RHS cardinality, the TDV query engine attempts to rewrite the query execution plan to use the semijoin optimization.
Min Ratio of Target Cardinality to Source Cardinality	Sets a minimum ratio of RHS to LHS to trigger use of semijoin optimization.

5. Save your settings.

## Using the Semijoin Option

### To define the semijoin in your SQL

1. Gather cardinality statistics on the tables that are part of the semijoin.  
The statistics are used for the execution plan.
2. Include the `LEFT_CARDINALITY` query hint and its value.

The query optimizer uses the hint to choose a better query plan. For example:

```
SELECT column1 FROM table1 INNER {OPTION LEFT_CARDINALITY=10}
JOIN table2 ON table1.id = table2.id
```

If the query optimizer knows that LHS cardinality is small enough compared to RHS, it attempts a semijoin.

If LHS cardinality is less than the value of Max Source Side Cardinality Estimate, and the product of LHS cardinality and the value of Min Ratio of Target Cardinality to Source Cardinality is less than the estimated RHS cardinality, the TDV query engine attempts to rewrite the query execution plan to use the semijoin optimization.

3. Define the `RIGHT_CARDINALITY` query hint and its value.

The optimizer uses the hint to choose a better query plan. Specifically, it is used when checking LHS cardinality against the minimum ratio set in Min Ratio of Target Cardinality to Source Cardinality.

```
SELECT column1 FROM table1 INNER {OPTION RIGHT_CARDINALITY=10000}
JOIN table2 ON table1.id = table2.id
```



If the RHS cardinality of a table is not known or not specified, the TDV query analyzer assumes that it is large, and determines whether to use semijoin according to the specified cardinality of the LHS.

4. If statistics have not been collected on the data source, optionally use Studio to specify the minimum, maximum, and expected cardinalities.

## Semijoin with Non-Equality Conditions Scenarios

Semijoin optimization can also apply to joins that use non-equality conditions (non-equi-joins).

Ideally, full statistics and cardinalities have been gathered on the tables, or predicate cardinality has been specified explicitly by query option in the view SQL. The semijoin can be used when tables are joined on an equality or non-equality condition. Non-equality semijoin optimizations require that table cardinality be specified; otherwise, the query is forced to use a less than optimum merge strategy.

For example:

```
SELECT * from DS1.R LEFT OUTER JOIN DS2.T on r1 > t1 and r1 <= t2
```

The target side predicate always uses the OR form, and looks like this:


```
(1 > t1 and 1 <= t2) OR (6 > t1 and 6 <= t2) ...)
```

The semijoin target is always the immediate child of the join.

In some cases the target is not the immediate child of the join. For example:

```
SELECT * from DS1.R INNER JOIN DS2.S INNER JOIN DS3.T on s1=t1 on r2=s2
```

The topology for this query example looks like this:



Two semijoins are possible. J2 can have S as source and T as target, and J1 can have R as source and S as target. Both joins can use the semijoin optimization at the same time. The definition of source and target of a semijoin needs to be refined.


For an inner join or a left outer join with semijoin, the immediate LHS child of the join is the source, and the target is a FETCH against a data source found in the RHS sub-tree of the join. The ON clauses that define table connections determine the specific FETCH node target. For right outer join, the definition is the reverse.

A join with a semijoin optimization can have more than one target. For example:  
`SELECT * from DS1.D1 INNER JOIN DS2.F INNER JOIN DS1.D2 on ds1=f1 on ds2=ds1`

The join with D1 as source can target both F and D2. Because multiple nodes target DS1, this join can be evaluated as a star schema semijoin.

## Star Schema Semijoin

A star schema semijoin is like a query with multiple joins. Consider this query topology.



Here the ON clauses of the joins are such that both D1 and D2 are connected to F, and both joins are inner joins. In this case two semijoins are possible—one from D1 to F and the other from D2 to F—because they both target the same data source.

If the data source is sufficiently robust, the data source can be marked in TDV Server so that the query engine is aware that the data source supports star schema semijoin optimization for multiple join nodes. In Studio, the Info > Advanced tab of the data source configuration pane has a Supports Star Schema property.

When the Supports Star Schema check box is enabled, the TDV query engine is made aware that both joins can be run using the semijoin optimization.

The reason this needs to be explicitly enabled is that even one semijoin with a large source side can place a significant burden on the target data source, and if several joins target the same data source at the same time the burden can overwhelm some data sources. It is easier for star schema semijoin to generate SQL strings that exceed the capabilities of the target data source. Thus this setting is useful when the target data source is very powerful or when all source sides are fairly small.

If the SQL sent to the target side in a star schema query exceeds the maximum length of SQL for the data source, the engine runs with a partitioned semijoin if possible, or it disables semijoin optimization for some of the joins.

The partitioned semijoin might not always apply to a star schema semijoin. If there are  $n$  joins targeting F and all but one of them generate a short IN clause but one generates a long IN clause, the query engine can still partition the long side of the semijoin. If all the joins produce IN clauses of approximately equal size partitioning might not be useful. In this case, the TDV query engine disables the semijoin optimization for the join that generates the longest SQL string. It continues to disable semijoin optimization until the total SQL for all remaining joins is within the capabilities of the target data source or partitioning becomes an option.

Because of the star schema semijoin, at most one of the predicates can be partitioned. If the query specifies more than one join with the `partition_size` option, at most only one of these requests can be satisfied.

For information about settings, see [Setting Semijoin Configuration Parameters, page 505](#).

You can override settings for specific data sources.

Data-source overrides apply when a given data source is the target of a semijoin. Typically these values are set conservatively at the server level, and overridden if necessary for specific data sources.

The target data source has the burden of processing the potentially large predicates generated by a semijoin, and the target data source must impose limits on how big the query predicate from the source side can be.

## Using Oracle SQL Optimizer Hints

Query performance can sometimes be improved by adding Oracle optimizer hints. If you decide a query hint is necessary, you can use TDV to add the hint to the query syntax; the hint is passed to the database for processing at runtime. The query must be against an Oracle database. The hint syntax must be valid for the version of Oracle that you are using.


No validation is done by TDV or Oracle on the hint syntax. TDV does not guarantee that the query hint will be pushed, because plan optimization may cause the hint to be dropped. Use the Show Execution Plan button to check whether the hint was pushed or not.

For more information about Oracle optimizer hints, see the *Oracle Database Performance Tuning Guide*.

### To add an Oracle optimizer hint to a query retrieving data from an Oracle data source

1. Locate a view in your TDV project that accesses data from an Oracle data source.
2. Select the SQL tab.
3. Enter in the Oracle hint syntax immediately following the SELECT statement.

For example:



```

SELECT
  /*+ LEADING (e2 e1) USE_NL (e1) INDEX (e1 emp_emp_id_pk)
     USE_MERGE (j) FULL (j) */
  e1.first_name, e1.last_name, j.job_id, sum(e2.salary) total_sal
FROM /shared/"Oracle Apps"/APPS/employees e1, /shared/"Oracle Apps"/APPS/employees e2,
     /shared/"Oracle Apps"/APPS/job_history j
WHERE e1.employee_id = e2.manager_id
      AND e1.employee_id = j.employee_id
      AND e1.hire_date = j.start_date
GROUP BY e1.first_name, e1.last_name, j.job_id
ORDER BY total_sal;

```

View is newly created and has not been saved. 2.4

\*SQL Columns Indexes Foreign Keys Caching Cardinality Statistics Info

4. Save the view.
5. Execute the view to test that the query performs as expected.

## Tuning Nested Aggregate Function Behavior

Several data sources support nested aggregate functions, but some do not. Meanwhile, checking for these functions can significantly slow performance. You can use a TDV configuration parameter to decide whether or not to check SQL queries for nested aggregate functions.

For example, Netezza does not support nested aggregate functions, so you can improve performance by setting the Check if nested aggregates is supported by datasource to False for queries pushed to a Netezza data source.

A nested aggregate function looks like this:

```
SELECT AVG(MAX(salary)) FROM employees GROUP BY department_id;
```

**To look for nested aggregate functions in SQL**

1. Open and log into Studio.
2. From the Administration menu, choose Configuration.
3. Navigate to and select Check if nested aggregates is supported by datasource.
4. Select True.

**Tuning Database Channel Queue Size**

The DB channel queue size is a setting that specifies the number of buffers within the TDV Server for a client request to prefetch from the database. By default this value is set to 0. If set to 1, the TDV Server can prefetch from the database and put it in a buffer to store it while the TDV JDBC driver is still fetching data from the TDV Server. When the TDV JDBC client asks for the next batch, it is already available in the buffer.

Value	Description of Behavior
1	Data is prefetched and stored in a buffer.
0	Data is only fetched when the client requests it.

**To tune database channel queue size**

1. Open and log into Studio.
2. From the Administration menu, choose Configuration.
3. Navigate to Server > Client Drivers > Performance.
4. Select DbChannel Queue Size.
5. Specify 0 or 1.

**Specifying the Fetch Size for Oracle and MS SQL Server**

You can control the amount of data fetched in each batch of rows retrieved from an Oracle or MS SQL Server data source. In the data source capabilities file, the `fetch_size` attribute controls the number of rows that are being fetched from the data source on every `ResultSet.next` call.

Adjusting `fetch_size` is optional and for performance tuning only. Be sure to test the effects of these adjustments to see if performance improves. If the configured value of `fetch_size` is zero or negative, the default value for the driver is used.

**Note:** A fetch size that is too small can degrade performance.

### To change the batch fetch size for Oracle or MS SQL Server

1. Locate the directory containing data source capabilities files which is:

```
<TDV_install_dir>\conf\adapters\system\
```

2. Using a text editor like Notepad, open the capabilities file in the directory for your data source:

```
microsoft_sql_server_2008_values.xml
```

```
oracle_11g_oci_driver_values.xml
```

```
oracle_11g_thin_driver_values.xml
```

3. Uncomment the `fetch_size` attribute and set its value. For example:

```
<ns5:attribute xmlns:ns5="http://www.compositesw.com/services/system/util/common">
```

```
<ns5:name>/runtime/iud/fetchSize</ns5:name>
```

```
<ns5:type>INTEGER</ns5:type>
```

```
<ns5:value>12345</ns5:value>
```

```
<ns5:configID>jdbc.fetch_size</ns5:configID>
```

```
</ns5:attribute>
```

4. Save the capabilities file.

# TDV Query Engine Optimizations

---

TDV includes many configuration parameters that can be manipulated to optimize how the server processes the queries that you execute through TDV. With many of these optimizations, TDV does the work to detect how it can best process your SQL. Query engine options let the developer influence the generation of the execution plan by overriding, for specific SQL statements and keywords, TDV configuration settings. The configuration settings can be found in Studio by selecting Administration > Configuration from the main menu and navigating to the parameters under TDV Server > SQL Engine.

Execution of SQL views, procedures, and transactions created with TDV-defined resources follows an optimized execution plan. The execution plan is generated dynamically based on how the SQL is written, what and how native resources are being used, TDV configuration settings, the presence of data-source-specific statistical data, and the presence of TDV SQL query engine options.

- [Subquery Optimizations, page 515](#)
- [Partition or Join Pruning Optimization, page 516](#)
- [DATA\\_SHIP\\_MODE Values, page 517](#)
- [Performance Configuration Parameter Tips from an Expert, page 517](#)

## Subquery Optimizations

TDV can analyze your subqueries and rewrite them as joins, if they meet the requirements for this subquery optimization. Often better performance can be achieved with joins as opposed to correlated subqueries.

### Requirements

- Subquery starts with IN or =.
- Subquery starts with '=' and includes an aggregation.
- The subquery can contain only one selectable of type COLUMN, LITERAL, FUNCTION, or AGGREGATE FUNCTION.
- The subquery can include SELECT, DISTINCT, AGGREGATE, FROM, RELATION and WHERE.
- Co-relation in the subquery can occur only in the WHERE clause for this feature. If co-relation occurs anywhere else, rewrite to join won't happen.

- Subquery operator of type SELECT, DISTINCT, AGGREGATE, FROM and WHERE clause. Or a sub-query contains a WHERE clause with a co-related predicate with a HAVING clause.
- Only co-related predicates is supported for the subquery WHERE clause.
- The co-related columns in the queries must come directly from the parent. Columns from a grandparent level are not supported.
- Type mismatches disqualify the subquery for rewriting.

### To enable the subquery optimization

1. In Studio, navigate to Administration > Configuration.
2. Expand Server > SQL Engine > Optimizations.
3. Locate the Rewrite IN Sub-Queries as Joins configuration parameter.
4. Validate or change the value to true.
5. Locate the Use Semi-Join While Rewriting IN Sub-Queries as Joins configuration parameter.
6. Review the value of the configuration parameter and determine if you want to change it.
7. Leave the value or make a change.
8. Select Apply or OK.

The change in the parameter takes effect immediately. All queries that begin processing after the configuration parameter change are analyzed to see if they can take advantage of the optimization. There is no need to restart the server.

## Partition or Join Pruning Optimization

Sometimes, for partitioned data, you want to run a query against a specific partition. This behavior is often referred to as join pruning. TDV has been set to perform this for you automatically. If you want to manipulate or confirm the settings, you can use the TDV configuration parameters that are accessed through Studio.

### Requirements

- Null values are not allowed in the tables for join pruning consideration.



### To review the join pruning optimization

1. In Studio, navigate to Administration > Configuration.
2. Expand Server > SQL Engine > Optimizations.
3. Locate the Disable Join Pruner configuration parameter.
4. Validate or change the value.
5. Select Apply or OK.

The change in the parameter takes effect immediately. All queries that begin processing after the configuration parameter change are analyzed to see if they can take advantage of the optimization. There is no need to restart the server.

## DATA\_SHIP\_MODE Values

DATA\_SHIP\_MODE is a SELECT option that controls automatic rework of federated queries across data sources. Reworked table selections can be shipped through an API to temporary tables so that query nodes can be joined with local tables.

DATA\_SHIP\_MODE modifies how the query engine handles queries that are candidates for data ship optimization.

For more information, see [Defining TDV Data Ship Configuration Parameters](#), page 526.

## Performance Configuration Parameter Tips from an Expert

When using several of the TDV performance enhancement features, such as caching and the data ship options, some of the values for the configuration parameters can create a conflict. In particular, pay attention to:

Configuration Parameter	Description
DBChannel Prefetch Optimization	Improves the performance for read/write operations. By default, this parameter is set to TRUE.
DBChannel Queue Size	Allows you to tune the number of buckets. By default, this parameter is set to 0. The appropriate starting value is 10.

Configuration Parameter	Description
DBChannel Flood Optimization	Setting the Flood Optimization option to True, will enable the Flood protocol to be used in client communications if requested by the client. The default value is True.  <b>Note:</b> It will not be necessary to restart server if this value changed.

---

**Note:** If the combination of DBChannel Prefetch Optimization set to TRUE and DBChannel Queue Size set to 1 exists in your environment, new sessions fail to be created after many sessions and requests terminate due to an exception. This is because only 1 prefetch bucket is created. Restarting the TDV may temporarily clear the issue, but it is best to adjust the values of the configuration parameters. Examine your DBChannel Queue Size setting and increase it as appropriate.

# Data Ship Performance Optimization

---

The data ship optimization analyzes your queries to determine if performance gains can be realized. By temporarily transferring a small amount of data to a data source target, the native data source query optimizations can be used to significantly improve performance.

- [About Data Ship, page 520](#)
- [Data Ship Support and Requirements, page 521](#)
- [Data Ship Limitations, page 524](#)
- [Defining TDV Data Ship Configuration Parameters, page 526](#)
- [Configuring Data Ship, page 529](#)
  - [Configuring Data Ship for DB2, page 530](#)
  - [Configuring Data Ship Bulk Loading Option for DB2, page 531](#)
  - [Configuring Data Ship for Microsoft SQL Server, page 533](#)
  - [Configuring Data Ship for Netezza, page 535](#)
  - [Configuring Data Ship for Oracle, page 536](#)
  - [Configuring Data Ship for Sybase IQ, page 537](#)
  - [Configuring Data Ship for Sybase IQ Targets with Location, page 540](#)
  - [Configuring Data Ship for PostgreSQL and Vertica, page 540](#)
- [Finishing Data Ship Configuration for Data Sources, page 540](#)
- [Evaluating Queries for Data Ship Using Execution Plans, page 545](#)
- [Using Time Series Functions for Vertica Data Ship Targets, page 546](#)
- [Disabling Data Ship for Specific Query SQL, page 548](#)
- [Managing Open Connection Threads, page 548](#)
- [Using Data Ship for Prepared Statements, page 549](#)


## About Data Ship

The data ship optimization accomplishes efficient federated query execution by transformation of federated queries into locally executed SQL operations. When SQL operations involve a very large table (with millions or hundreds of thousands of rows) and a small table with significantly fewer rows, the TDV Server can enhance query performance by shipping a copy of the smaller table to the data source of the larger table. This optimization can yield significantly faster results than a traditional federated query.

The following SQL operators can take advantage of the data ship optimization:

- JOIN
- UNION
- INTERSECT
- EXCEPT

When data ship optimization is enabled the TDV query engine evaluates a query, which can include explicitly defined query option hints, with all relevant data source statistics gathered on query dependencies to determine whether using the data ship optimization yields best performance. If data ship optimization can yield faster execution times according to the analysis and settings, an execution of the query sends data source specific instructions to move copies of tables (or results sets from an execution) from the database with the smaller table to a temporary table on the target data source. Processing of the query occurs on the data source with the larger source table. Because the two sides of the federated query reside on a single data source, processing efficiencies yield a faster return of the result set.



When a query is submitted to TDV, TDV evaluates the query and produces an execution plan without using the data ship optimization. This plan is a pre-data ship plan. TDV goes on to examine the fetch nodes of this plan and decides whether to use the data ship optimization. The data ship optimization is used if:

- The data sources corresponding to fetch node supports data ship.
- Data ship is not disabled for the query using query hints.
- Data source is configured as data ship source or target.

Among all the nodes involved, TDV dedicates one node as the target and all others as sources. TDV creates temp tables in the target data source and moves data from other nodes into this temp table. An alternate query plan is generated that transfers the federated SQL operation of a prior plan to the targeted data source.

Determining the target node is based on the:

- Data source corresponding to the fetch node is configured as source or target.
- Cost of retrieving the data with in the lower and upper bound set for data ship.

## Data Ship Support and Requirements

The data ship optimization feature requires that at least one data source participating in a join, union, intersect, or except in an eligible SQL execution be configured to act as a target for the data ship, and that at least one other data source participating in the data ship act as the data ship source. The data ship source and the data ship target can be the same type of database or of different database types. For example, you can configure data ship to have an Oracle data ship source and an Oracle data ship target, or you can configure data ship to have an Oracle data ship source and a Teradata data ship target.

**Note:** Netezza and DB2 assume that if they are used as a data ship target that they can also be the data ship source, therefore if TDV determines that by reversing the direction of the data ship that better performance can be achieved, it will do so regardless of what you may have defined.

Data ship optimization is supported for following data source types.

Data Source Type	Data Ship Source Support	Data Ship Target Support	Performance Option	Notes
DB2 v10.5	Active	Active	Bulk Load using the LOAD utility	LUW
Greenplum 3.3	Active	Active		
Greenplum 4.1	Active	Active		
Greenplum 4.3	Active	Active		
Microsoft SQL Server 2008	Active	Active	Bulk import/export using BCP	
Microsoft SQL Server 2012	Active	Active	Bulk import/export using BCP	
Microsoft SQL Server 2014	Active	Active	Bulk import/export using BCP	
Microsoft SQL Server 2016	Active	Active	Bulk import/export using BCP	
Microsoft SQL Server 2019	Active	Active	Bulk import/export using BCP	
Netezza 6.0	Active	Active	external tables	
Netezza 7.0	Active	Active	external tables	

Data Source Type	Data Ship Source Support	Data Ship Target Support	Performance Option	Notes
Oracle 11g	Active	Active	Database Links	<p>To use an Oracle data source for data ship, the DBA must install the DBMS_XPLAN package in the database and create an area for temporary tables.</p> <p>For this data source to participate in data ship, it must be specified as a data ship source. Participation as a data ship target is optional. If Oracle is both source and target, DB Link needs to be set up between the Oracle databases.</p>
Oracle 12c	Active	Active	Database Links	
Oracle 19c	Active	Active	Database Links	
PostgreSQL 9.1	Active	Active	Database Links	
PostgreSQL 9.2.3	Active	Active	Database Links	
Sybase IQ 15	Active	Active	Location: iAnywhere JDBC driver	<p>For a Sybase IQ data source to participate in data ship, the QUERY_PLAN_TEXT_ACCESS database option must be set to ON.</p> <p>For this data source to participate in data ship, it must be specified as a data ship source. Participation as a data ship target is optional.</p>

Data Source Type	Data Ship Source Support	Data Ship Target Support	Performance Option	Notes
Teradata 13.00	Active	Active	FastLoad/ FastExport	<p>For this data source to participate in data ship, it must be specified as a data ship source. Participation as a data ship target is optional.</p> <p>Teradata Fastload mode doesn't work correctly using the 14.10 JDBC driver when Teradata is the Target Data Source. To workaroud this issue, use a later version of the Teradata JDBC driver.</p>
Teradata 13.10	Active	Active	FastLoad/ FastExport	
Teradata 14.10	Active	Active	FastLoad/ FastExport	
Teradata 15	Active	Active	FastLoad	
Teradata 16.20	Active	Active	FastLoad	
Vertica 5.0	Inactive	Inactive		
Vertica 6.1	Active	Active	Bulk load utility  Export to another Vertica database	

## Data Ship Limitations

Some resource constraints limit the use of data ship optimization. Most limitations are related to data type mismatches. Data type mismatches are handled by a transformation of the data, but certain data types from different sources are incompatible for a selected target. Typically, these data type mismatches are most notable for numeric precision.

The following is a list of cases where use of the Data Ship optimization is not recommended.

Data Source Type	Limitation
Microsoft SQL Server	When using Microsoft SQL Server with the bcp utility, you might get data type mismatch errors if you are using BLOB or CLOB data types.



Data Source Type	Limitation
To Netezza	<p>Netezza cannot be the data ship target for source tables containing data of type BINARY or VARBINARY (for example Oracle).</p> <hr/> <p>Netezza cannot be the data ship target for tables with LONGVARCHAR or VARCHAR columns more than 64 KB long, because creation of the temporary table fails.</p> <hr/> <p>When Netezza is the data ship source, data types of FLOAT or DOUBLE might lose precision because of rounding of values sent to a target of a different type.</p>
Netezza to Sybase IQ	<p>With data ship from Netezza to Sybase IQ, NULL values are replaced with zeroes, which results in different query results than when data ship is disabled.</p>
Sybase IQ or Netezza to Oracle	<p>When Sybase IQ or Netezza data sources use Oracle as a data ship target, trailing spaces sent in the shipped table are trimmed in the result sets with the Oracle table.</p>
Sybase IQ to Netezza	<p>When Sybase IQ data sources use Netezza as the data ship target can cause a data mismatch because the Netezza database appends a padding space character in result set data.</p>
To Oracle	<p>If an Oracle database is a data ship target and the transferred data contains UTF-8-encoded East Asian characters, a column length limitation exception can occur.</p> <p>Oracle databases with a UTF-16 character set does not have this problem.</p>
To Sybase IQ	<p>If you are moving data of type FLOAT to a Sybase IQ database, the scale of the data can be lost because of the way that the Sybase IQ JDBC driver handles the FLOAT data type.</p>
Sybase IQ Type4 Driver	<p>Sybase IQ Type4 driver appears to lose the precision of time stamp columns by promoting or demoting it. To avoid this issue, use the Sybase IQ Type2 driver.</p>

Data Source Type	Limitation
Teradata	<p>Teradata controls the number of concurrent FastLoad and FastExport tasks using the MaxLoadTasks and MaxLoadAWT parameters. Excess FastLoad or FastExport tasks are rejected.</p> <hr/> <p>The maximum number of sessions for each FastLoad or FastExport job is limited to the number of AMPs of the Teradata database. Eight sessions work well for most scenarios.</p> <hr/> <p>Teradata's implementation of UNION does not follow the SQL standard, which can result in a data mismatch when the data is shipped to Teradata.</p> <hr/> <p>A row fetch size bigger than 64 KB causes a Teradata error. Refer to Teradata documentation for the best solution to this problem.</p> <hr/> <p>Teradata FastLoad requires that the target table be empty. If the target Teradata table is not empty, JDBC is used to load data into the table.</p>
To Vertica	<p>For Vertica, the maximum length of a BINARY or VARBINARY column is 65000.</p>

## Defining TDV Data Ship Configuration Parameters

Several parameters are available for configuring data ship:

- Maximum Number of Concurrent Data Transfers
- Execution Mode
- Buffer flush threshold

Because every system varies, you might need to test several values for these parameters to determine what works best.

### To configure data ship parameters

1. Log into Studio as the admin user.
2. From the Administration menu, choose Configuration.

## 3. Navigate to and determine the best settings for the following parameters.

Parameter	Description
Execution Mode	<p data-bbox="496 256 1033 288">Default server handling for data ship queries:</p> <ul data-bbox="496 305 1299 368" style="list-style-type: none"> <li data-bbox="496 305 1299 368">• EXECUTE_FULL_SHIP_ONLY—(Default) Generates an error to alert you that the full data ship was not successful.</li> </ul> <p data-bbox="539 385 1316 482">Allows data-ship execution only when the query can be performed without federation after shipment. In other words, after shipment the query must be pass-through.</p> <p data-bbox="539 499 1316 624">With EXECUTE_FULL_SHIP_ONLY, if parts of the query are federated <i>after</i> the data ship query optimization has been applied, the query execution plan Data Ship Notes contain a message like the following:</p> <p data-bbox="539 642 1310 704">Data Ship Query is not possible because after ship query is still federated and Data Ship Mode is EXECUTE_FULL_SHIP_ONLY.</p> <ul data-bbox="496 722 1305 819" style="list-style-type: none"> <li data-bbox="496 722 1305 819">• EXECUTE_PARTIAL_SHIP – This option allows both data ship and federated queries to coexist and proceed to execution even if they cannot be fully resolved into a full data ship.</li> </ul> <p data-bbox="539 836 1279 933">EXECUTE_PARTIAL_SHIP allows a query to proceed without throwing an error, even if a federated query is still required to complete query execution.</p> <ul data-bbox="496 951 1316 1048" style="list-style-type: none"> <li data-bbox="496 951 1316 1048">• EXECUTE_ORIGINAL – If certain nodes cannot be pushed and shipped because some predicates cannot be resolved prior to data pass-through, the original (pre-data ship) query plan is executed.</li> </ul> <p data-bbox="539 1065 1316 1190">EXECUTE_ORIGINAL causes query execution using the pre-data-ship execution plan whenever a query cannot be completely pushed to the data sources. The Data Ship Notes reveal that fact on execution.</p> <p data-bbox="539 1208 1316 1364">When a data ship query is not possible because of dependency on external results or to support something that cannot be pushed to the data source, the original pre-data-ship execution plan is used without shipping results to the targeted table to complete the invocation.</p> <ul data-bbox="496 1381 1310 1479" style="list-style-type: none"> <li data-bbox="496 1381 1310 1479">• DISABLED — causes the query execution plan to process the request invocations without data ship. DISABLED mode is useful for debugging.</li> </ul>

Parameter	Description
Maximum Number of Concurrent Data Transfers	Limits the number of concurrent data transfers (default 100,000), to avoid affecting the performance of other processes. Beyond this limit, new queries requiring data transfers are queued until an existing transfer is completed.

4. Click Apply.
5. (Optional) Navigate to and determine the best settings for the following parameters.

Parameter	Description
Buffer Flush Threshold	Limits the size of the buffer. (Default is 10000.) Certain types of data ship SQL executions buffer large tables before delivery to the data ship target, and the buffer size can exceed available memory. The buffer is flushed when this limit is reached.

DataShip Keep Temp File or Table	<p>The default value is false. When set to true, the server does not delete the temp table or file generated for each data ship request. This option should only be enabled when requested by a support team member.</p> <p>This value is locally defined. It is not altered when restoring a backup and is not replicated in a cluster.</p> <p>This parameter is ignored if you are using data ship and check the 'Use global temporary space for temporary tables' check box for the data ship target.</p>
----------------------------------	--

6. (Netezza only) Navigate to and determine the best setting for the following parameters.

Parameter	Description
Keep nzload Log File	<p>The Netezza driver generates a log file for each nzload operation. If true, all log files are kept. If false (default), no log files are saved to disk.</p> <p>This value is locally defined. It is not altered when restoring a backup and is not replicated in a cluster.</p>

nzload Log Directory	<p>The directory to save the Netezza driver nzload log file for data ship. The default log directory is \$TDV/tmp/dataship/netezza.</p> <p>This value is locally defined. It is not altered when restoring a backup and is not replicated in a cluster.</p>
----------------------	---

Parameter	Description
Escape Character	The escape character to use while exporting contents to or importing contents from a flat file. It defaults to backslash (\).
Truncate Long Strings during native loading	Boolean. True causes any string value that exceeds its declared CHAR or VARCHAR storage to be truncated to fit. False (default) causes the system to report an error when a string exceeds its declared storage.

7. Click Apply.
8. (Teradata only) Navigate to and determine the best settings for the following parameter:

Parameter	Description
DataShip FastExport/FastLoad Threshold	Limit for the FastLoad and FastExport processes within Teradata. If the row number exceeds this limit, use FastLoad or FastExport.  This value is locally defined. It is not altered when restoring a backup and is not replicated in a cluster.

9. Click Apply and then OK.
10. Restart the TDV Server.

## Configuring Data Ship

Depending on the type of your TDV data source, one or more of the following configuration tasks might be required:

- [Configuring Data Ship for DB2, page 530](#)
- [Configuring Data Ship Bulk Loading Option for DB2, page 531](#)
- [Configuring Data Ship for Microsoft SQL Server, page 533](#)
- [Configuring Data Ship for Netezza, page 535](#)
- [Configuring Data Ship for Oracle, page 536](#)
- [Configuring Data Ship for Sybase IQ, page 537](#)
- [Configuring Data Ship for Sybase IQ Targets with Location, page 540](#)
- [Configuring Data Ship for PostgreSQL and Vertica, page 540](#)

## Configuring Data Ship for DB2

### Requirements

- The DB2 database must have EXPLAIN plan tables created within the DB2 SYSTOOLS schema on the database that will participate in TDV data ship.

### Limitations

This feature is not valid for:

- Binary and BLOB data types
- Kerberos implementations

### About Data Ship and DB2 Temporary Tables

When a DB2 database is the target for your TDV data ship operation, you can ship the data to temporary tables. The 'Use global temporary space for temporary tables' option creates global temporary tables in DB2 and drops the data and table structure after the data ship query is completed.

The temporary table is materialized under the DB2 session schema. CREATE TABLE permissions are required on the database or schema where the temporary table will be created. The schema name is not used in the DDL to create the temporary table. The table structure is saved in the shared data dictionary, when TDV inserts data, the table is created in the session schema, and data is loaded.

When TDV drops the temporary table, it drops the instance tied to the session and the shared table structure.

### To configure the DB2 data sources that might participate in data ship

1. Log into DB2 system and start DB2 command processor db2 and call a system procedure:

```
$ db2
```

2. Connect as a user with privileges to create and modify tables within the DB2 SYSTOOLS schema on the database that will participate in TDV data ship. For example:

```
db2 => CONNECT TO <db-name> USER '<db-user>' USING '<db-pass>'
```

3. Determine if EXPLAIN tables already exist in SYSTOOLS schema, using syntax similar to the following:

```
db2 => SELECT NAME, CREATOR, TYPE
FROM SYSIBM.SYSTABLES
WHERE TYPE = 'T' AND (NAME LIKE 'ADVISE\_%' ESCAPE '\' OR NAME LIKE 'EXPLAIN\_%' ESCAPE '\')
```

If these tables exist, skip the rest of this section.

4. If the EXPLAIN tables do not exist, create them using syntax similar to the following:

```
db2 => CALL SYSPROC.SYSINSTALLOBJECTS('EXPLAIN', 'C', CAST (NULL AS VARCHAR(128)),
    CAST (NULL AS VARCHAR(128)))
```

5. Verify that the command shows:

```
Return Status = 0
```

6. Verify that the tables were created by using the following syntax:

```
db2 => list tables for schema systools
```

## Configuring Data Ship Bulk Loading Option for DB2

For DB2, the TDV bulk loading option makes use of DB2's LOAD utility. The LOAD utility can quickly load or add data to a table where large amounts of data need to move. LOAD can perform significantly faster than IMPORT because LOAD writes formatted pages directly into the database while IMPORT uses SQL INSERTS. Before attempting to use this method, we recommend that you see if using JDBC batch insert options can give you acceptable performance improvements. If you choose to implement the JDBC functionality, you do not need to configure the DB2 LOAD utility, or change any TDV configuration settings.

The DB2 LOAD utility when working with TDV requires that the DB2 command-line utility be run. How it works with TDV varies by platform:

Platform	DB2 Command-Line Utility Name	Execution Details
Windows	DB2CMD.exe	When it runs, a command window pops up, requires a password, and stays active until the upload completes. While the window is open, the password might be visible.
UNIX	db2	It can be run as a background process.

### Requirements

- The data being loaded must be local to the server.
- Requires advanced DB2 database level configuration

## Limitations

This feature is not valid for:

- Binary and BLOB data types
- Kerberos implementations

## To configure the DB2 LOAD utility to work with TDV for data ship

1. Consult the IBM documentation on configuring and using the DB2 LOAD utility.
2. Install and configure all relevant parts of the DB2 LOAD utility according to IBM's instructions for your platform.

The client drivers might need to be installed on all the machines that are part of your TDV environment.

3. Verify the full path to the DB2 command-line utility that you want to use to run the DB2 LOAD utility. For example, locate the path to your DB2 SQL command-line client.
4. Open Studio.
5. Select Administration > Configuration.
6. Locate the DB2 Command-Line Utility Path configuration parameter.
7. For Value, type the full directory path to the DB2 LOAD command-line program. For example:

For example: for Windows, set the value to "C:/Program Files/IBM/SQLLIB/BIN/db2cmd.exe"; for UNIX, set it to /opt/ibm/db2/V10.5/bin/db2. If there are spaces or special characters in the pathname, be sure to enclose the whole string in double quotes.

8. Locate the Debug Output Enabled for Data Sources configuration parameter and set the value to True.
9. Locate the Enable Bulk Data Loading configuration parameter.
10. Set the value to True.
11. Click Apply.
12. Click OK.
13. Restart your TDV Server.

Some configuration parameter value changes are applied while the TDV Server is running, but many of them require a server restart to work correctly.



14. Open Studio and locate the DB2 data source for which you want to enable the bulk load feature.
15. Open the data source editor.
16. Select the Advanced tab.
17. Scroll down to locate the Database Alias (Used For DB2 Load) field.  
This property is passed on to the DB2 Load to identify the cataloged database.
18. For Value, type the name of the DB2 database. For example: dvbudb21.
19. Save your changes.
20. Refresh your cache.

Temporary files used to support this feature are created in `infl<TDV_install_dir>\...tmp\cacheloading\db2`, all files, data, commands and logs are deleted by TDV after the upload process completes.

## Configuring Data Ship for Microsoft SQL Server

The bulk import and bulk export functionality available for data ship for Microsoft SQL Server requires the configuration of the Microsoft bcp utility. When the bulk import and bulk export functionality is used instead of the JDBC functionality, performance of operations is greatly improved. The BCP utility (`bcp.exe`) is a command-line tool that uses the Bulk Copy Program API. The Microsoft bcp utility performs the following tasks:

- Bulk exports data from a SQL Server table into a data file.
- Bulk exports data from a query.
- Bulk imports data from a data file into a SQL Server table.
- Generates format files.

If you choose to implement the JDBC functionality, you do not need to configure the bcp utility, or change any TDV configuration settings.

When configuring data ship or a cache for Microsoft SQL Server, you can configure the bcp utility and then set up access permissions. Both of these processes are described below.

The configuration steps are very similar for caching and data ship, for more information see [Configuring Native Caching Option for Vertica, page 443](#).

Note: Note: In the bcp utility, NULL values are interpreted as EMPTY and EMPTY values are interpreted as NULL. TDV passes the '\0' value (which represents EMPTY) through the bcp utility to insert an EMPTY value into the cache or data ship target. Similarly, TDV passes an EMPTY string ("" ) to the bcp utility to insert a NULL value into the cache or data ship target.

### To configure the Microsoft bcp utility to work with TDV for data ship

1. Verify that bcp.exe has been installed in an accessible directory.  
Note the full path to the bcp.exe file.
2. Open Studio.
3. Select Administration > Configuration.
4. Locate and select the Microsoft BCP utility parameter.
5. For **Value**, type the full directory path to the bcp.exe. For example:  
C:\Program Files\Microsoft SQL Server\100\Tools\Binn\bcp.exe
6. Optionally to use Windows Authentication, locate and select the DataShip BCP Threshold parameter.  
The default value is 50000. After bcp utility is enabled, if the data shipping cost estimate is 50000 or above, data ship uses the bulk import and export implementation; otherwise JDBC, is used to move the data.
7. Optionally to use Windows Authentication, adjust the value of the DataShip BCP Threshold parameter to values that fit your requirements.
8. Locate and select the DataShip BCP Threshold parameter.  
The default value is 50000. After bcp utility is enabled, if the data shipping cost estimate is 50000 or above, data ship uses the bulk import and export implementation; otherwise JDBC, is used to move the data.
9. Adjust the value of the DataShip BCP Threshold parameter to values that fit your requirements.
10. Click Apply.
11. Click OK.
12. Stop the TDV Server.
13. From the command line where your TDV Server runs, log in as the domain user.
14. Start the TDV Server.
15. Click OK.

16. Optionally, when running with Windows Authentication, on windows, open Services > TDV Server <version> and select Properties.
17. Select the Login On tab, set the This account fields to a domain user who has access to MSSQL instance.
18. Click OK.

### To set up access permissions for SQL Server for data ship

1. Consult your SQL Server documentation for how to set the SHOWPLAN permissions for the database.
2. For every SQL Server database that will participate in the data ship optimization, grant the SHOWPLAN permissions. For example:  

```
GRANT SHOWPLAN
TO <database> [ ,...n ]
```
3. You can now complete the setup in [Finishing Data Ship Configuration for Data Sources, page 540](#).

## Configuring Data Ship for Netezza

All Netezza data source connection configurations must be set to take advantage of the data ship optimization. Refer to the TDV Netezza Adapter Guide. You can now complete the set-up in [Finishing Data Ship Configuration for Data Sources, page 540](#).

Optionally, if you need to move data that has NUL characters, you can use the following procedure to determine how those characters are managed by TDV.

When the Ignore Nul Characters in Strings configuration parameter is true, NUL('\0') characters get discarded by Netezza and rest of the String is loaded. When the configuration parameter is false, NUL characters in Strings are not discarded. The default value is false.

### To ignore Nul characters in strings

1. Make sure you have both Modify All Config and Access Tools rights.
2. Log into Studio as the admin user.
3. From the Administration menu, choose Configuration.
4. In the tree pane, navigate to Data Sources > Netezza Sources > Ignore Nul Characters in Strings.
5. Select True.

When set to false, NUL characters in strings are not discarded.

6. Click Apply.
7. Click OK.

This Studio configuration change is not immediately propagated to other open instances of Studio connected with this server.

8. Restart the TDV Server.

## Configuring Data Ship for Oracle

Data ship makes use of explain plans. If your Oracle database does not already have plan tables designated to hold that data, then for data ship to work, you must create them.

### To configure data ship for Oracle

1. As a user with DBA rights for your Oracle databases involved with data ship, open your favorite tool to use to create tables.
2. Create one or more tables to hold explain plan data.
3. Make sure that the TDV users that are designing your data ship sources and targets has the following privileges:
  - create plan tables
  - execute explain plans

If this error occurs, permissions might still need adjusting:

An internal error has occurred.Cause: For input string: ""

If data is being moved between Oracle instances, performance is significantly better when database links are used instead of JDBC. Using Oracle database links allows the Oracle instance to take advantage of the proprietary channels for transferring large data tables from one Oracle instance to another.

The following steps are optional, but recommended.

### To use database links for the data ship

1. Grant the TDV-Oracle database user privilege to execute the following query:  

```
SELECT * FROM dba_db_links;
```
2. Create a database link in the Oracle client using syntax similar to the following on the Oracle instance:

```
CREATE DATABASE LINK oral2_dblink connect to devdata identified by password using '(DESCRIPTION =
(ADDRESS_LIST = (ADDRESS = (PROTOCOL = TCP)(HOST = <host_name>)(PORT = 1521)) )
(CONNECT_DATA = (SERVER = DEDICATED) (SERVICE_NAME = <service_name>))');
```

3. Verify a connection with the new database, oral2\_dblink, by executing a query like the following:  
SELECT \* FROM dual@oral2\_dblink
4. Continue with the instructions in [Finishing Data Ship Configuration for Data Sources](#), page 540.

## Configuring Data Ship for Sybase IQ

When Sybase IQ is the target of the data ship, you must perform these steps. Depending on the platform you are installing to, your steps might vary. These steps do not detail every step as might be required by Sybase, refer to your Sybase documentation for further details.

### To configure data ship for Sybase

1. Verify or install a SQL Anywhere Database Client. You can obtain a trial version through the Sybase download site.  
  
If you don't have SQL Anywhere Database Client and don't want to install one on your Unix system, then you can copy the client into <TDV\_install\_dir>/sqlanywhere<ver>, because the SQL Anywhere database client has the drivers that are needed for TDV.
2. Locate the following files in the directory where the Sybase client is installed.
  - jodbc.jar
  - libdbjodbc<ver>.so for Unix
  - dbjodbc<ver>.dll for Windows
3. Copy the files to the locations described in the following table:

OS	Copy jodbc.jar Into	Copy dbjodbc<ver>.dll Into
Windows 64	<TDV_install_dir>\apps\common\lib	<TDV_install_dir>\apps\common\lib\win64
Windows 32	<TDV_install_dir>\apps\common\lib	<TDV_install_dir>\apps\common\lib

OS	Copy jodbc.jar Into	Copy dbjodbc<ver>.dll Into
UNIX (32 and 64)	<TDV_install_dir>\apps\common\lib	<TDV_install_dir>\apps\common\lib

- Stop the TDV Server.
- For UNIX, set the global LD\_LIBRARY\_PATH environment variable to point at the SQL Anywhere client libraries folder. TDV uses LD\_LIBRARY\_PATH to find the Sybase Client library. For example, to temporarily set the variable, type:  

```
export LD_LIBRARY_PATH=/opt/<TDV_install_dir>/sqlanywhere<ver>/lib<ver>/
```
- Create an ODBC data source following the guidelines in your Sybase documentation. The following instructions highlight some of the necessary steps depending on your platform

Platform	Instructions
UNIX	<ol style="list-style-type: none"> <li>Create an odbc.ini file. We recommend that you create it under &lt;TDV_install_dir&gt;.</li> <li>Create a Sybase IQ data source name (DSN) in the odbc.ini file. For work with TDV, the Driver variable is the most important setting, because it points to the SQL Anywhere client that you have installed. For example, data sources named, test1 and test2, would look similar to the following:  <pre>##### SybDB@machine64:cat odbc.ini [test1] Driver=/opt/&lt;TDV_install_dir&gt;/sqlanywhere&lt;ver&gt;/lib&lt;ver&gt;/libdbodbc&lt;ver&gt;_r.so host=10.5.3.73 port=2638 uid=dba PWD=password DatabaseName=asiqdemo PreventNotCapable=YES  [test2] Driver=/opt/&lt;TDV_install_dir&gt;/sqlanywhere&lt;ver&gt;/lib&lt;ver&gt;/libdbodbc&lt;ver&gt;_r.so host=10.5.3.74 port=2638 uid=dba PWD=password DatabaseName=asiqdemo PreventNotCapable=YES #####</pre> </li> </ol>

Platform	Instructions
Windows	<ol style="list-style-type: none"> <li>1. Start the ODBC Administrator, select Sybase &gt; Data Access &gt; ODBC Data Source Administrator.</li> <li>2. Click Add on the User DSN tab.</li> <li>3. Select the Sybase IQ driver and click Finish.</li> <li>4. The Configuration dialog box appears.</li> <li>5. Type the Data Source Name in the appropriate text box. Type a Description of the data source in the Description text box if necessary. Do not click OK yet.</li> <li>6. Click the Login tab. Type the username and password. If the data source is on a remote machine, type a server name and database filename (with the .DB suffix).</li> <li>7. If the data source is on your local machine, type a start line and database name (without the DB suffix).</li> <li>8. If the data source is on a remote system, click the Network tab. Click the check box for a protocol and type the options in the text box.</li> <li>9. Click OK when you have finished defining your data source.</li> </ol>

10. On Unix, use the following commands to verify that the DSN is set up successfully:

```
cd sqlanywhere<ver>/bin<ver>
./dbping -m -c "DSN=test1"
```

A “Ping server successful” message means that the DSN is working. At this point any application can use the DSN to contact the Sybase IQ through the ODBC Driver.

11. On Unix, set the global ODBCINI environment variable to point at the SQL Anywhere `odbc.ini` file. For example, to temporarily set the variable, type:

```
export ODBCINI=/opt/<TDV_install_dir>/odbc.ini
```

12. Set the `QUERY_PLAN_AS_HTML` Sybase option to off. For example, run the following SQL command:

```
SET OPTION <USER_NAME>.QUERY_PLAN_AS_HTML = OFF;
```

This setting prevents Sybase from creating extra HTML plan files that can take up too much disk space.

13. Set the `QUERY_NAME` option to specify a name for each of the queries generated to help with future database cleanup.

14. Start TDV server.
15. Continue with the instructions in [Finishing Data Ship Configuration for Data Sources, page 540](#).

## Configuring Data Ship for Sybase IQ Targets with Location

JDBC can be used to transfer tables, but significantly better performance can be had with use of location. The following steps are optional, but recommended, when moving data between two Sybase IQ data sources.

### To configure Sybase IQ to ship tables using location

1. Create a Sybase IQ server:  

```
CREATE SERVER "<server-name_database_name>" CLASS 'ASAJDBC' USING '<host_name>:2638';
```
2. On the Sybase IQ instance create a user sign-in to allow remote connections:  

```
CREATE EXTERNLOGIN <user_name> TO "<host_name>_<database_name>" REMOTE LOGIN <user_name>  
IDENTIFIED BY <password>;
```
3. Configure the added server info in the interfaces file for the Sybase IQ server.
4. Repeat the configuration for each Sybase IQ server, pointing the SQL location at each of the other Sybase IQ instances.
5. Continue with the instructions in [Finishing Data Ship Configuration for Data Sources, page 540](#).

## Configuring Data Ship for PostgreSQL and Vertica

There are no special configuration steps necessary for the data sources outside of Studio.

## Finishing Data Ship Configuration for Data Sources

All data sources that are to participate in data ship should be configured as data ship targets. If only one node is configured to be a data ship target, the relative sizes of the nodes are not considered; the SQL operation can only be performed on the data source that can be the data ship target.

At least one data source in a federated join must be configured to accept data shipments of external tables as the target; otherwise, data ship optimization is not possible.



Data can only be shipped in the direction of the data ship target.

When all participating data sources are configured to act as a data ship target, the estimated costs to obtain results from each of the nodes is analyzed. The node that is likely to cost the most to retrieve is designated as the target and nodes with smaller cardinality are fetched to ship to the target node. The SQL operation is performed locally on the temporary tables in the data source to gain the efficiencies available on the target.

### **About Lower and Upper Bounds**

When data-source-specific analytic or aggregate functions are used in queries, set the lower bound to zero so that nodes with very low cardinality results get pushed to the data source for shipment. For joins where the nodes have low cardinality and do not use data-source-specific functions, set the lower bound to block data shipment of results with only a small number of rows. Performance is ordinarily better in this case because the query initialization and temp table creation can take a few seconds longer than direct processing of a small number of rows that do not require SQL analytical processing.

Where more than two nodes are involved in a SQL operation, it might not make sense to limit shipment of a small result set, because external table creation and shipment can happen in parallel. The SQL operation is not hindered by gathering relatively small results tables from multiple sources while a larger data set is loading.

The upper bound value sets the size (as estimated and measured by rows) limiting what result tables can be considered for shipping as external tables.

A value of zero disables data shipment for that data source, but does not disqualify it from participating in a data ship as the target for other results tables. If a query node estimate is greater than the upper bound for that data source, it can only participate as the data ship target. The upper bound is data-source-specific; it sets the bounds to restrict the movement of very large result tables.

### **To finish data ship configuration**

1. Open Studio.
2. Right-click the data source name in the Studio resource tree and select **Open**.

3. Select the Configuration tab, and provide values for the following on the Basic tab:
  - **Pass-through Login**—For non-Netezza data sources, set to **Disabled** so that data ship functionality can work properly.
  - **Transaction Isolation level**—Set to **Serializable** for data ship functionality. This prevents dirty reads, non-repeatable reads, and phantom reads.
4. Use the **Advanced** tab to set values for the following fields. The fields that you see vary depending on the type of data source with which you are working. For example, a Sybase IQ data source might have the Sybase iAnywhere JDBC driver check box displayed, but a Teradata data source would not

Field	Type of Data Source	Description
Is dataship source	<ul style="list-style-type: none"> <li>• DB2</li> <li>• Oracle 11g</li> <li>• Sybase IQ 15</li> <li>• Teradata</li> <li>• MS SQL Server</li> <li>• Vertica</li> </ul>	This must be checked if the physical data source might be used as a source of shipped tables to another data ship enabled data source. Check <b>Is dataship source</b> for all data sources so that the TDV Server can analyze the query and determine the side that would be best to ship to based on expected or estimated query node cardinality.
Is dataship target	All	This must be checked if the physical data source might be used to receive shipped tables from another data ship enabled data source. Check <b>Is dataship target</b> for all data sources so that the TDV Server can analyze the query and determine the side that would be best to ship to based on expected or estimated query node cardinality.
Lower bound for data ship	All	TDV uses <b>Explain Plan</b> to arrive at a numeric estimate of the cost of shipping data from a node to the Data Virtualizer. When the cost of shipping a federated query node falls between the limits of the <b>Lowerbound</b> and <b>Upperbound</b> , it is considered eligible for shipment so that it can be processed locally.
Upper bound for data ship		
LowerBoundForDataShip		
UpperBoundForDataShip		

Field	Type of Data Source	Description
Use global temp space for temp tables	DB2	When this data source is the data ship target, this option creates global temporary tables and drops the data together with the table structure after the data ship query is completed.
Schema path for Temp Tables	All	A relative path to set the location of the temp tables on the data source. It is the name of a schema in the data source.  Required for DB2, make sure that this name matches a schema name known to TDV. Case should match exactly.
Temp Table Prefix	All	A character string addition to temporary table names so that they are recognized if they are needed.  Optional for DB2.
Enable Bulk Import/Export	MS SQL Server	Check box that enables the bulk movement of data using the bcp utility. You must have finished the steps in <a href="#">Configuring Data Ship for Netezza, page 535</a> .
Database Link List	Oracle with database links	Add your database links separated with semicolons, using the following syntax: [DBLINK NAME]@[DBLINK OWNER DS PATH]  For example: oral2_dblink@/users/composite/test/sources/dship/DEV-DSJ-ORA11G-2
Enable Bulk Export/Load	PostgreSQL Vertica	Takes advantage of PostgreSQL COPY command.
Enable PostgreSql dblink	PostgreSQL	Check to enable database links to improve performance if you plan to use this data source for data caching or data ship optimization. If you check this box, add one or more database links by specifying the database link name and path of the data source for each link

Field	Type of Data Source	Description
Sybase iAnywhere JDBC Driver	Sybase IQ	Select this check box to enable better performance. This option enables the Sybase IQ specific ODBC LOAD TABLE SQL tool to import data into TDV.  You must have finished the steps in <a href="#">Configuring Data Ship for Sybase IQ</a> , page 537.
Sql Anywhere Data Source	Sybase IQ	Enter your ODBC DSN name.
Enable Sybase IQ SQL Location	Sybase IQ with Location	Select this check box to enable this option for the data source.
SQL Location Name	Sybase IQ with Location	The <b>SQL Location</b> name should take the form: <server_name>.<database_name>
Path of data source	Sybase IQ with Location	The TDV full pathname to the other Sybase data source. For example: /shared/sybase_iq_1
Add Sql Location	Sybase IQ with Location	If there are more than two Sybase IQ instances you can add multiple locations by using the green plus button.
Enable FastLoad/FastExport for large tables	Teradata	Setting this option indicates that you want to use Teradata's FastLoad or FastExport utility to speed up your query times. For a given query, cardinality information is used to decide whether to use Fastpath or JDBC default loading.
FastExport Session Count	Teradata	The number of FastExport sessions to use for Teradata.
FastLoad Session Count	Teradata	The number of FastLoad sessions to use for Teradata.
Enable Bulk Load	Vertica	Setting this option indicates that you want to use Vertica's Bulk Load utility to speed up your query times. For a given query, cardinality information is used to decide whether to use Bulk Load or JDBC default loading.

Field	Type of Data Source	Description
Enable Export To Another Vertica Database	Vertica	When set, allows data to be exported to another Vertica database. You need to name each database that is available to accept the exported data. TDV uses the CONNECT and EXPORT commands to establish the connections between the data ship source and the data ship target.
Exported Databases	Vertica	Only available if you have selected the <b>Enable Export To Another Vertica Database</b> option.
Exported database name	Vertica	Name of the Vertica database to which you want to export data.
Path of data source	Vertica	The TDV full pathname to the other Vertica data source. For example: /shared/vertica

5. Save your settings.

## Evaluating Queries for Data Ship Using Execution Plans

Studio execution plans can tell you whether a query can make use of data ship or not. When you create views and procedures that involve data from tables that exist on separate sources the execution plan reveals whether the data ship optimization can improve performance of the query.

During the query development phase, verify that the data ship query plan performs better than a standard query plan without the data ship. Sometimes, the time cost of shipping a very large table across the network between two different kinds of data sources can cost almost as much as processing the query normally.

After configuring your data source to use the data ship optimization, you need to evaluate the queries that are run by that data source to determine if they benefit from the data ship. If the queries benefit from the data ship optimization, there is nothing further that you need to do. If the queries do not benefit from the data ship, you need to disable the feature in the hint of the query SQL.

For more information about the execution plan fields and what they represent, see [Performance Tuning, page 475](#).

**To use execution plans to evaluate your queries**

1. Open Studio.
2. Open the view or procedure that has the query you want to evaluate.
3. Validate that the query is a SQL operation between two or more data sources that can act as the data ship source and at least one data source that can act as the data ship target receiving the shipped tables.
4. Click Show Execution Plan to reveal the Execution Plan tab.
5. Review the query execution report paying specific attention to:

Detail	Description
Estimated Rows Returned	A value estimated from table cardinalities which are not generally used to estimate the cost of shipping SQL requests. For Netezza, determine the cost of a query with an Explain Plan function. For Netezza, the estimated rows returned field will have a value of Unknown.
Data Ship target	Where to send the results of SQL execution. The presence of a data ship target indicates that data ship will be performed.
Data Ship Notes	A report of the estimated number of rows to be shipped, and the amount of time consumed to get the cost estimate. When a condition blocks the use of data ship, this field usually describes the condition, case, or option that ruled out optimization.

6. Execute other queries to show statistics like costs of table creation and other query initialization costs that add to the overall retrieval time.

See [Execution Plan Panel, page 613](#) for information about the buttons and controls on the Execution Plan. See [Working with the SQL Execution Plan, page 477](#) for information about using the execution plan and evaluating the results.

## Using Time Series Functions for Vertica Data Ship Targets

There are a few special steps to consider when defining views that include Vertica time series functions. The following steps are guidelines for how you can make use of the following Vertica time series functions within a data ship target view where the SQL will be run entirely on the Vertica database:

- `TIMESERIES SELECT` clause which names a time slice
- `TS_FIRST_VALUE`

- TS\_LAST\_VALUE

### Restrictions

- Running the Vertica time series functions in any data source besides Vertica results in processing errors.
- Time functions with time zone and timestamp functions with time zone, do not have micro- and nanosecond precision, nor time zone information. A workaround for that limitation includes using the CAST function to have the time zone value converted to a VARCHAR value.

### To use Vertica time series functions

1. Create or identify a view from any data source for which you want to use the time series functions.
2. If non-Vertica data sources are involved, enable data ship with Vertica as the target. For more information, see [Finishing Data Ship Configuration for Data Sources, page 540](#).
3. Enable data ship with Vertica as a source.
4. Manipulate your view code to make use of the Vertica time series function. Refer to *Vertica Programmers Guide* and *Vertica Reference Guide* for details of the time series syntax. The following view SQL is included as a sample of one way to write a data ship query that uses Vertica time series functions:

```
SELECT
  store_key, cc_class, case when store_key is not null then store_key end mycase
FROM
  /users/composite/test/sources/vertica50/store/store_dimension
inner join
  /users/composite/test/sources/netezza50/TPCDS100_2/TPCDS100/PROD/CALL_CENTER
ON cc_call_center_sk = store_key
timeseries ts as '3 hour'
over (partition by store_key, first_open_date, cc_class
order by cast(cc_rec_start_date as timestamp))
order by case when ts is not null then ts end , store_key
```

5. Test the view to make sure that all the SQL is pushed and processed on the Vertica database.

## Disabling Data Ship for Specific Query SQL

The data ship optimization is configured for each data source. A data source might have hundreds of queries that it runs. Some of those queries can benefit from having the data ship optimization enabled and so you must configure the data ship. However, there might be a few queries that do not benefit from using the data ship optimization. For those queries that do not benefit from the optimization, you must disable the optimization. For more information on data ship options, see the *TDV Reference Guide*.

### To disable data ship for specific queries

1. Open Studio.
2. Open the view or procedure for which you want to disable data ship.
3. Select the **SQL** tab.
4. Add the following hint syntax to the SELECT statement:  
{OPTION DATA\_SHIP\_MODE="DISABLED"}
5. Save the change.

## Managing Open Connection Threads

The driver properties are used to specify connection timeout settings as required by the specific driver. By specifying the properties that are used by your specific data source, you can avoid situations where connections are left open indefinitely. This will prevent TDV threads from locking up on requests that need to establish a database connection.

Because each database has different connection properties, you will need to become familiar with them to determine which property to set and what values are appropriate for your environment.

### To manage the connection threads

1. Open the data source editor for the data source that has been identified as having connection threads that stay open too long.
2. Open the Advanced tab.
3. Edit the **Connection Properties—JDBC Connection Properties** to define connection timeout intervals that are appropriate for your environment.



## Using Data Ship for Prepared Statements

If data ship has been enabled and a query is submitted using a prepared statement where the query is static but input variables can change, TDV evaluates it for data ship. For queries, TDV computes an execution plan. The execution plan considers data ship for each invocation of a prepared statement after the parameter values are known and presented to TDV.

For queries with prepared statements, the value of each parameter for a given execution is determined, the query is evaluated to build an execution plan, and data ship is considered. If TDV determines that data ship can be used to optimize the performance of the query, then TDV will process the query using data ship.

### **To use data ship for each invocation of a prepared statement**

1. Define a table or view with a PreparedStatement.
2. Make sure that both the source and target data sources have data ship enabled.
3. Publish your table or view.
4. Run the queries containing the PreparedStatement.



# Configuring the TDV Massively Parallel Processing Engine

---

TDV is automatically configured to use the massively parallel processing (MPP) engine. MPP Engine automatically distributes the workload and automatically evaluates and optimizes existing views and data services.

The following topics are covered in this chapter:

- [About the TDV MPP Engine Configuration, page 551](#)
- [Setting Up and Configuring the TDV MPP Engine, page 554](#)
- [When should the MPP Engine be engaged?, page 556](#)
- [Configuring the MPP engine from the Query Execution Plan Viewer, page 557](#)
- [Considerations for using MPP Engine, page 561](#)
- [SQL Functions, page 566](#)
- [Canceling Jobs When MPP Engine is Active, page 574](#)

## About the TDV MPP Engine Configuration

TDV allows you to publish large federated datalakes and datawarehouses as one virtual datalake and make it available to consuming applications. TDV implements a new execution engine for MPP style processing. The Massively Parallel Processing (MPP) execution engine provides the acceleration that is essential for analytical processing of your business needs. The MPP Engine dynamically distributes the queries across multiple processors spanning the entire cluster for large data volume workloads. TDV takes into consideration the dataset volume, the compute capability of the underlying source, the cardinality statistics information from the source, and the compute capacity of TDV when optimizing for MPP style execution. TDV employs a hybrid approach to scheduling queries by determining which engine (MPP or Classic) is most appropriate for it. The use of MPP Engine is transparent and does not require any rewrite of existing DV artifacts.


The MPP Execution Engine optimizes operators like JOINS, UNIONS, AGGREGATEs, and SORTs by distributing the processing across multiple processors. Unlike the traditional single node query execution, the MPP Engine can leverage the entire cluster's compute and memory for expensive operators like the above. The choice of selecting MPP execution should take into account the

volume of dataset being retrieved and whether it involves single or multiple datasources. For a data set to be analyzed by the MPP engine its data source must be configured to allow for receiving partitioned queries. This can be done by setting the data source setting `concurrentRequestLimit` in the Advanced Connection Settings to a value greater than 0.

If the datasets involved in a query are small, then using the MPP Engine will entail a penalty of setup time and network cost of data hops across the nodes. The traditional single node query execution will be much faster in that situation. There is a tunable Minimum Partition Volume property that controls the threshold beyond which the optimizer will consider MPP execution.

For the MPP configuration, data is partitioned across multiple servers or nodes with each server node having memory and processors to manage the data locally. All communication is through the network—there is no disk-level sharing or contention. TDV recommends that the nodes are homogeneous in terms of CPU cores and memory.

The following image illustrates how the MPP Engine distributes processing of a query in parallel on two nodes of a cluster.



## MPP Engine OS Support

MPP Engine is supported on Linux platforms only with the following pre-installed 3rd party software:

- a. Network Security Service (NSS) Package version 3.28.4 x86\_64 or higher (package name: nss).
- b. CentOS/RedHat/Oracle Linux versions 6.5 or higher are supported for this feature.
- c. SUSE Linux version 12 and above is supported for this feature.

## Supported Data sources

The following datasources are currently supported for the MPP Engine:

Datasource, version
GreenPlum
Postgresql
MS SQL Server
Oracle
Vertica
Hive
Impala
DB2 LUW
ComputeDB
Netezza
Microsoft Azure Data Lake Gen2
Amazon AWS S3

## Ports used for TDV MPP Engine

7 additional ports are required by MPP Engine.

IF the port specified for TDV is P (the TDV base port default is 9400), then the following ports are needed.

Zookeeper Quorum Port =  $P - 100$

Zookeeper Election Port =  $P - 100 + 1$

Zookeeper Client Port =  $P - 100 + 2$

Drill HTTP (web console) Port =  $P - 100 + 3$

Drill User Port =  $P - 100 + 4$

Drill Server Bit Ports =  $(P - 100 + 5)$  and  $(P - 100 + 6)$

Note: The above ports are only active on operating systems that support MPP engine. (Refer to [MPP Engine OS Support](#), page 27 in the Installation Guide).

## Setting Up and Configuring the TDV MPP Engine

The TDV MPP Engine is enabled by default. It is recommended to use the Active Cluster deployment strategy for harnessing the power of MPP Engine.

An Active Cluster configuration is not necessary, but can provide optimal performance for parallel query processing.

### To set up and configure the TDV MPP engine

1. Open Studio.
2. From the Administration menu, choose Configuration.
3. Navigate to Server > SQL Engine > Parallel Processing.

Configuration Parameter	Description
Maximum Heap Memory	Maximum heap memory allocated for parallel processing. For this value to take effect you will need to disable and enable parallel processing. Default value will be 10% to total system memory, and the value set must be greater than 0.
Enabled	Determines whether the MPP engine is enabled or not. The default value is true for Linux environments and False for Windows and AIX environments.
Limit scalar subqueries	True or False Controls whether you want a LIMIT 1 clause to automatically append to your scalar subqueries.

Configuration Parameter	Description
Logging Level	<p>Set to one of: OFF, LOW, MEDIUM, HIGH</p> <p>LOW level allows for distributed query routing to be traced - from original TDV query to Drill query to partitioned TDV virtual scan queries. Fallback reason is also recorded. MEDIUM level augments this information with resource allocation information pertaining to each query. HIGH level further augments this information with a non-parallelization reason.</p>
Maximum Direct Memory	<p>Maximum direct memory allocated for parallel processing. For this value to take effect you will need to disable and enable parallel processing. Default value will be 50% to total system memory, and the value set must be greater than 0.</p>
Minimum Partition Volume	<p>The minimum data volume to be fetched by each partition (in MB). This setting is approximate, because it is based on virtual scan query result volume estimates.</p> <p>Default value is 256. If set to 0 or a negative value, it has no effect.</p>
Resource Quota per Request	<p>This value is the percentage of system resources that each request is limited to during parallel execution.</p> <p>Setting this value to 100 would allow only 1 query at a time to run in the MPP Engine, using a value of 50 would allow 2 concurrent queries to be served by the MPP Engine and so on and so forth.</p>
Startup Connection Retry Count: 30	<p>This value is the number of times the server will try to autoconfigure the parallel runtime engine at server startup.</p> <p>Default value is 30.</p>
Startup Connection Retry Interval	<p>This value is the amount of time in milliseconds the server will wait before retrying to auto-configure the parallel runtime engine at server startup.</p> <p>Default value is 1000.</p>

4. Click **Apply**.
5. Click **OK**.
6. Open the data source editor for the data sources involved in MPP.

- Open the Advanced tab, locate the Concurrent Request Limit field and adjust the value according to the instruction given below

Configuration Parameter	Description
Concurrent Request Limit	This configuration can take a value between 0 to 65536. It specifies the concurrency limits to be imposed on the underlying data source. If concurrentRequestLimit is set to 0, then partitioned queries will not be issued against the data source and the query engine will not operate in parallel mode against the data source. For any value greater than 0, the query engine will throttle concurrency to X number of concurrent connections, where concurrentRequestLimit=X. Choose concurrentRequestLimit appropriately by taking into account the acceptable concurrent load on the data source as well as the number of concurrent queries in DV that will run in parallel (determined by "Request Quota Per Request").

## When should the MPP Engine be engaged?

MPP Engine is best suited when

- The datasets retrieved by queries are of significant volume.
- There are at least two or more datasets that need to be combined.

If the datasets are small, then using the MPP Engine will result in an overhead of setup time, unnecessary routing of data to different nodes and also to combine them back at runtime. In such a situation, using the classic engine gives best results.

However, the choice of not using the MPP Engine when not required can be controlled in the configuration of SQL Engine by the field called Minimum Partition Requirement.

### Query examples to demonstrate the best use of the MPP Engine

Following is a sample query that can be handled by the MPP Engine:



```

SELECT nation, o_year, sum(1) sum_profit
FROM (SELECT n_name nation, EXTRACT(YEAR FROM o_orderdate) o_year, l_extendedprice
- ps_supplycost * l_quantity amount
FROM /users/composite/drill/ds/tpchorcl234/C##TPCH10/H_part,
/users/composite/drill/ds/tpchorcl236/C##TPCH10/H_supplier,
/users/composite/drill/ds/tpchorcl234/C##TPCH10/H_lineitem,
/users/composite/drill/ds/impala20_247/tpch/partsupp,
/users/composite/drill/ds/tpchorcl234/C##TPCH10/H_order,
/users/composite/drill/ds/impala20_247/tpch/nation
WHERE ((((((s_suppkey = l_suppkey AND ps_suppkey = l_suppkey) AND ps_partkey =
l_partkey) AND p_partkey = l_partkey) AND o_orderkey = l_orderkey) AND s_nationkey =
n_nationkey) AND s_nationkey < 19) AND n_nationkey > 5) AND p_name LIKE '%dodger%'))
profit
GROUP BY nation, o_year
ORDER BY nation ASC, o_year DESC

```

Follow these steps to run your query. The TDV MPP Engine is enabled by default, if the datasource is supported.

1. Create view with query, and fetch its execution plan. For instructions on running the Query Execution Plan, refer to [Configuring the MPP engine from the Query Execution Plan Viewer, page 557](#)
2. Check if it is passed to MPP Engine.
3. If a “No parallelization reason” is displayed, then according to the reason, decide if you need to adjust server configurations or if this query can only be supported by Classic engine.
4. If the query is passed to the MPP Engine, then execute the query. If MPP Engine supports the query in runtime, then the engine will return result, otherwise it will fall back to the Classic engine to execute.

## Configuring the MPP engine from the Query Execution Plan Viewer

From the Studio View editor, generate the query execution plan by clicking on the button Show Execution Plan. The following plan is displayed in the Execution Plan pane.

The screenshot shows the Query Execution Plan Viewer interface. The top navigation bar includes tabs for SQL, Columns, Indexes, Foreign Keys, Caching, Cardinality Statistics, Test Identity, and Info. Below this is the 'Execution Plan' tab. The main area is split into two panes. The left pane shows a tree view of the execution plan, with 'tst-dre' expanded to 'SELECT', and 'PARALLEL\_FETCH' selected. The right pane displays the detailed configuration for the selected operator, including its name, estimated rows returned, SQL text, and details for virtual scans R\_2 and R\_3.

Click on the PARALLEL\_FETCH on the left hand side to display a detailed Query Execution Plan on the right hand side. In case PARALLEL\_FETCH did not happen, click on SELECT, to investigate the reason. The reason explained in the right-pane will help you tune your settings. Refer the section [Considerations for using MPP Engine, page 561](#) for a list of things to consider while using the MPP Engine.

**Name:** PARALLEL FETCH

**Estimated Rows Returned:** 8000000 (between 0 and 9223372036854775807 rows)

**SQL:** SELECT `R\_1`.`nation`, `R\_1`.`o\_year`, SUM(1) AS `sum\_profit` FROM (SELECT `R\_3`.`nation`, EXTRACT(YEAR FROM `R\_5`.`o\_orderdate`) AS `o\_year` FROM `ciscodv.Q-1919832149200026`.`R\_3` INNER JOIN `ciscodv.Q-1919832149200026`.`R\_4` ON `R\_3`.`n\_nationkey` = `R\_4`.`s\_nationkey` INNER JOIN `ciscodv.Q-1919832149200026`.`R\_5` ON `R\_4`.`s\_suppkey` = `R\_5`.`l\_suppkey` INNER JOIN `ciscodv.Q-1919832149200026`.`R\_2` ON `R\_5`.`l\_partkey` = `R\_2`.`ps\_partkey` AND `R\_5`.`l\_suppkey` = `R\_2`.`ps\_suppkey`) `R\_1` GROUP BY `R\_1`.`nation`, `R\_1`.`o\_year` ORDER BY `R\_1`.`nation` NULLS FIRST, `R\_1`.`o\_year` DESC NULLS LAST

**Virtual Scan R\_2:**

**R\_2 - Data source path:** /users/composite/drill/ds/impala20\_247

**R\_2 - Data source type:** Impala

**R\_2 - SQL:** SELECT tpch.partsupp.`ps\_partkey`, tpch.partsupp.`ps\_suppkey` FROM tpch.partsupp

**R\_2 - Estimated row data volume:** 64

**R\_2 - Estimated number of rows:** 8000000

**R\_2 - Estimated total data volume:**512000000

**R\_2 - Partition count:**1

**R\_2 - Partition column name:**ps\_partkey

**R\_2 - Partition rank:**100

**Virtual Scan R\_3:**

**R\_3 - Data source path:**/users/composite/drill/ds/impala20\_247

**R\_3 - Data source type:**Impala

**R\_3 - SQL:**SELECT tpch.nation.`n\_name` AS `nation`,tpch.nation.`n\_nationkey` FROM tpch.nation WHERE (tpch.nation.`n\_nationkey` > 5 AND tpch.nation.`n\_nationkey` < 19)

**R\_3 - Estimated row data volume:**4294967398

**R\_3 - Estimated number of rows:**14

**R\_3 - Estimated total data volume:**60129543572

**R\_3 - Partition count:**8

**R\_3 - Partition column name:**nation

**R\_3 - Partition rank:**150

**Virtual Scan R\_4:**

**R\_4 - Data source path:**/users/composite/drill/ds/tpchorcl236

**R\_4 - Data source type:**Oracle

**R\_4 - SQL:**SELECT

"C##TPCH10"."H\_SUPPLIER"."S\_SUPPKEY","C##TPCH10"."H\_SUPPLIER"."S\_NATIONKEY" FROM "C##TPCH10"."H\_SUPPLIER" WHERE ("C##TPCH10"."H\_SUPPLIER"."S\_NATIONKEY" < 19 AND "C##TPCH10"."H\_SUPPLIER"."S\_NATIONKEY" > 5)

**R\_4 - Estimated row data volume:**64

**R\_4 - Estimated number of rows:**56089

**R\_4 - Estimated total data volume:**3589696

**R\_4 - Partition count:**1

**R\_4 - Partition column name:**s\_suppkey

**R\_4 - Partition rank:**100

**Virtual Scan R\_5:**

**R\_5 - Data source path:**/users/composite/drill/ds/tpchorcl234

**R\_5 - Data source type:**Oracle

**R\_5 - SQL:**SELECT

"C##TPCH10"."H\_PART"."P\_PARTKEY","C##TPCH10"."H\_ORDER"."O\_ORDERDATE","C##TPCH10"."H\_LINEITEM"."L\_PARTKEY","C##TPCH10"."H\_LINEITEM"."L\_SUPPKEY" FROM "C##TPCH10"."H\_PART" INNER JOIN ("C##TPCH10"."H\_LINEITEM" INNER JOIN "C##TPCH10"."H\_ORDER" ON "C##TPCH10"."H\_LINEITEM"."L\_ORDERKEY" = "C##TPCH10"."H\_ORDER"."O\_ORDERKEY") ON "C##TPCH10"."H\_PART"."P\_NAME" LIKE "%dodger%" AND "C##TPCH10"."H\_PART"."P\_PARTKEY" = "C##TPCH10"."H\_LINEITEM"."L\_PARTKEY"

**R\_5 - Estimated row data volume:**168

**R\_5 - Estimated number of rows:**31959459

**R\_5 - Estimated total data volume:**5369189112

**R\_5 - Partition count:**1

**R\_5 - Partition column name:**p\_partkey

**R\_5 - Partition rank:**100

The following table explains the different fields in the query execution plan..

Field	Description
Estimated Rows Returned	The estimated number of rows returned for the whole query. Notice that in the above example, multiple data sources are being used in the query and the estimated number of rows returned is 8M.
SQL	The SQL query that is being executed. Notice that in the above example, the topmost query is the main query which is decomposed into partitioned queries.
<b>Virtual Scan</b>	
	A Virtual Scan represents a FETCH against a datasource that would spawn multiple queries partitioned by the partition column.
Data Source Path	The path of each of the datasource that is being used in each virtual scan.
Data Source Type	The type of each of the datasource that is being used in each virtual scan.
Estimated Row Data Volume	The estimated row data volume in bytes.
Estimated Number of Rows	The estimated number of rows that is returned in each virtual scan.
Estimated Total Data Volume	The estimated total data volume for each virtual scan.
Partition Count	Partition Count represents the number of ranges of the partition column that is dynamically computed. It indicates the number of partitioned queries that will be issued as part of each virtual scan.
Partition Column Name	This is the column chosen as the most suitable candidate for issuing partitioned queries, most likely candidates are numeric columns.
Partition Rank	Partition rank is a weight assigned to candidate partition columns based on their data type, the uniqueness of their values and the type of statistics (detailed or boundary) available for the distribution of their values. One of the columns with the highest weight is designated as the partition column.

*Note:* On the top level SELECT node of the query execution plan, when there is a note “*No Parallelization*”, it indicates that the query did not match the conditions to be processed in parallel. Some of the reasons for such a scenario include Concurrent Request Limit not set, data sources characteristics not suitable for parallel processing, Case-sensitivity or Trailing space settings do not allow for parallel processing, Semi-join optimization takes precedence over parallel processing, etc. In these cases tune the appropriate settings to force parallel mode.

If you find that your query does not run in parallel mode though the query plan shows a Parallel Fetch then there could be a runtime failure that causes the Fallback to classic engine. The fallback reason will be logged in the DV log under Server > SQL Engine > Parallel Processing > Log Level (when it is set to HIGH). There could be various reasons why a runtime failure occurs: for example, the node got disconnected from the cluster, configured memory was not sufficient for query to finish, runtime code generation caused a failure, etc.

## Considerations for using MPP Engine

You must consider the following while configuring TDV MPP Engine and designing your queries.

1. MPP Engine is only applicable for Linux based deployment
2. Not all datasources are supported by the MPP Engine. Refer to [Supported Data sources, page 553](#) for a list of the datasources currently supported by the MPP Engine.
3. If a Query uses the MAX\_ROWS\_LIMIT option to limit the number of rows returned, then the query will not run use the MPP Engine.
4. Most of the SQL statements are supported by MPP Engine with the exception of DDLs like CREATE, DROP, ALTER and DMLs like INSERT, UPDATE, DELETE, MERGE
5. Procedure joins are not supported.
6. SQL Operators Except and Intersect are not supported.
7. The Case Sensitivity and Ignore Trailing Spaces settings may need to be altered to match with the MPP Engine’s default case sensitivity behavior. The MPP Engine uses a case sensitive approach for String columns.
8. In some cases, semi-join optimization may be chosen over a parallel plan. To force a parallel plan, the MAX\_SOURCE\_CARDINALITY for semi-join setting may need to be tuned.
9. For TIME and TIMESTAMP columns, the MPP Engine only handles up to 3 digits of precision for milliseconds.

10. Non-equi joins may not get scheduled for parallel processing.
11. In some cases, you may need to enable statistics for selected tables and columns in order to engage the MPP Engine.
12. Using < or > with VARCHAR may have mismatches due to case-sensitivity differences

## JOIN Restrictions

There are certain restrictions around the types used in the JOIN predicates. The following example demonstrates a fallback scenario:

```
select
  p.productnumber foo
from /users/composite/admin/oracle9i/GOSALES1/PRODUCT p
where 1 in (select
  c.categoryid
from /users/composite/admin/northwind/Northwind/dbo/Categories c
where c.categoryid AS DECIMAL = p.productnumber)
```

The fallback reason while running the execution plan for the above query is:

"Unable to retrieve result from data source "/system/runtime/DRE" during query execution. Failed query: "SELECT `R\_2`.`foo` FROM `ciscodv.Q-1920181812400727`.`R\_2` WHERE 1 IN (SELECT DISTINCT `R\_1`.`categoryid` FROM `ciscodv.Q-1920181812400727`.`R\_1` WHERE `R\_1`.`categoryid` = `R\_2`.`foo`)". [data-3923000] - Cause: SYSTEM ERROR: DrillRuntimeException: Join only supports implicit casts between 1. Numeric data (none of types is decimal or both of them are decimal) 2. Varchar, Varbinary data 3. Date, Timestamp data Left type: VARDECIMAL, Right type: INT. Add explicit casts to avoid this error Fragment 1:2 [Error Id: 1854e912-7999-4429-a78a-40f160e81764 on dv-spark-5148.dv.local:3304]

By adding an explicit CAST (as given below), this situation can be avoided and the query will start to use the MPP Engine.

```
select
  p.productnumber foo
from /users/composite/admin/oracle9i/GOSALES1/PRODUCT p
where 1 in (select
  c.categoryid
from /users/composite/admin/northwind/Northwind/dbo/Categories c
where CAST(c.categoryid AS DECIMAL) = p.productnumber)
```

## Tuning the Server Configuration

There are certain configuration parameters that can be tuned, in order to use the MPP Engine for your query. Certain tuning options are explored in this section with examples.

### Max Source Side Cardinality Estimate

This setting controls the estimated maximum number of rows in the source side of a join to trigger an automatic semi-join. This value can be overridden at data source level using the Studio.

```
SELECT
  supp_nation,
  cust_nation,
  sum(1) revenue
FROM (SELECT
  n1.n_name supp_nation,
  n2.n_name cust_nation,
  l_extendedprice volume
  FROM /shared/new_DS/hive211/tpch_11/supplier,
  /shared/new_DS/hive211/tpch_11/lineitem,
  /shared/new_DS/hive211/tpch_11/orders,
  /shared/new_DS/hive211/tpch_11/customer,

  /shared/new_DS/imp27/tpch_11/nation n1,
  /shared/new_DS/imp27/tpch_11/nation n2
  WHERE ((((((s_suppkey = l_suppkey AND o_orderkey = l_orderkey) AND c_custkey = o_custkey)
  AND s_nationkey = n1.n_nationkey) AND c_nationkey = n2.n_nationkey) AND ((n1.n_name LIKE
  'FRANCE%' AND n2.n_name LIKE 'GERMANY%') OR (n1.n_name LIKE 'EGYPT%' AND n2.n_name
  LIKE 'IRAN%')))) AND l_shipdate BETWEEN DATE '1995-01-01' AND DATE '1996-12-31')) shipping
GROUP BY supp_nation,
  cust_nation
ORDER BY supp_nation ASC,
  cust_nation ASC
```

While running the execution plan for the above query, depending on your configuration of this setting, you may have the following fallback reason:

```
Query plan contains a SCAN node using a SEMI join: |physical.operator.SqlScan (@44093785,
@471fc95b) |Type : |Node Id : 10 |Datasource Id : 20173 |Plan Level : 0 |Cardinality : 8 (between 0
and 9223372036854775807 rows) | Selectables: customer.c_nationkey, supplier.s_nationkey | Map : 0,
1 | Matching Id : 30, 32 |semiJoinID: 2 |semiJoinNode:
physical.operator.DynamicHashJoin@2ced0d21 |Push SQL is SELECT
customer.`c_nationkey`,supplier.`s_nationkey` FROM tpch_11.supplier JOIN tpch_11.lineitem ON
supplier.`s_suppkey` = lineitem.`l_suppkey` JOIN tpch_11.orders ON lineitem.`l_orderkey` =
orders.`o_orderkey` JOIN tpch_11.customer ON orders.`o_custkey` = customer.`c_custkey` WHERE
(lineitem.`l_shipdate` >= '1995-01-01' AND lineitem.`l_shipdate` <= '1996-12-31')
```

Follow these steps:

1. Navigate to Administration -> Configuration -> Server -> SQL Engine -> Optimizations -> Semi join and set the “Max Source Side Cardinality Estimate” to -1. You can also navigate to the property by searching for it using the search option in the configuration window.
2. Click on Apply.
3. Rerun the execution plan

Once the setting is tuned appropriately tuned, the query will do a Parallel Fetch.

### Case Sensitivity

This setting controls the default case-sensitivity of queries. If false, string comparisons are done ignoring case. If this setting does not match the case-sensitivity setting of a data source, performance will be degraded when querying that source. The default value is False. Depending on your configuration of this option, you may come across the following fallback reason:

Cannot delegate plan execution to the parallel runtime engine: Cannot push Selectable because the data source Apache Drill 1.14 is case sensitive and our system is not case sensitive and the selectable is not wrapped with upper or lower function --R\_1`.supp\_nation`--

Follow these steps:

1. Navigate to Administration -> Configuration -> Server -> SQL Engine -> SQL Language and set the “Case Sensitivity” to True. You can also navigate to the property by searching for it using the search option in the configuration window.
2. Click on Apply.
3. Rerun the execution plan

Once the setting is tuned appropriately tuned, the query will do a Parallel Fetch.

### Ignore Trailing Spaces

This setting controls the ignore trailing spaces during string comparisons in queries. If true, string comparisons are done ignoring trailing spaces. If this setting does not match the trailing spaces setting of a data source, performance will be degraded when querying that source. Default value is True. Depending on your configuration of this option, you may come across the following fallback reason:

Cannot delegate plan execution to the parallel runtime engine: Cannot push selectable because the data source Apache Drill 1.14 does not ignore trailing spaces and our system ignores trailing spaces and the selectable is not wrapped with rtrim function --R\_1`.supp\_nation`--



Follow these steps:

1. Navigate to Administration -> Configuration -> Server -> SQL Engine -> SQL Language and set the “Ignore Trailing Spaces” to False. You can also navigate to the property by searching for it using the search option in the configuration window.
2. Click on Apply.
3. Rerun the execution plan

Once the setting is tuned appropriately, the query will do a Parallel Fetch.

### Minimum Partition Volume

The Minimum Partition Volume configuration is used to set the data volume to be fetched by each partition. The default value is 256. If set to 0 or a negative value, this has no effect. Run the following query to analyze this option:

```
select CASE (N_NAME)
  WHEN 'ALGERIA' THEN 'result1'
  WHEN 'KENYA' THEN 'result2'
  ELSE 'other'
END as col1
from /users/composite/drill/ds/tpchorcl234/C##TPCH10/H_NATION inner join
/users/composite/drill/ds/tpchorcl236/C##TPCH10/H_REGION
on N_REGIONKEY=R_REGIONKEY
```

The following fallback scenario may arise.

Plan has scans with low estimated data volumes. Maximum estimated data volume: 4250

Follow these steps:

1. Navigate to Server -> SQL Engine -> Parallel Processing -> Minimum Partition Volume and set it to a lower value. You can also navigate to the property by searching for it using the search option in the configuration window.
2. Click on Apply.
3. Rerun the execution plan

Note: Queries handling data of low volume are typically not handled by the parallel processing engine. The setting “Disable Low Data Volume Restriction” can be turned on to disable this rule.

Once the configuration parameters are appropriately tuned as explained above, the query will do a Parallel Fetch.

## SQL Functions

This section lists the SQL Functions that are supported and not supported by the MPP Engine. See the Reference guide, [About SQL Functions in TDV, page 79](#) for a detailed description of these functions.

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
<b>Analytical Functions</b>	
AVG	COVAR_POP
COUNT	COVAR_SAMP
CUME_DIST	CORR
DENSE_RANK	LISTAGG
FIRST_VALUE	NTH_VALUE
LAG	PERCENTILE_CONT
LAST_VALUE	PERCENTILE_DISC
LEAD	RATIO_TO_REPORT
MAX	REGR_AVGX
MIN	REGR_AVGY
NTILE	REGR_COUNT
PERCENT_RANK	REGR_INTERCEPT
RANK	REGR_R2
ROW_NUMBER	REGR_SLOPE
SUM	REGR_SXX
	REGR_SYY
	STDDEV
	STDDEV_POP

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
	STDDEV_SAMP
<b>Array Functions</b>	
CARDINALITY	EXTEND
CAST	FIND_INDEX
CONCAT	TRUNCATE
<b>Binary Functions</b>	
INT1AND, INT2AND, INT4AND, INT8AND	
INT1NOT, INT2NOT, INT4NOT, INT8NOT	
INT1OR, INT2OR, INT4OR, INT8OR	
INT1SHL, INT2SHL, INT4SHL, INT8SHL	
INT1SHR, INT2SHR, INT4SHR, INT8SHR	
INT1XOR, INT2XOR, INT4XOR, INT8XOR	
<b>Character Functions</b>	
ASCII	BITSTREAM_TO_BINARY
BITCOUNT	CHR
BIT_LENGTH	DLE_DST
BTRIM	FIND
CHAR_LENGTH	FIND_IN_SET
CONCAT	GREATEST
GET_JSON_OBJECT	INET_ATON
HEX_TO_BINARY	INET_NTOA
INSTR	INITCAP
ISUTF8	JSON_TABLES

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
LOWER	LCASE
LPAD	LEAST
LTRIM	LEFT
OCTET_LENGTH	LENGTH
PARSE_URL	LE_DST
POSITION	MD5
QUOTE_IDENT	OVERLAYB
QUOTE_LITERAL	PARTIAL_STRING_MASK
REGEXP_EXTRACT	REVERSE
REGEXP_REPLACE	RIGHT
REPEAT	SPLIT_PART
REPLACE	TO_CANONICAL
RPAD	TRANSLATE
RTRIM	UCASE
SPACE	UNICHR
SOUNDEX	UNICODE
STRPOS	V6_ATON
SUBSTR	V6_NTOA
TRIM	V6_SUBNETA
TRIMBOTH	V6_SUBNETN
TRIMLEADING	V6_TYPE
TRIMTRAILING	
UPPER	

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
<b>Conditional Functions</b>	
COALESCE	DECODE
IFNULL	NVL2
ISNULL	
ISNUMERIC	
NULLIF	
NVL	
<b>Convert Functions</b>	
CAST	TO_CHAR
FORMAT_DATE	TRUNCATE
PARSE_DATE	
PARSE_TIME	
PARSE_TIMESTAMP	
TIMESTAMP	
TO_BITSTRING	
TO_DATE	
TO_HEX	
TO_NUMBER	
TO_TIMESTAMP	
TRUNC	
<b>Cryptographic Functions</b>	
HASHMD2	
HASHMD5	

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
HASHSHA	
HASHSHA1	
<b>Date Functions</b>	
CLOCK_TIMESTAMP	ADD_MONTHS
CURRENT_DATE	AT_TIMEZONE
CURRENT_TIME	DATEDIFF
CURRENT_TIMESTAMP	DAYOFMONTH
DATE_PART	DAYOFYEAR
DATE_SUB	DB_TIMEZONE
DATE_TRUNC	EXTRACTDOW
DAY	EXTRACTDOY
DAYOFWEEK	EXTRACTEPOCH
DAYOFWEEK_ISO	EXTRACTMICROSECOND
DAYS	EXTRACTMILLISECOND
DAYS_BETWEEN	EXTRACTQUARTER
EXTRACT	ISFINITE
EXTRACTDAY	JULIAN_DAY
EXTRACTHOUR	MICROSECOND
EXTRACTMINUTE	MIDNIGHT_SECONDS
EXTRACTSECOND	NUMTODSINTERVAL
EXTRACTMONTH	NUMTOYMININTERVAL
EXTRACTYEAR	QUARTER
FROM_UNIXTIME	STATEMENT_TIMESTAMP

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
GETUTCDATE	SYSDATE
HOUR	TIMESTAMP_ROUND
MINUTE	TIMESTAMP_TRUNC
MONTH	TIMESTAMPADD
MONTHS_BETWEEN	TIMESTAMPDIFF
NEXT_DAY	TRANSACTION_TIMESTAMP
NOW	WEEK
SECOND	WEEK_ISO
TIME_SLICE	
TIMEOFDAY	
TZ_OFFSET	
TZCONVERTOR	
UNIX_TIMESTAMP	
UTC_TO_TIMESTAMP	
YEAR	
<b>Numeric Functions</b>	
ABS	ATAN2
ACOS	DEGREES
ASIN	LN
ATAN	LOG10
CBRT	NUMERIC_LOG
CEILING	ROWNUM
COS	SINH

SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
COT	TANH
EXP	
FLOOR	
LOG	
MOD	
PI	
POW	
POWER	
RADIANS	
RAND	
RANDOM	
ROUND	
SIGN	
SIN	
SQRT	
TAN	
<b>Phonetic Functions</b>	
DBL_MP	
NYSIIS	
PRI_MP	
SCORE_MP	
SEC_MP	
<b>XML Functions</b>	



SQL Functions - Supported by MPP Engine	SQL Functions - Not supported by MPP Engine
---	---

XMLATTRIBUTES

XMLAGG

XMLCOMMENT

XMLCONCAT

XMLDOCUMENT

XMLELEMENT

XMLFOREST

XMLNAMESPACES

XMLPI

XMLQUERY

XMLTEXT

XPATH

XSLT

**Operator Functions**

X + Y (Add)

FACTORIAL or X!

X - Y (Subtract)

X || Y (Concatenate)

X \* Y (Multiply)

X \*\* Y (Exponentiate)

X / Y (Divide)

X % Y (Modulus)

-X (Negate)

**Note:** If an expression that is computed has an undefined result (for example, 0/0), the MPP Engine returns the value "NaN". For a similar scenario, the classic query engine throws an exception. The results may vary if the query is pushed down to a datasource.

## Canceling Jobs When MPP Engine is Active

Canceling jobs being run with the MPP can be done directly from the Studio or Web Manager.

### **To cancel MPP jobs from Studio Manager**

1. From Studio, select the Manager tab on the left most Studio tabs.
2. From Studio Manager, select Requests.
3. Locate the job request that is running the MPP query and select it.
4. Select Cancel.

### **To cancel MPP jobs from Web Manager**

1. Open web Manager.
2. Select Monitoring > Requests.
3. Locate the job request that is running the MPP query and select it.
4. Select Cancel Request(s).

# Push-Based Incremental Caching

---

Push-based incremental caching can be set up using the native TDV caching mechanism, plus the TDV Cache Management Service (CMS), to configure a Central Event Server. If you have subscribed to notices from objects that store data in an incremental cache, subscribed clients are notified whenever the result sets are updated. After they are notified, clients can choose to update their result sets or refresh the affected views. Each client instance of TDV can be configured to process the messages and automatically update its incremental cache.

The following resources cannot be cached without being wrapped in a view or procedure:

- Procedures with no outputs. There is no data to cache in this case.
- XML files that have been introspected.
- System tables.
- Non-data sources such as folders and definition sets.

The following topics are covered and should be performed in order:

- [View Requirements and Restrictions for Push-Based Incremental Caching, page 575](#)
- [Requirements for Push-Based Incremental Caching, page 576](#)
- [Adding the Change Notification Custom Java Procedures, page 582](#)
- [Defining Connectors, page 583](#)
- [Install the Central Server, page 584](#)
- [Configuring Push-Based Incremental Caching and Change Management, page 584](#)
- [Publishing the cms\\_call\\_propagator Procedure, page 585](#)
- [Configuring Oracle Data Sources for Change Notification, page 585](#)
- [Setting Up an Push-Based Incremental Cache in Studio, page 586](#)
- [Publish Push-Based Incremental Caches, page 588](#)
- [Recovering from a Messaging Error, page 588](#)
- [Push-Based Incremental Caching Configuration Parameters, page 590](#)

## View Requirements and Restrictions for Push-Based Incremental

## Caching

When you decide to use a view for push-based incremental caching, you must consider how the view is defined and how the data source is monitored for change capture.

Subscribed views must have explicitly defined or implicitly inferred keys. Composite views (subqueries) are supported if they occur in the FROM clause. Incremental caches do not support INTERVALDAYTOSECOND and INTERVALYEARTOMONTH data types as key values.

The following view operators are supported.

Operator	Supported
Renaming	Yes. Example: C1 AS C2
Projection	Yes, for creating a view from two table columns with scalar function support. Example: SELECT UPPER(C1)
Selection	Yes, with scalar function support. Example: WHERE LOWER(C1) = 'abc'
Inner Join	Yes.
Left Outer Join	Yes, if only the left side is monitored by GoldenGate. Otherwise, no. The restriction applies because processing of the data change for left outer joins could result in inaccurate data.
Right Outer Join	Yes, if only the right operand is monitored by GoldenGate. Otherwise, no. The restriction applies because processing of the data change for right outer joins could result in inaccurate data.

## Requirements for Push-Based Incremental Caching

To set up push-based incremental caching, you must meet the following requirements and perform the described steps:

- The monitored data sources and cache database must be Oracle.

- You must install and configure the following products, using your own licensing and customer agreements with the companies that distribute the products:
  - TIBCO Enterprise Message Service (EMS) and JMS
  - Oracle database
  - Oracle GoldenGate change data capture
  - Apache Geronimo

This section provides some guidelines for configuring these systems to work with the TDV push-based incremental caching feature, but you must follow the requirements and instructions as detailed in the documentation for each product.

- Installed a valid Active Cluster instance.
- Before you configure push-based incremental caching, you must locate the following:
  - `cscms.jar`, `composite_cdc.jar`, `cscms_call_propagator.jar`
  - `tibjms.jar`, `tibjmsadmin.jar`
  - `axis2-adb-1.3.jar`
- You must also complete the steps and address the suggestions in the following sections:
  - [Configuring Oracle Database for Push-based Incremental Caching, page 577](#)
  - [Installing and Configuring Oracle GoldenGate, page 578](#)
  - [Installing the TIBCO JAR File, page 581](#)
  - [Configuring JMS Pump for Oracle GoldenGate Using TIBCO EMS, page 581](#)

## Configuring Oracle Database for Push-based Incremental Caching

Data sources and derived tables must be prepared for use in automatically updated incrementally maintained caches and view subscriptions. The caching databases used must set permissions so that tables and indexes can be dynamically created for subscription-related tables.

“Change” messaging from the change-data capture (CDC) service to the specified data source topic is required; without it, no view updates are possible. Refer to [Installing and Configuring Oracle GoldenGate, page 578](#) for information on making the CDC service compatible for use with the TDV Software Change Management Service.

Push-based incremental caching requires an Oracle account that grants the following permissions to connect with and use the targeted Oracle database as a subscription store:

- Create subscription-related tables and indexes.
- Introspect required tables. Both **READ** and **SELECT** access are required.
- Execute regular SQL queries against data sources and tables of interest.
- Grant **EXECUTE**, **INSERT**, **UPDATE**, and **DELETE** permissions against those tables.
- Execute **flashback** queries against data sources and tables of interest.

Oracle databases used to store incrementally cached views and views involving joins of monitored tables must be configured with `cursor_sharing` set to **EXACT**. Other settings for `cursor_sharing` result in degradation of performance.

### To configure Oracle data sources

1. Log on to the Oracle database machine as SYSDBA.
2. Turn on supplemental logging at the database level using commands like the following:

```
SQL> ALTER DATABASE ADD SUPPLEMENTAL LOG DATA;
```

```
SQL> ALTER SYSTEM SWITCH LOGFILE;
```

Or, log in to the database server as the schema owner for the tables that are to be monitored and change the supplemental logging for individual tables.

```
SQL> ALTER TABLE <tableName> ADD SUPPLEMENTAL LOG DATA (ALL) COLUMNS;
```

3. Make sure that the Oracle databases have archivelog and flashback enabled.

To enable flashback, get the system change number (SCN) value using:

```
SELECT dbms_flashback.get_system_change_number FROM dual;
```

## Installing and Configuring Oracle GoldenGate

GoldenGate monitors the Oracle tables for changes, and sends change notification messages to the TIBCO EMS queue so that dependent queries can be updated, and subscribed clients can be notified when data table changes might impact their view.

Access to your Oracle GoldenGate server depends on your implementation environment, and it might require use of an SSH utility like PuTTY or WinSCP. The server address, login, password, and port used are all environment- and implementation-dependent. In the example scripts, parameter files, and code given, the GoldenGate installation directory, \$GGHOME, is /opt/oracle/ggs/, but that is configurable.

The three \*.prm file parameters, GETUPDATEBEFORES, NOCOMPRESSUPDATES, and NOCOMPRESSDELETES, must be included, because these settings control the format of the change notification messages so that they are sent in the format expected by TDV.

If any of the parameters are omitted, then the message content and message format might be malformed, and all incrementally maintained caches might be marked as invalid to prevent use of bad data. Malformed change messaging from the GoldenGate instance can force the Change Management Service on the Central Event Server to shut down, so that the system can be corrected prior to end-use.

Most of the messaging errors result in invalidation of the caches and termination of CMS until the messaging can be corrected. Error messages are recorded in the cs\_server.log.

### To configure GoldenGate

1. Install GoldenGate co-located with the Oracle data source that is to be monitored. Refer to the GoldenGate documents for a description of the requirements and installation considerations.
2. Copy the composite\_cdc.jar file from the TDV installation directory to the directory:

```
<$GoldenGateHome>/GGIEJ_304/javaue/resources/lib
```

The TDV CDC JAR inserts a header into the GoldenGate messages and includes the SCN value for the transaction classpath of the Java UE.

3. Log in to the Oracle GoldenGate server and navigate to: \$GGHOME/dirprm.
4. Using the GGSCI command line utility, create an EXTRACT group.

```
GGSCI (comp-name)
```

```
1> ADD EXTRACT <ExtractGroupName>, TRANLOG, BEGIN NOW
```

The string <ExtractGroupName> cannot be more than eight characters.

5. Create as many extracts as required for the monitoring of data source tables. Each extract is run as a separate process that can be set to monitor a different set of tables. Groups of extracts can be started and stopped from an .obey file

or by a batch or shell script collectively. See the *GoldenGate Administrator Guide* for details.

6. Extract a trail file by entering the following at the GGSCI command prompt:

```
GGSCI (comp-name)
2> ADD EXTTRAIL <C:\sub-dir\...\$GGHOME\dirdat\XX>, EXTRACT <ExtractGroupName>
```

XX is the two-character name of the exttrail filename group. All trail files have this prefix with a six-digit incrementing numeral, and they are placed in the \$GGHOME/dirdat directory. The GGSCI utility creates a new exttrail and an extract parameter file. This file defines the table resources for monitoring and extraction.

7. Edit the <ExtractGroupName>.prm parameter file, using a text editor, with the following command:

```
GGSCI (comp-name)
3> EDIT PARAMS <ExtractGroupName>
```

8. Save the parameter file in the /dirprm subdirectory.

### Example Parameter File

In this example:

- EXTGROUP is the <ExtractGroupName>;
- EG is the two character name of the EXTTRAIL file name group
- TRANLOGOPTIONS controls transaction log options such as the Automatic Storage Management User login to set SQL execution options.
- WILDCARDRESOLVE sets the default explicitly. SQL EXEC sets the NLS\_DATE\_FORMAT handling so that date data type handling is consistent with the TDV system.

```
• extract EXTGROUP
userid UserName, password password
exttrail ./dirdat/EG
TRANLOGOPTIONS ASMUSER sys@VAULTREPO_ASM, ASMPASSWORD password333
WILDCARDRESOLVE DYNAMIC
SQLEXEC "ALTER SESSION SET NLS_DATE_FORMAT='YYYY-MM-DD HH24:MI:SS'"
-- The following parameters explicitly set the defaults:
EOFDELAYCSECS 1
FLUSHCSECS 1
--GROUPTRANSOPS 10
REPORTCOUNT EVERY 1 SECONDS, RATE
-- The following three parameters are required to ensure compatibility with CMS:
GETUPDATEBEFORES
NOCOMPRESSUPDATES
NOCOMPRESSDELETES
```

-- Monitored tables are listed here. The following tables are used as examples.



```

table qacntrial.address;
table qacntrial.bid;
table qacntrial.category;
table qacntrial.creditcard;
table qacntrial.favoritesearch;
table qacntrial.item;
table qacntrial.sale;
table qacntrial.users;

```

## Installing the TIBCO JAR File

As another prerequisite to push-based incremental caching, you need to install the TIBCO JAR file.

### To install the TIBCO JAR file

1. Copy the `tibjms.jar` TIBCO file from the TIBCO installation folder to the directory:  
<TDV\_install\_dir>/apps/server/lib/
2. Restart the TDV Server.

## Configuring JMS Pump for Oracle GoldenGate Using TIBCO EMS

GoldenGate must be enabled with JARs from both TIBCO JMS and a TDV Java User Exit Program. The TDV Java User Exit Program must also be configured and enabled for use with TIBCO EMS.

### To configure JMS pump

1. Copy the `tibjms.jar` TIBCO file from the TIBCO EMS installation to the directory:  
<\$GoldenGateHome>/GGIEJ\_304/javaue/resources/lib
2. Copy the `composite_cdc.jar` file from the TDV `cscms.jar` installation directory to the directory:  
<\$GoldenGateHome>/GGIEJ\_304/javaue/resources/lib

The TDV CDC JAR inserts a header into GoldenGate messages, and includes the SCN value for the transaction classpath of the Java user environment.


3. Restart the Oracle GoldenGate CDC processes.

## Adding the Change Notification Custom Java Procedures

Load the Java procedures to set up change notification and incremental caching. The CMS Change Engine (CE) provides core functionality for the Change Notification feature. For example, it implements and manages the Virtual View Resolver, incremental cache updating, and Change Data Notification (CDN). These features are provided with a TDV Custom Java Procedure (CJP).

### To create a new data source based on a custom Java procedure

1. Search for and verify the paths to the following files:
  - axis2-adb-1.3.jar
  - cscms\_call\_propagator.jar
  - tibjmsadmin.jar
2. In Studio, right-click My Home in the resource tree and select New Data Source.
3. Select Custom Java Procedure and click Next.
4. Enter a name for the new Change Notification Custom Java Procedure and use Browse to specify the location of cscms.jar.



5. In Additional classpath (semicolon separated), type the paths to the JAR files, using forward-slashes (“/”) in the path:
  - <TDV\_install\_dir>/../axis2-adb-1.3.jar;
  - <TDV\_install\_dir>/../cscms\_call\_propagator.jar;
  - <TDV\_install\_dir>/../tibjmsadmin.jar
6. Click Create and Introspect.
7. Select all the procedures listed.
8. Click Next, Finish, and OK.

## Defining Connectors

You need to define connectors to establish messaging between the servers, and to ensure fault-tolerance. The connector settings should be identical between the servers in your environment. The Servers require Connector Management configurations after the TDV Server is restarted with the TIBCO interface JAR. The Input EMS and Output EMS could be the same connector on the same TIBCO instance, but because of the amount of traffic expected, and for scalability, input and output messages are best handled by separate queue connectors. The Input EMS is the default Connector handling messages from GoldenGate JMS Pump. The Output EMS handles TDV-to-client change message notifications for subscribing clients.

### To define connectors

1. Follow the steps in “Configuring TDV for Using a JMS Broker” in the *TDV Administration Guide* to use Manager to configure TDV for use with a JMS broker.

2. Still in Manager, select CONFIGURATION > Connectors.

You are going to create a JMS Connector to connect with the TIBCO Queue and a Queue Connection Factory (QCF).

3. Click Add Connector.
4. Type a name for the connector.
5. Select the JMS via JNDI tab.
6. Define the Input EMS JMS connector information.

This connector takes the messages from GoldenGate and passes them to TDV for processing. Your TIBCO EMS and deployment environment dictates the values you need to enter for the Connector parameters. Type c in Initial Context Factory and select `com.tibco.tibjms.naming.TibjmsInitialContextFactory` from the list of factories. Type the JNDI Provider URL (for example, `tibjmsnaming://dev-tibco-6:7222`).

7. Record the name you gave to the Input EMS Connector.
8. Create another Connector to serve as the Output EMS connector.  
TDV sends messages to subscribing clients through this connector so they can update their caches.
9. Record the name you gave to the Output EMS Connector.

10. Click OK to save the JMS Connector.

## Install the Central Server

Push-based incremental caching requires that a central server be defined. In a cluster, one TDV instance is the Central Event Server. Subscribing clients then receive cache increments from the Central Event Server rather than from the Oracle database through GoldenGate.

### To install the central server

1. Expand the CMS node you created in the Studio My Home directory.
2. Open the cms\_admin\_install procedure.
3. Execute the cms\_admin\_install procedure.
4. Enter CENTRAL as the value of the Mode parameter and click OK.
5. Open Studio > Administration > Configuration and verify that the Change Management Service node (folder) is now present.

## Configuring Push-Based Incremental Caching and Change Management

The following Central Event Server settings are required for CMS functionality.

### To configure push-based incremental caching and change management messaging

1. Open the TDV Configuration panel by selecting Administration > Configuration from the Studio menu bar, and navigate to Change Management Service > Central Function > Messaging.
2. Configure Input EMS > Default Connector.  

This is the name of the Input EMS connector you defined using Manager. It is the messaging connection that the Central Event Server uses to receive Change Data Capture data source monitoring change notifications.
3. Configure Internal EMS > Queue Connector.
4. Configure Output EMS > Default Connector.

This is the name of the Output EMS connector you defined using Manager. It is the messaging connection that the Central Event Server uses to forward change notifications to subscribing clients.

5. Configure Output EMS > Security Domain.
6. Review the configuration parameters under Internal EMS and change them based on the information in [Push-Based Incremental Caching Configuration Parameters, page 590](#).

## Publishing the cms\_call\_propagator Procedure

If you are implementing push-based incremental caching in a cluster environment, you must publish the cms\_call\_propagator client web services. The Server publishes the procedures cms\_client\_subscribe, cms\_client\_unsubscribe, cms\_client\_renewSubscriptions, and cms\_client\_getSubscriptions, and the servers use the cms\_call\_propagator procedure to pass parameters from those calls to the Central Event Server.

For more information on creating a Web service and publishing procedures, see:

- [Publishing Resources to a Web Service, page 346](#)
- [Publishing Resources to a Database Service, page 340](#)

### To publish the cms\_call\_propagator

1. Create a new service under the Web Services folder; for example, CS\_CMS.
2. Locate cms\_call\_propagator procedure in the Studio navigation tree.
3. Publish it to the Web service you created for it; for example CS\_CMS.
4. Click OK.
5. Verify that you can see the procedure in the resource tree.

## Configuring Oracle Data Sources for Change Notification

Data sources must have a change notification connector and a topic name specified.

Derived views must be available to be subscribed to, or have cached views that are incrementally maintained. The topic name must be specified on the Change Notification tab of the data source; otherwise, the data source will not receive data source change messages from the Oracle GoldenGate process.

**Note:** The Change Notification tab for the data source only appears after the Central Event Server has been configured.

The data source Change Notification tab defines the Topic Name to which Oracle GoldenGate is configured to send change notification messages.

Each watched data source must specify a topic on which to receive change notification messaging from the Oracle GoldenGate utility. The topic can use the Input EMS Default Connector or a different JMS Connector specific for that data source.

If a single instance of Oracle GoldenGate has been sending nonconforming messages, it is possible that only the topics affected by that Oracle GoldenGate instance need to be purged rather than all of the data sources topics.

### To configure an Oracle data source for change notification

1. Create the Oracle data source.
2. Open the Oracle data source.
3. Select the **Change Notification** tab.
4. (Optional) Type a JMS Connector Name. This value overrides any JMS connection that is defined in the TDV configuration parameters. If no value is specified, the value of the Default Connector TDV configuration parameter is used as the JMS connector.
5. Type a Topic Name. The topic name must be the one you created during JMS configuration. (See [Defining Connectors, page 583.](#))
6. Save the information.

## Setting Up an Push-Based Incremental Cache in Studio

For the resource being cached, storage depends on the result set output, and on retrieval of the entire result set or retrieval of a filtered subset. Decide on a storage type for caching the execution result. For information on how TDV cached data types are mapped to data source data types, see “Cache Data Type Mapping” in the *TDV Reference Guide*.

**Note:** For tables, the expiration period applies to the whole table. For procedures, each input variant’s data has its expiration tracked separately.

If a resource uses a data source that was originally added to TDV Server using the pass-through mode without saving the password, row-based security can affect the cache refresh functionality. For details on Save Password and Pass-through Login, see [Adding a Data Source, page 70.](#)

For information about the objects created by the cache, see [Caching to a File Target, page 420](#).

### To enable caching, select the cache storage type, and schedule caching

1. Make sure the data source and tables on which the view is based are set up to be monitored for changes and the data source has a connector and topic specified on which change notification messages will be received.
2. In Studio, open a view or procedure.
3. Select the Caching tab.
4. Click Create Cache.
5. Under Status, select the Enable check box.
6. Under Storage, specify the storage type as User Specified.
7. Use Browse to locate and specify the data source. After you select the data source, its full path is displayed in the Data Source field.
8. Use the Open button to open the data source to create two tables, one for storing cache status data and the other for storing cache tracking data.
9. (Optionally) If you want to rename the cache status table, in the Caching section of the data source Configuration tab, select Browse to the right of Status Table.
10. Close the data source Configuration tab. Navigate back to the view or procedure with the open Caching panel.
11. Use Browse to the right of result in the Table for Caching section to specify a location within the data source to create a table for caching.  
This location can be the root level of the data source or a schema.
12. In the Select cache table for result window, select the location and type a name under Create Table.
13. Click Create, examine the DDL for result code, and click Execute.
14. Open the table you created to the Caching panel and click Create Cache.
15. On the Caching panel, select Incrementally Maintained.
16. Save the cache settings. After cache settings are saved the resource appears with a lightning-bolt icon in the Studio resource tree to show that the resource is cached.

After a brief initial data load task, the cache view is actively updated. Status for the cache is **UP** when the resource is saved. If cache initialization fails for any reason, clear the Incrementally Maintained check box, save the view, and

then check the box again and save the view again. Because cache initialization is not automatically fault-tolerant, a retry re-initializes the cache.

When a view cache is marked as incrementally maintained and the connection to the source table or the target table caching database instance is down, the time it takes to report the connection problem depends on operating system network settings, such as the TCP default timeout.

If you have data type incompatibilities between your view and your data storage type, see “Cache Data Type Mapping” in the *TDV Reference Guide* to determine the best data storage option for you cache.

## Publish Push-Based Incremental Caches

Publishing an automatically updated incrementally maintained cache view is no different from publishing any other view. When an authorized user requests an incrementally maintained view, the result set returned is already synchronized with the data present in the data source. The automatically updated incrementally maintained cache results are served immediately to the user without any additional request or load imposed on the data sources.

## Recovering from a Messaging Error

The Change Management Service is stopped when a nonconforming message is received. When CMS is stopped due to a messaging error, all incrementally maintained caches are marked as Disabled, and subscription failure messages with content of “<ops/>” are sent to all subscribed clients.

The `cs_server.log` should be checked for an exception message like the following example:

```
Exception: java.lang.Exception: Invalid message element: expecting 'before' element, got 'missing'...
```

Invalid message element indicates that the messaging format was broken and outside of schema requirements. CMS issues “<ops/>” messages to subscribing clients, invalidates caches, and stops so that CMS and messaging can be restarted from a configured state.

If the exception is a data type mismatch, it is likely that the source of the error was not the Oracle GoldenGate process, and so those processes do not need to be recreated. However, queues and topics might still have to be purged to clear the system of corrupt data.



## To resolve messaging issues

1. Check the Oracle GoldenGate configuration parameter file in the /dirprm subdirectory where Oracle GoldenGate is installed. Make sure that the parameters GETUPDATEBEFORES, NOCOMPRESSUPDATES, and NOCOMPRESSDELETES (and any other relevant parameters) are set up to create messages that are compatible with CMS.
2. Stop the “extract” and the “JMS Pump” processes.
3. Delete the GoldenGate extract and JMS Pump processes.
4. Remove the trail files defined in the two related \*.prm files. The trail files are typically in the dirdat folder of the GoldenGate home directory, \$GGHOME/dirdat, and the files all begin with the two-character prefix specified for the name of the extrail filename group. (See [Installing and Configuring Oracle GoldenGate](#), page 578.)
5. Make corrections to the configuration parameters.
6. Recreate the GoldenGate extract and JMS Pump processes using the .obey file.
7. If the TDV-Managed Destinations configuration parameter is set to false, use a TIBCO EMS utility to purge queues and topics named under Change Management Service > Central Function > Messaging > Internal EMS, as follows:
  - Use purge queue <queue\_name> to purge the queue named in In Transit Event Queue.
  - Use purge topic <topic\_name> to purge the topic named in Transient Cache Buffering Topic.
8. Use TIBCO EMS utility purge topic <topic\_name> to purge the input EMS topics specified on the Change Notification panels of all data sources configured for incremental caching.
9. Restart the TDV Change Messaging Service on the Central Events Server.
10. Restart all disabled caches with the following for each incrementally maintained cache.
  - a. Clear the Incrementally Maintained check box on the Caching tab of the view.
  - b. Save the view.
  - c. Select the Incrementally Maintained check box and then save the view again. Wait a few moments while the cache re-initializes itself by creating a materialized view based on the SCN timestamp reported by the GoldenGate monitoring utility.

Incrementally maintained caches that were marked as Disabled should then show a status of Up, and those caches will be kept in sync, mirroring all changes made to the watched data sources.

Outbound EMS topics with subscribers listening for change notifications on subscribed views automatically begin receiving change notification messaging when changes to the watched sources are reported.

## Push-Based Incremental Caching Configuration Parameters

The following is an alphabetical list and description of the TDV Change Management Service configuration parameters on the Central Event Server. These parameters are visible with an active CSCMS license after CMS has been installed. All of them appear in the Configuration window (select Administration > Configuration from the Studio menu bar) under Change Management Service. In two cases, Logging Options and Tibco, parameters are described in groups.

Parameter/Group	Description
Administration	For a description, see under parameter group Logging Options.
Attempt Count	Under Central Function > Fault Tolerance. The number of times CMS attempts connection recovery after a failure. With the default setting of "0" CMS attempts connection recovery with data sources, EMS, and other active cluster members until all connections are restored.
Attempt Delay	Under Central Function > Fault Tolerance. This value denotes the delay, in milliseconds, between attempts to recover from a connection failure. The default value is 1000.
Caching	For a description, see under parameter group Logging Options.
Change Inference	
Change Inference Messages	
TDV-Managed Destinations	Under Central Function > Messaging. Typically, TDV is set to manage output messaging queue and topic destinations. TDV creates queues and topics according to the needs of the client subscriptions, in transit events, and transient cache buffers. If TDV-Managed Destinations is set to false, all of the Messaging > Internal EMS properties must be set.

Parameter/Group	Description
Connection Attempt Count	For a description, see under parameter group Tibco.
Connection Attempt Delay	
Connection Attempt Timeout	
Data Sources	For a description, see under parameter group Logging Options.
Default Connector	Under Central Function > Messaging > Input EMS. The name of the EMS topic connection factory for receiving change notification messages from Oracle GoldenGate through TIBCO EMS. Data source specific connectors and topics can be defined to override the default connector. The value of the Input EMS Default Connector server property is the name of the JMS via JNDI Connector. JMS connector attributes like initial context factory and JNDI provider URL are defined on the CONNECTOR MANAGEMENT page of the Manager (Web) interface.
Default Connector	Under Central Function > Messaging > Output EMS. The name of the EMS topic connection factory to be used for creating topics to send change notification messages from TDV to subscribed clients. Individual topics are created dynamically based on client subscription requests. Data source specific EMS Connectors and topics can be defined to override the default connector. The value of the Output EMS Default Connector is the name of the JMS via JNDI Connector.
Error Handling Procedure	The name of the procedure to call in case an invalid message has been received. The procedure must accept three arguments: a string value for the error, a string value for the offending message, and a timestamp for the time at which the error was reported.
Expiration Period	The number of hours a client subscription remains valid without renewal to monitor a view for changes. Client subscription renewals before the expiration period has elapsed result in extensions that last for another expiration period. The expiration period begins when the client subscription is created and it is reported to the client subscriber.
In Transit Event Queue	Under Central Function > Messaging > Internal EMS. If TDV-Managed Destinations is set to false, this parameter must be set to a valid queue created to host in-transit change events. The In Transit Event Queue is used to ensure fault tolerance so that if a server instance crashes, event processing can resume, starting from the last successfully processed message.

Parameter/Group	Description
Include Column Names	<p>Under Central Function &gt; Messaging &gt; Message Format. The following example shows an update message (“U”) with a format that includes both the rank (“r”) and the column names (“n”):</p> <pre data-bbox="361 296 729 748"> &lt;U a="true"&gt; &lt;k r="0" n="Column Name 0"&gt;value0&lt;/k&gt; &lt;k r="1" n="Column Name 1"&gt;value1&lt;/k&gt; &lt;c r="2" n="Column Name 2"&gt; &lt;n&gt;newvalue2&lt;/n&gt; &lt;o&gt;oldvalue2&lt;/o&gt; &lt;/c&gt; &lt;c r="3" n="Column Name 3"&gt; &lt;n&gt;newvalue3&lt;/n&gt; &lt;o&gt;oldvalue3&lt;/o&gt; &lt;/c&gt; &lt;c r="4" n="Column Name 4"&gt; &lt;n&gt;newvalue4&lt;/n&gt; &lt;/c&gt; &lt;c r="5" n="Column Name 5"&gt; &lt;n&gt;newvalue5&lt;/n&gt; &lt;/c&gt; &lt;/U&gt; </pre>
Include non-Key Deleted Values	<p>Under Central Function &gt; Messaging &gt; Message Format. Change notification messages always include a primary key that might have one or many columns to ensure a unique key on which create, update, and delete operations were detected. For Delete operations, the message setting can be set to include only key identifying values, or all values, of the row that has been deleted.</p> <p>If set to true, extraneous column information is included in the change notification message, as in the following example where a delete operation, &lt;D&gt;, includes the key columns (“k”), and non-key values {value3, value4, xsi:nil=“true”}:</p> <pre data-bbox="361 1090 793 1312"> &lt;ops&gt; &lt;D&gt; &lt;k r="0" n="Column Name 0"&gt;value1&lt;/k&gt; &lt;k r="1" n="Column Name 1"&gt;value2&lt;/k&gt; &lt;c r="2" n="Column Name 2"&gt;value3&lt;/c&gt; &lt;c r="3" n="Column Name 3"&gt;value4&lt;/c&gt; &lt;c r="4" n="Column Name 4" xsi:nil="true"&gt;&lt;/c&gt; &lt;/D&gt; &lt;/ops&gt; </pre> <p>If set to false, the “c” columns would not appear in the message.</p>

Parameter/Group	Description
Include non-Updated Values	<p>Under Central Function &gt; Messaging &gt; Message Format. When set to false, change notification messages exclude values that are not changed since the last checkpoint of the table being monitored.</p> <p>For example:</p> <pre data-bbox="406 338 756 642">&lt;U a="true"&gt; &lt;k r="0" n="Column Name 0"&gt;value0&lt;/k&gt; &lt;k r="1" n="Column Name 1"&gt;value1&lt;/k&gt; &lt;c r="2" n="Column Name 2"&gt; &lt;n&gt;newvalue2&lt;/n&gt; &lt;o&gt;oldvalue2&lt;/o&gt; &lt;/c&gt; &lt;c r="3" n="Column Name 3"&gt; &lt;n&gt;newvalue3&lt;/n&gt; &lt;o&gt;oldvalue3&lt;/o&gt; &lt;/c&gt; &lt;/U&gt;</pre>
Include Old Updated Values	<p>Under Central Function &gt; Messaging &gt; Message Format. If set to true, change notification messages include the old values that are being replaced.</p> <p>For example, this message highlights the old values, (<b>&lt;o&gt;</b> <b>&lt;/o&gt;</b>), that would be omitted if the property were set to false.</p> <pre data-bbox="406 815 756 1119">&lt;U a="true"&gt; &lt;k r="0" n="Column Name 0"&gt;value0&lt;/k&gt; &lt;k r="1" n="Column Name 1"&gt;value1&lt;/k&gt; &lt;c r="2" n="Column Name 2"&gt; &lt;n&gt;newvalue2&lt;/n&gt; &lt;o&gt;oldvalue2&lt;/o&gt; &lt;/c&gt; &lt;c r="3" n="Column Name 3"&gt; &lt;n&gt;newvalue3&lt;/n&gt; &lt;o&gt;oldvalue3&lt;/o&gt; &lt;/c&gt; &lt;/U&gt;</pre>

Parameter/Group	Description
Logging Options	<p>Parameter group. Typically, logging options are set to false. Log entries and events can be found in the TDV events log (<code>cs_server_events.log</code>) and/or server log (<code>cs_server.log</code>) files present in the server <code>&lt;TDV_install_dir&gt;/logs</code> directory. Each of the following logging options can be turned on (true) or off (false):</p> <p>Administration—CMS installation or uninstallation, CMS start or stop.</p> <p>Caching—Logging for incrementally maintained caching of views.</p> <p>Change Inference—This setting logs messages received through connected EMS topics. The Input EMS Default Connector and change messages are passed from CDC when triggered by changes to watched data source tables. This setting does not show change data in the logs.</p> <p>Change Inference Messages—This setting logs more detailed messages (including data changes) received through connected EMS topics. The messages logged by this setting can help verify whether change data capture messaging is arriving to the EMS topics and connectors currently listening for change messaging.</p> <p>Data Sources—This setting logs activities on the push-based incremental caching data sources. Metadata Inference—Information captured by this log setting shows dependency analysis messages.</p> <p>Subscriptions—Subscription requests, unsubscribe, and renew subscription requests are logged when this setting is true.</p>
Message Format	<p>All of the messaging parameters can be turned on (true) or off (false). The parameter settings affect the content of the change notification message format. Message formatting is a global setting that affects all change notification messaging received by subscribed clients.</p>

Parameter/Group	Description
Message Handling	<p>Correct change notification is dependent on correct change messaging sent from the monitored data source tables. Messaging ensures that incrementally maintained caches and subscribed users have notification of changes in the source data. If messages from the monitored data sources are malformed or lacking in content, the Change Management Service might treat the message as a systemic error requiring manual assessment and reconfiguration, generate logging errors (in <code>cs_server.log</code>), and possibly abort. If messaging errors occur, check the CMS server log file, and check the Oracle GoldenGate <code>*.prm</code> parameter file for configuration.</p> <pre> PROCEDURE OnError(IN ex VARCHAR(2147483647), IN msg VARCHAR(2147483647), IN t TIMESTAMP) BEGIN   -- Add your code here   CALL /lib/debug/Log(concat('M5 Test[GG erroneous message]---Exception: ',ex));   CALL /lib/debug/Log(concat('M5 Test[GG erroneous message]---Received message: ',msg));   CALL /lib/debug/Log(CAST(concat('M5 Test[GG erroneous message]---Time: ',t) AS VARCHAR(255))); END </pre>
Metadata Inference	<p>For a description, see under parameter group Logging Options.</p>
On Error Procedure	<p>Sets a procedure to execute when a messaging error occurs. Specify the full path name of the TDV Server procedure to call if an invalid message is encountered. The procedure specified must accept three input arguments: a string value for the error, a string value for the offending message, and a timestamp for the time at which the error is reported.</p>
Persistence Store	<p>The TDV resource path name that points to a relational data source container that should be used to host a subscription store table, which is created and maintained by CMS. On application of a valid TDV persistence store location, CMS creates the <code>cis_cms_appl_subs</code> table. That table records client invocations of <code>cms_client_subscribe</code> with data such as the Subscription ID, Application ID, an encoded expiration, the full path of the subscribed view, and subscribed columns if different from the full view.</p> <p>Because the persistence store, <code>cis_cms_appl_subs</code> table, should not be shared between TDV nodes, the Persistence Store target setting should be changed after synchronization by backup server import.</p>
Queue Connector	<p>Under Central Function &gt; Messaging &gt; Internal EMS. The name of the JMS Connector to be used by CMS to create an in-transit event queue. The in-transit event queue is used to maintain in-transit change events in a fault-tolerant manner, while they are being processed by the Central Event server. The value of the Internal EMS Queue Connector server property is the name of the JMS via JNDI Connector. A new or a changed Queue Connector setting requires a CMS restart to initialize the in-transit queue.</p>

Parameter/Group	Description
Reconnection Attempt Count	For a description, see under parameter group Tibco.
Reconnection Attempt Delay	For a description, see under parameter group Tibco.
Reconnection Attempt Timeout	For a description, see under parameter group Tibco.
Security Domain	Under Central Function > Messaging > Output EMS. The LDAP domain value that can be used to restrict topic connection to permitted groups and users for the subscribed view.
Started	Under Central Function. This setting is an indicator that shows whether CMS is started or not. It should not be modified because the value is not a switch. It is an indicator provided to show CMS status. CMS can be started and stopped with the procedures <code>cms_admin_start</code> and <code>cms_admin_stop</code> .
Stop on Any Error	<p>Under Central Function &gt; Fault Tolerance &gt; Message Handling. CMS aborts on receiving source change messages with an invalid message structure. This flag specifies whether CMS aborts if any other types of errors are detected in a source change message notification. Invalid GG configuration is a systemic error.</p> <p>Partial compliance with the expected change notification message schema is a more serious error than inadvertent messages. Some data type mismatches are handled, but a mismatch invalidates all derived incremental caches and sends a notification to all subscribed clients (&lt;ops/&gt;, set with a message property of <code>aborted="true"</code>) to signify a break in the monitored data.</p> <p>When Stop on Any Error is set to false, most messaging errors are still serious, and such errors invalidate all incrementally maintained caches, subscription failure messages, and a purposeful stop of CMS. If a message significantly deviates from the expected CMS schema and is inserted into a monitored input topic or queue, that message is ignored.</p>
Subscriptions	For a description, see under parameter group Logging Options.



Parameter/Group	Description
Tibco	<p>Parameter group. These optional settings override the TIBCO EMS connection factory settings, so that CMS can manage timing and number of connection attempts. The switch from a primary to a backup EMS can initiate a large number of connection and reconnection attempts that can exceed the number allowed.</p> <p>Connection Attempt Count—Number of attempts made to connect to the JMS server.</p> <p>Connection Attempt Delay—Milliseconds to wait before the next connection is made.</p> <p>Connection Attempt Timeout—Milliseconds the connection factory waits before declaring a failure if the attempt is unsuccessful.</p> <p>Reconnection Attempt Count—Number of attempts to make to reconnect to the JMS server. (TIBCO has separate connect and reconnect attempt parameters.)</p> <p>Reconnection Attempt Delay—Milliseconds to wait before the next connection is made.</p> <p>Reconnection Attempt Timeout—Milliseconds the connection factory waits before declaring a failure.</p> <p>For hard connection failures, problems can be reported earlier than these JMS vendor settings indicate.</p>
Topic Connector	<p>Under Central Function &gt; Messaging &gt; Internal EMS. If TDV-Managed Destinations is set to false, this parameter must be set to a valid topic connector for TDV to manage transient cache buffers, which might be needed while an incrementally maintained data cache is being initialized.</p>
Transient Cache Buffering Topic	<p>Under Central Function &gt; Messaging &gt; Internal EMS. If TDV-Managed Destinations is set to false, this parameter must be set to a valid topic so that a transient cache buffer can be set up to provide a temporary topic to handle change messages during cache initialization. The Central Event Server uses this topic to handle change notifications that occur while the cache table is being created and loaded for the first time.</p>



# Legacy Web Services

---

This topic describes managing of legacy web services. The following topics are covered:

- [Limitations for Legacy Web Service Conversion, page 599](#)
- [Converting Legacy Web Service, page 600](#)

## Limitations for Legacy Web Service Conversion

If the data service contains a service or operation that TDV does not support, the resource tree does not display that service or operation. For every object that is not supported in TDV, an error is generated in the `cs_server.log`.

After migration, a report dialog displays messages indicating what needs to be fixed for the web service to be fully functional within TDV. Resolve all warning messages. Consider reconfiguring any older communication protocols between the converted web service and any client applications that consumed the legacy web service.

### Limitations Include

- JMS transport is not supported.
- WSDL access authentication method is not supported.
- Combined authentication methods for service endpoint URLs are not supported.
- Multiple services and multiple ports are not supported.

They are converted to different services, and ports are split into separate web services after migration.

- Wild XML output types are not supported.

If present they cause conversion of the legacy web service to fail.

- Enclosed keystores are not supported.

Before upgrade, the enclosed keystore of the legacy web service needs to be integrated with a server key store.

### Additional Conversion Tips from an Expert

Legacy web services allowed each Composite web service to have its own keystore to store private and public key pairs. After upgrade, the legacy web service needs to be exported and reimported for the Configuration parameter values that define the key pairs of the TDV global keystore to be configured in the Configuration panel. Because the new service doesn't support separate keystores for each new web service.

## Converting Legacy WSDL Data Sources to SOAP Data Sources

If you have existing WSDL data source resources, you can redefine them as SOAP. You must set a TDV configuration parameter. Optionally, after setting the configuration parameter, you can modify your existing data source definitions.

If the WSDL source has multiple services or multiple ports, it is converted to several SOAP data sources based on service and port number. For each SOAP data source, only one service and one port is allowed.

### To convert legacy WSDL data sources into SOAP data sources

1. Open and log into Studio.
2. From the **Administration** menu, choose **Configuration**.
3. Search for or select **Import the WSDL data source as a SOAP data source. (Data Sources > SOAP Sources)**
4. Select True to convert all older legacy WSDL data sources into SOAP data sources.

Click **OK** to save your changes and exit the window.


## Converting Legacy Web Service

Legacy Web services that you might have can be converted, with some limitations, to the currently used Web services paradigm within Studio. In TDV, a legacy WSDL Web service is an older way to create WSDL that has been retained to support existing implementations.


### To convert a legacy web service

1. Make sure that your web service meets the requirements for conversion.
2. In the Studio resource tree locate your legacy web services.

3. Right click the legacy web service that you want to convert.
4. Select Upgrade Legacy Web Service.



5. Type a name you want to give to the copy of your old web service.  
If warnings are listed, your web service might not convert using the wizard. Consider deleting or rewriting your older web services to comply to the updated TDV web services paradigm.
6. Click **OK** twice to close the window and complete the action.
7. Right click the legacy web service that you want to convert.
8. Select Upgrade Legacy Web Service
9. Select the radio button underneath Web Service Name:.
10. Type a name for the converted web service.
11. Click **OK** twice. Depending on the original structure of your legacy web service you might get more than one new web service. For example:



12. Review and test your new web services as necessary.



# Studio User Interface Reference

---

This topic contains panel, toolbar, menus and other user interface reference material. It includes the following topics:

- [Studio Menus, page 603](#)
- [Studio Status Bar, page 605](#)
- [Studio Text Editing, page 606](#)
- [View and Table Editor Panel Reference, page 611](#)
- [Procedure Editor Panel Reference, page 613](#)
- [Trigger Editor Panel Reference, page 619](#)
- [SQL Definition Set Editor, page 624](#)
- [XML Definition Set Editor, page 624](#)
- [WSDL Definition Set Editor, page 626](#)

## Studio Menus

The Studio menus contain options applicable to the current window and context. These menus are subject to change and this section might not include listings for options that you see in your version of Studio.

Almost every container or resource in the Modeler resource tree has a right-click menu. The exact listing of options varies by resource type and version of Studio that you are running. See these sections for a quick summary:

- [File Menu, page 604](#)
- [Edit Menu, page 604](#)
- [View Menu, page 604](#)
- [Resource Menu, page 605](#)

## File Menu

Available menu options vary depending on where you are in Studio. Many of the options standard to most user interfaces have been omitted.

Menu item	Shortcut
Close Active Editor	Ctrl+W
Close All	Ctrl+Shift+W
Open Lineage for "<resource>"	Ctrl+L
Refresh "<resource>"	F5
Refresh All	Shift+F5
Save All	Ctrl+Shift+S
Save As	Alt+S
Show SQL Scratchpad	Ctrl+Q

## Edit Menu

Many of the options standard to most user interfaces have been omitted.

Menu Item	Shortcut
Comment/Uncomment Block	Ctrl+Minus,(Ctrl+Hyphen)
Goto Line	Ctrl+G
Rename <resource>	Shift+F6
Shift-Left	Alt+Left
Shift-Right	Alt+Right

## View Menu

Many of the options standard to most user interfaces have been omitted.

Menu item	Shortcut
Last Tab	Ctrl+Alt+Left



Menu item	Shortcut
Next Tab	Ctrl+Alt+Right
Tab Left	Alt+Left
Tab Right	Alt+Right

## Resource Menu

Available options vary depending on where you are in Studio.

Menu Item	Shortcut
Find Resource	Ctrl+N
Lock Resource	Ctrl+K
Publish <resource>	Ctrl+P
Unlock Resource	Ctrl+U

## Studio Status Bar

The Studio status bar is displayed in the lower right corner of the Studio window. It displays the encryption status of the connection between Studio and TDV. It also displays the current Studio memory usage, and enables you to run JVM garbage collection to free up memory space no longer in use.

Object	Description
Garbage Collection Button	This button initiates a JVM (Java Virtual Machine) garbage collection cycle to free up unused Studio memory. If the TDV Server is on the same computer as the Studio client, this button initiates a garbage collection cycle on the shared JVM.
Studio Memory Use Indicator Bar	This bar shows the total memory available to Studio and the memory it is currently using. Even if TDV Server is on the same computer, this indicator shows only the Studio usage.

Object	Description
Studio-Server Connection Type	A closed-lock icon indicates that SSL protection is being applied to the connection between Studio and the TDV Server.
Encrypted connection—	If the Studio and TDV are on the same computer or if they are both within a secured LAN, it is less important to encrypt the connection between the two.
Unencrypted connection—	
	If the connection must be secured, use the Encrypt check box at login to initiate an SSL connection between Studio and TDV.


## Studio Text Editing

This section explains some text editing features of Studio:


- [Line numbers in the SQL Editor, page 606](#)
- [Studio Code Editing Keyboard Shortcuts, page 607](#)

### Line numbers in the SQL Editor

The following image shows a snapshot of the SQL Editor with a query. The line numbers in the SQL editor aids users in coding.



Additionally, when there is a compile error, it also helps users identify where the error has occurred, as shown below.



## Studio Code Editing Keyboard Shortcuts

Studio keyboard shortcuts help you write and edit code in the SQL, XML, XSLT, or XQuery editors. For a list of keyboard shortcuts go to Help > Editor Quick Help.

Action	Shortcut key	Description
Backspace	Backspace	Delete the previous character at the caret position.
Clear	Esc	Clear all selections from Find All.
Delete to Word Start	Ctrl+Backspace	Delete previous characters until a non-word character.
Delete	Delete	Delete the next character at the caret position.
Delete to Word End	Ctrl+Delete	Delete next characters until a non-word character.
Delete Line	Shift+Delete	Delete current line.
Insert Line Break	Enter	Insert a line break at the caret position.
Split Line	Ctrl+Enter	Insert a line break at the caret position and keep current caret position.

Action	Shortcut key	Description
New Line	Shift+Enter	Start a new line next to the caret line and put caret at the beginning of the new line.
Indent Selection	Tab	Indent the caret line if no selection and all selected lines if there is a selection.
Unindent Selection	Shift+Tab	Unindent the caret line if no selection and all selected lines if there is a selection.
Join Lines	Ctrl+Shift+J	Join the next line with caret line if no selection or join all selected lines as one line if there is a selection.
Toggle Insert/Overwrite	Insert	Toggle the Insert/Overwrite status.
Toggle Rectangular Selection	Ctrl+Backslash	Toggle from regular selection to rectangular selection.
Toggle Case	Ctrl+Shift+U	Toggle the case of the selection.
Undo	Ctrl+Z	Undo the last editing operation.
Redo	Ctrl+Y	Redo the last done editing operation.
Cut	Ctrl+X or Shift+Delete	Cut the currently selected text. If nothing is selected, cut the current line.
Copy	Ctrl+C or Ctrl+Insert	Copy the currently selected text. If nothing is selected, copy the current line.
Paste	Ctrl+V or Shift+Insert	Paste clipboard to the current caret position.
Paste from history	Ctrl+Shift+V or Ctrl+Shift+Insert	Prompt a dialogue to allow user to select one of the previous clipboards and paste it.
Find	Ctrl+F	Prompt a dialogue to allow user to type in a text to search for.
Find Next	F3	Find the next occurrence of the search text.
Find Previous	Shift+F3	Find the previous occurrence of the search text.
Replace	Ctrl+R	Prompt a dialogue to allow user to type in a text to replace with another text.

Action	Shortcut key	Description
Select all	Ctrl+A	Select all the text in the editor.
Move to line start	Home	Move caret to the start of the line.
Move to line end	End	Move caret to the end of the line.
Select to line start	Shift+Home	Select from the current caret position to the line start.
Select to line end	Shift+End	Select from the current caret position to the line end.
Move to document start	Ctrl+Home	Move caret to the start of the code editor.
Move to document end	Ctrl+End	Move caret to the end of the code editor.
Select to document start	Ctrl+Shift+Home	Select from the current caret position to the start of the code editor.
Select to document end	Ctrl+Shift+End	Select from the current caret position to the end of the code editor.
Page up	Page_Up	Move caret position one page up.
Page down	Page_Down	Move caret position one page down.
Select to previous page	Shift+Page_Up	Select from the current caret position up by one page.
Select to next page	Shift+Page_Down	Select from the current caret position down by one page.
Move to previous character	Left	Move caret one character left.
Move to next character	Right	Move caret one character right.
Select previous character	Shift+Left	Select the previous character of the current caret position
Select next character	Shift+Right	Select the next character of the current caret position
Move to previous word	Ctrl+Left	Move caret to the previous word.

Action	Shortcut key	Description
Move to next word	Ctrl+Right	Move caret to the next word.
Select previous word	Ctrl+Shift+Left	Select the current caret position to the first character position before it.
Select next word	Ctrl+Shift+Right	Select the current caret position to the first character position after it.
Move to previous line	Up	Move caret up by one line.
Move to next line	Down	Move caret down by one line.
Select previous line	Shift+Up	Select from the caret position up by one line,
Select next line	Shift+Down	Select from the caret position down by one line,
Goto Line	Ctrl+G	Prompt a dialogue to let user type a line index and scroll to it.
Select word at caret	Ctrl+W	Select the current word.
Select to matching bracket	Ctrl+B	Select the current block that starts and ends with two matching brackets.
Duplicate selection	Ctrl+D	Duplicate the selection. If no selection, the caret line will be duplicated.
Comments	Ctrl+Dash	Comment a line or selected lines for SQL, XML and Xquery editors.
Manual Fold selection	Ctrl+Period	Creates a folding which contains the currently selected text.
Expand folding	Ctrl+Equals	Expand the current manual folding.
Expand all foldings	Ctrl+Shift+Equals	Expand all the foldings created manually.

## View and Table Editor Panel Reference

The editor has a collection of right-pane panels for viewing and editing view properties, depending on what is available for the resource you are working with. You can open these panels by clicking tabs at the bottom of the right pane:

- [Model Panel, page 611](#)
- [Grid Panel, page 611](#)
- [SQL Panel, page 612](#)
- [Columns Panel, page 612](#)
- [Indexes Panel, page 612](#)
- [Foreign Keys Panel, page 612](#)
- [Cardinality Statistics Panel, page 612](#)

Any combination of the following four panels can appear below the right-pane panels:

- [Rebind Panel, page 612](#), which appears when you click the **Show Rebind Panel** button, so you can bind a view (or procedure) to sources whose names or locations have changed.
- [Result Panel, page 613](#), which appears when results from executing a view (or procedure) execution results are available.
- [Execution Plan Panel, page 613](#), which appears when you click the **Show Execution Plan** button.
- [Lineage Panel](#), which appears when you click the **Show Lineage Panel** button.

After you have created a view or procedure, these four panels are available so you can understand and troubleshoot the view or procedure. You can dismiss them by clicking the button on the right side of the tab.

### Model Panel

Use the **Model** panel as a graphical tool to add resources to a view, and to jump-start design of the query that defines the view. For further details, see [Designing a View and Table Resource, page 138](#).

### Grid Panel

For details on using the Grid panel, see [Designing a View in the Grid Panel, page 148](#).

## SQL Panel

For details on using the **SQL** panel, see [Designing SQL for a View in the SQL Panel, page 155](#).

## Columns Panel

See [Designing Column Projections Using the Columns Panel, page 162](#) for more information.

## Indexes Panel

For details about using this panel, see [Defining Primary Key for a View or Table in the Indexes Panel, page 156](#).

## Foreign Keys Panel

For details about using this panel, see [Defining a Foreign Key for a View or Table Resource, page 157](#).

## Cardinality Statistics Panel

The **Cardinality Statistics** panel enables TDV to collect table and column boundary statistics for a cached view (and for data sources and tables) so that the TDV query engine can use those statistics to optimize query execution plans. For details, see [Updating the Query Execution Plan, page 486](#).

The configuration and usage of cardinality statistics is described in [Creating Cardinality Statistics for Cost-Based Optimization, page 489](#). Refer to the topic on [Creating Cardinality Statistics for a View, page 490](#) for information on how this panel is configured and used.

Cardinality statistics are also used to optimize parallel cache loading. See [Setting Up the Parallel Cache Option, page 443](#) for more information.

## Rebind Panel

The Rebind panel allows you to rebind the view resources to the appropriate sources if the names or locations of those sources have changed. Display the Rebind panel by clicking the Show Rebind Panel button on the editor toolbar. The Rebind panel displays the schema of the resources that the given view depends on.



For details about using this panel, see [Rebinding a View, page 165](#).

## Result Panel

The Result panel appears in the bottom area of a view or procedure editor panel when you click the Execute button on the editor toolbar. For queries, the Result panel displays up to 50 lines of execution results. For some extremely large results, such as those generated by using EXTEND on an array to generate BIGINT number values, some of the data might be truncated without a visual indication by Studio.

For transformations, the Result panel displays the target schema, XML text, or query output.

When you close the Result panel, any query or procedure execution in progress for the Studio display is canceled.

For details, see [Generating a Query Execution \(Explain\) Plan, page 164](#) and [Executing a Procedure in Studio, page 224](#).

## Execution Plan Panel

The Execution Plan panel displays information about the query like an estimate for how much data will be returned, the SQL and projections processed for each command, the data sources involved, and so on. You can also execute the query from the Execution Plan panel. The panel opens when you click the Show Execution Plan button in the toolbar of any view editor panel, the procedure editor panel for a SQL Script or Parameterized Query, or from the SQL tab of the OLAP View editor.

**Note:** The words “Identity Simulated” appear in the upper right corner of the Execution Plan if row-based security is in use and you are using a simulated identity to test that the results are as expected. This is done using the **Test Identity** tab in the View editor.

See [Working with the SQL Execution Plan, page 477](#) for information about generating and understanding the execution plan.

## Procedure Editor Panel Reference

Studio provides a procedure editor for creating and modifying various types of procedures.

This section introduces the following panels:

- [Introduction to Procedure Panels and Tabs](#), page 614
- [Model Panel](#), page 615
- [Grid Panel](#), page 616
- [SQL Script Panel](#), page 616
- [SQL Panel](#), page 616
- [Parameters Panel](#), page 617
- [Data Map Panel](#), page 617
- [XSLT Panel for XSLT Transformations](#), page 617
- [XSLT Panel for XSLT Procedures](#), page 618
- [XQuery Panel](#), page 618
- [Inputs Panel](#), page 618
- [Outputs Panel](#), page 618
- [XSLT Debug Input Panel](#), page 619
- [XSLT Debug Output Panel](#), page 619

The order of the lower-panel tabs (the last four in the list above) depends on the order in which you click a button (in the case of the **Rebind** panel) or execute procedures.

## Introduction to Procedure Panels and Tabs

The procedure editor offers a different set of panels for each type of procedure. To open a panel, click the corresponding tab along the bottom of the editor.

Procedure Type	Panels											
	Model	XQuery	Grid	Data Map	XSLT	Inputs	Outputs	SQL Script	SQL	Parameters	Caching	Info
SQL script								x		x	x	x
Custom Java procedure										x	x	x
Packaged query									x	x	x	x

Procedure Type	Panels											
	Model	XQuery	Grid	Data Map	XSLT	Inputs	Outputs	SQL Script	SQL	Parameters	Caching	Info
Parameterized query	x		x					x		x	x	x
Physical stored procedure										x	x	x
XML to tabular mapping										x		x
XSLT transformation				x	x	x	x				x	x
XSLT procedure					x					x	x	x
Streaming transformation				x		x	x				x	x
XQuery transformation	x	x				x	x				x	x
XQuery procedure		x								x	x	x

## Model Panel

The **Model** panel is available for Parameterized Queries and XQuery Transformations.

- For a parameterized query, use the Model panel to add resources. You can add any type of table (relational, LDAP, delimited file) and a procedure that outputs either a set of scalars or one cursor. This panel works with the Grid Panel where you can specify the output column projections and the constraints on a query. The Model panel is permanently disabled if you edit the script in the SQL Script Panel for a parameterized query.
- For an XQuery transformation, use this panel for specifying the sources and target values that provide the data for the output XML document. The **Model** panel is permanently disabled if you edit the script in the **XQuery** panel.

For information about using the **Model** panel for XQuery transformations, see [Creating an XQuery Transformation, page 240](#).

## Grid Panel

The **Grid** panel in the procedure editor is available for Parameterized Queries. Use this panel for including columns in the output that is obtained when a parameterized query is executed. This panel works with the Model Panel. The Grid panel is permanently disabled if you edit the script in the SQL Script Panel for the parameterized query.

## SQL Script Panel

The **SQL Script** panel is available for SQL scripts and Parameterized Queries. This panel has several editing capabilities including keyword high-lighting and syntax formatting. You can also drag resources from the resource tree and drop them into this panel at the cursor position.

Use this panel to formulate and edit the SQL script for a procedure. This panel works with the Parameters Panel. The parameters you define in the **SQL Script** panel must match the parameters designed in the **Parameters** panel, including the order in which they are provided. Editing text in this panel permanently disables the **Model** and **Grid** panels for a parameterized query.

For details about using this panel, see [Java Procedures, page 195](#).

## SQL Panel

The **SQL** panel is available for Packaged Queries. Use this panel to formulate and edit the SQL native to the data source targeted for your packaged query.

This panel works with the Parameters Panel. The parameters you use in this panel must match the parameters designed in the Parameters panel, including the order in which they are provided.

For details about using this panel, see [Creating a Packaged Query, page 204](#).

## Parameters Panel

The Parameters panel is available for custom Java Procedures, SQL scripts, certain Transformations, Packaged Queries, and Parameterized Queries. This panel displays the input and output parameters for a procedure, and works with the SQL Script panel (or the SQL panel). The parameters you design in this panel must match the parameters defined in the SQL Script panel (or the SQL panel) including the order in which they are provided.

- For Java procedures and transformations, you can only view the parameters in the **Parameters** panel, because the parameters are defined in the source Java code (for a Java procedure) and in the XML or WSDL (for a transformation). Each parameter is displayed with its TDV JDBC data type and the data type native to the corresponding data source. The output parameters shown in this panel are rendered as columns in the result set when you execute the procedure.
- For a SQL script, packaged query, or parameterized query, use the **Parameters** panel to design and edit the parameters.

## Data Map Panel

The Data Map panel is available for certain types of transformations (XSLT and streaming), and lets you transform XML data into tabular data by mapping XML sources to target columns. It displays the hierarchical relationship among the elements in the input XML document with the corresponding data type for each element. The Source column displays the structure of the input XML document, and the Target column the structure of the output table. The output items you specify in the Target column are rendered as columns in the result set when you execute the transformation.

This panel is permanently disabled if you edit the XSLT in the XSLT Panel for XSLT Transformations.

## XSLT Panel for XSLT Transformations

An XSLT panel is available for XSLT transformations. Use this panel to view the XSLT for the output. The system auto-generates the XSLT when you use the Data Map Panel to design the output for the transformation.

You can edit the XSLT in this panel, but after you start editing the XSLT, the mapping in the **Data Map** panel is permanently disabled. When editing XSLT directly, you can use the same keyboard shortcuts as those used to edit SQL. See [Studio Code Editing Keyboard Shortcuts, page 607](#).

## XSLT Panel for XSLT Procedures

An **XSLT** panel is available for XSLT procedures. Use this panel to view the XSLT for the output.

You can edit the XSLT in this panel, or prepare XSLT in any editor and paste it into this panel. When editing XSLT in this panel, you can use the same keyboard shortcuts as those used to edit SQL. See [Studio Code Editing Keyboard Shortcuts](#), page 607.

## XQuery Panel

The **XQuery** panel is available for XQuery transformations and procedures. Use this panel to view an XQuery that returns an XML document when the transformation is executed. The system auto-generates the XQuery when you use the Model Panel to design the output for the transformation.

You can edit the XQuery in this panel, but after you start editing the XQuery, the **Model** panel is permanently disabled. When editing XQuery directly, you can use the same keyboard shortcuts as those used to edit SQL. See [Studio Code Editing Keyboard Shortcuts](#), page 607.

## Inputs Panel

The **Inputs** panel is available for certain types of transformations (XSLT, streaming, and XQuery). Use this panel to:

- View the input columns if you have used the **Data Map** panel to generate the XSLT for an XSLT transformation.
- Supply global input parameters for an XQuery transformation.

## Outputs Panel

The **Outputs** panel is available for certain types of transformations (XSLT, streaming, and XQuery). Use this panel to:

- View the output columns if you have used the **Data Map** panel to generate the XSLT for an XSLT transformation. If you edit the XSLT, disabling the **Data Map** panel, you must use the **Outputs** panel to manually design the output columns for the transformation.
- Supply global output parameters for an XQuery transformation. If you edit the XQuery, disabling the **Model** panel, you must choose an appropriate schema for the output XML document.

The output parameters shown in the **Outputs** panel are rendered as columns in the result set when you execute the transformation.

For details about using the **Outputs** panel, see [Adding Target Columns through the Outputs Panel \(XSLT\)](#), page 239.

## XSLT Debug Input Panel

The **XSLT Debug Input** panel is available for XSLT transformations, and opens below the main procedure editor panel when a transformation is executed. Use this panel to view the input to the XSLT. The result columns are displayed with data.

## XSLT Debug Output Panel

The **XSLT Debug Output** panel is available for XSLT transformations, and opens below the main procedure editor panel when a transformation is executed. Use this panel to view the output from the XSLT. The result columns are displayed with the created XML.

## Trigger Editor Panel Reference

Studio provides a trigger editor for configuration and modification of triggers. You can create a trigger as you would create any other resource: with a right click from an appropriate container within **My Home** or **Shared** folders. The trigger editor opens when you create a trigger. At any time later, you can open a trigger editor by double-clicking the trigger name in the resource tree.

Triggers are also present in a simplified form as part of the configuration panels used for scheduling cache refreshes and cardinality statistics gathering. If more scheduling complexity is wanted for cache refreshes or statistics gathering, then triggers can be created to invoke either the `/lib/resource/RefreshResourceCache` or the `/lib/resource/RefreshResourceStatistics` procedure.

When scheduled resources from previous TDV releases are imported, those schedules are displayed as triggers in the Studio resource tree.

The trigger editor has two tabs:

- [Condition Tab](#), page 620
- The Info tab, described in [Getting Information about a Resource](#), page 44

## Condition Tab

The Enable Trigger check box is at the top of the Condition tab. This check box must be selected to activate a trigger.

The Trigger Condition tab has four panes in which you specify the trigger information:

- [Condition Types for a Trigger, page 310](#) (upper-left pane)
- [Condition Pane, page 620](#) (upper-right pane)
- [Action Types for a Trigger, page 313](#) (lower-left pane)
- [Action Pane, page 621](#) (lower-right pane)

The selections in the panes on the left (Condition Type and Action Type) determine what options are displayed in the panes on the right (Condition and Action). For example, the trigger editor below shows the options for a condition type of Timer Event and an action type of Send E-mail.

### Condition Pane

The contents of the **Condition** pane depend on the condition type selected.

### JMS Event Conditions

Prior to use of the JMS event trigger, you need to configure a JMS connector with a queue or topic connection factory for use with TDV. See “Configuring TDV Data Connections” in the *TDV Administration Guide* for information about the JMS configuration requirements. See [Creating a JMS Event Trigger, page 314](#) for how to define a JMS event trigger.

### System Event Conditions

You specify the system event name. See [Creating a System Event Trigger, page 315](#).

### Timer Event Conditions

You specify the frequency for when the trigger occurs. See [Creating a Timer Event Trigger, page 318](#) for more details.

**Only once per cluster**—When checked (the default), specifies that the trigger action be performed only once in the cluster. That is, if the trigger action is invoked on one node of the cluster, the other nodes are notified and the trigger action is not invoked again. When unchecked, the trigger action is invoked on every node of the cluster.



## User-Defined Event Conditions

You specify the user-defined event name. See [Creating a User-Defined Event Trigger](#), page 320 for more details.

## Action Pane

The contents of the **Action** pane depend on the action type (described in [Action Types for a Trigger](#), page 313). A description of the options for each action type are as follows.

### Execute Procedure

This action lets you trigger execution of a procedure without sending any notification. The Action pane lists the fields to fill in:

**Procedure Path**—Specify the procedure to execute:

- Type the procedure path, or open the procedure and copy the path and name from the Name field at the top of the procedure's Info tab.
- Click the Browse button to open a dialog box that lists the resource tree folders that contain procedures. When you make a valid selection, the OK button is ungrayed.

**Parameter Values**—Specify any parameters and values that the procedure or view uses:

- Click the Edit button to open a dialog box if the procedure takes parameters. Type values in the fields. For fields left blank, check or leave checked the Null box to the right of the field. When you click OK, an ordered, comma-separated list of parameter values is posted to the Parameter Values field.
- Type (or edit after copy-pasting a starter set from the Parameter Values field) an ordered, comma-separated list of input parameter values.

**Note:** Only static input parameters can be used by the trigger, but the procedure invoked can use whatever variables it might require.

**Exhaust output cursors**—If the procedure is a SQL script that contains a PIPE cursor, and if the pipe needs to fully execute and load all rows to complete execution of a trigger (for example, to email a result set) checking this box forces the trigger to wait until all the rows are buffered and read before completing. If you leave this unchecked, the trigger returns while the pipe is buffering, cutting off the buffering of the pipe.

**Note:** As soon as you begin typing text in any field of the dialog box, the NULL box for that field is unchecked. If you decide to delete all text from the field, be sure to recheck its NULL box.

## Gather Statistics

This action lets you specify a data source for which to gather statistics data.

**Data Source Path**—Specify the data source path and name:

- Type the data source path; or open the data source, copy the contents from the Name field at the top of the Info tab, and paste it here.
- Click the Browse button to open a dialog box that lists the resource tree folders that contain data sources. When you make a valid selection, the OK button is ungrayed.

To see how this action works, select the data source to be scanned for data statistics. After creating the trigger, view the **Triggers** console in **Studio Manager** to check if the trigger fired as scheduled.

## Reintrospect Data Source

This action lets you specify a data source to reintrospect.

**Data Source Path**—Specify the data source path and name:

- Type the data source path; or open the data source, copy the contents from the Name field at the top of the Info tab, and paste it here.
- Click the Browse button to open a dialog box that lists the resource tree folders that contains data sources. When you make a valid selection, the OK button is ungrayed.

**To, Cc, Bcc, Reply-To**—These work the same as in ordinary email applications. You can specify a list of email addresses by separating them with commas (,) or semicolons (;). The email recipients are sent a notification with the result of the output of the procedure or view.

**Message Subject, Message Body**—These work the same as in ordinary email applications.

**Do Not Persist Detected Changes**—Check this if you want only a report about the changes detected in the data source, and not save the changes. This option allows the TDV developer or administrator to assess the impact of data source changes to the TDV model before actually applying them.

**Do Not Send If No Changes Detected**—Check this if you do not want email sent if no changes were detected.

To see how this action works, select the data source to be reintrospected. After creating the trigger, view the **Triggers** console in **Studio Manager** to check if the trigger fired as scheduled. Also verify if the notification was sent to the e-mail recipients.

## Send E-mail

This action lets you specify a procedure or view to execute and then send the results through email to one or more recipients. The Action pane lists the fields to fill in:

**Resource Path**—Specify a procedure or view to execute:

- Type the resource path; or open the resource, copy the contents from the Name field at the top of the Info tab, and paste it here.
- Click the Browse button to open a dialog box that lists the resource tree folders that contain procedures or views. When you make a valid selection, the OK button is ungrayed.

**Note:** Before scheduling execution, set the From Address and SMTP configuration parameters.

**Parameter Values**—Specify any parameters and values that the procedure or view uses:

- Click the Edit button to open a dialog box if the procedure or view takes parameters. Type values in the fields. For fields left blank, check or leave checked the Null box to the right of the field. When you click OK, an ordered, comma-separated list of parameter values is posted to the Parameter Values field.
- Type (or edit after copy-pasting a starter set from the Parameter Values field) an ordered, comma-separated list of input parameter values.

**Note:** For an example of a procedure and its parameter values, see [Execute Procedure, page 621](#).

**To, Cc, Bcc, Reply-To**—These work the same as in ordinary email applications. You can specify a list of email addresses by separating them with commas (,) or semicolons (;). The email recipients are sent a notification with the result of the output of the procedure or view.

**Message Subject, Message Body**—These work the same as in ordinary email applications.

**Include Summary**—Check this if you want to include a summary of the notification.

**Do Not Send If No Results**—Check this if you do not want to receive notification if there are no results.

To see how the **Send E-mail** action works, select the transformation to be executed. After creating the trigger, view the **Triggers** console in **Studio Manager** to check if the trigger was fired as scheduled. Also verify if the notification was sent to the mail recipients.

## SQL Definition Set Editor

The SQL definition set editor lets you create your own SQL type definitions, exceptions, and constants.

- [SQL Definition Set Editor Toolbars, page 624](#)

See [Creating a SQL Definition Set, page 299](#) for more information.

### SQL Definition Set Editor Toolbars

The following table lists the buttons that appear on the **Types**, **Exceptions** and **Constants** panel toolbars for SQL definition sets, and explains what they do. To find out the purpose of any panel button, let the cursor hover over it so its name appears. You can then look it up in the table below, which lists the buttons in their order on the toolbar.

Label	Functionality
Add	<p>Opens a window where you can choose a data type for a type definition you want to add to a definition set. The new type definition is automatically assigned a unique, descriptive name that you can change by selecting Rename from the context menu in the Name column.</p> <p>Available data types are listed in <a href="#">About Definition Sets, page 297</a>.</p>
Change Type	<p>(<b>Types</b> panel only) Opens a <b>Choose Data Type</b> dialog box in which you can change the column type.</p> <p>Available data types are listed in <a href="#">About Definition Sets, page 297</a>.</p>
Move Parameter Up	Moves a column up, down, to the left, or to the right, respectively.
Move Parameter Down	These buttons are enabled only if an entry in the definition set is complex such as a CURSOR and it has non-complex base types (for example, binary, decimal, integer, string, time, or array) under it which can be reordered.
Move Parameter Out	
Move Parameter In	

## XML Definition Set Editor

The XML definition set editor lets you create XML schema definitions. You can import definitions from existing XML files, validate definitions, format definitions, and create definitions from an XML instance.

This editor has two panels—**XML Schema** and **Info**—which are described in the following sections:

- [XML Schema Panel \(XML Definition Set\), page 625](#)
- [XML Schema Panel Toolbar, page 625](#)

See [Creating an XML Definition Set, page 302](#) for more information.

## XML Schema Panel (XML Definition Set)

The **XML Schema** panel displays the XML schema, element declarations, and type definitions for the selected XML definition set. You can type the schema definitions or import definitions from an existing file, validate the schema, format the schema, or create definitions from an XML instance. You can also add definition source files that can be referenced from other sources in the definition set.

Studio displays keywords in orange type and literal definitions in blue type.

For a table of toolbar buttons, see [XML Schema Panel Toolbar, page 625](#).

## XML Schema Panel Toolbar

The following table lists the buttons that appear on the **XML Schema** panel toolbar, and explains what they do. To find out the purpose of any panel button, let the cursor hover over it so its name appears. You can then look it up in the table below, which lists the buttons in their order on the toolbar.

Label	Functionality
Import XML Schema Definitions from File(s)	Opens a dialog box in which to type or browse to the location of a file containing an XML schema definition.
Validate XML Schema Definitions	Requests validation from the definition set editor. If it is not valid, an error box describes the error and its line and column. (The current cursor location is shown in the lower right corner of the panel in line:column format.)
Format XML Schema Definitions	Formats the definition set with hierarchical indentation, and with keywords in orange type and literal definitions in blue type.
Create XML Schema Definitions from XML Instance	Opens a window in which to navigate to an existing XML instance. When you click Open, the XML file appears on the XML Schema panel of the editor.

Label	Functionality
Add Definition Source	Opens an Add Definition Set Source window where you can type a name for a definition source. The name is added to the Select Definition Source drop-down list, from which it can be referenced from other sources within the definition set.
Delete Definition Source	Deletes the definition source currently displayed in the Select Definition Source drop-down list (except XML DefinitionSet).
Rename Definition Source	Opens a dialog box in which to enter a new name for the definition source named in the Select Definition Source drop-down list. All references to the old name will be updated.
Select Definition Source	Provides a drop-down list of available definition sources (XML DefinitionSet plus any you have added).

## WSDL Definition Set Editor

The WSDL definition set editor lets you create your own WSDL definition set. You can import WSDL and XML schema definitions, validate definitions, and format definitions. This editor has two panels—**WSDL** and **Info**—which are described in the following sections:

- [WSDL Panel, page 626](#)
- [WSDL Panel Toolbar, page 627](#)

See [Creating a WSDL Definition Set, page 304](#) for more information.

### WSDL Panel

The **WSDL** panel displays the XML schema defined for the WSDL, including type definitions, message definitions, port type definitions, binding definitions, and service definitions.

Studio displays keywords in orange type and literal definitions in blue type.

In the **WSDL** panel, you can type the definitions or import WSDL and XML schema definitions from a file. You can also add definition source files that can be referenced from other sources in the definition set.

## WSDL Panel Toolbar

The following table lists the buttons that appear on the **WSDL** panel toolbar, and explains what they do. To find out the purpose of any panel button, let the cursor hover over it so its name appears. You can then look it up in the table below, which lists the buttons in their order on the toolbar.

Label	Functionality
Import WSDL or XML Schema Definitions from File(s)	Opens a dialog box in which to type or browse to the location of a file containing an XML schema definition.
Validate WSDL or XML Schema Definitions	Requests that the definition set editor validate the definition set. If it is valid, a dialog box says so; if it is not valid, an error dialog box describes the error and at which line and column of the definition the error was found. (The current cursor location is shown in the lower right corner of the panel in line:column format (for example <b>1:100</b> for line 1, column 100).
Format WSDL or XML Schema Definitions	Formats the definition set with hierarchical indentation, and with keywords in orange type and literal definitions in blue type.
Add Definition Source	Opens an Add Definition Set Source window where you can type a name for a definition source. The name is added to the Select Definition Source drop-down list, from which it can be referenced from other sources within the definition set.
Delete Definition Source	Deletes the definition source currently displayed in the Select Definition Source drop-down list (except WSDL DefinitionSet).
Rename Definition Source	Opens a dialog box in which to enter a new name for the definition source named in the Select Definition Source drop-down list. All references to the old name will be updated.
Select Definition Source	Provides a drop-down list of available definition sources (WSDL DefinitionSet plus any you have added).

