

TIBCO Enterprise Message Service™

C and COBOL Reference

*Software Release 8.1
April 2014*

Important Information

SOME TIBCO SOFTWARE EMBEDS OR BUNDLES OTHER TIBCO SOFTWARE. USE OF SUCH EMBEDDED OR BUNDLED TIBCO SOFTWARE IS SOLELY TO ENABLE THE FUNCTIONALITY (OR PROVIDE LIMITED ADD-ON FUNCTIONALITY) OF THE LICENSED TIBCO SOFTWARE. THE EMBEDDED OR BUNDLED SOFTWARE IS NOT LICENSED TO BE USED OR ACCESSED BY ANY OTHER TIBCO SOFTWARE OR FOR ANY OTHER PURPOSE.

USE OF TIBCO SOFTWARE AND THIS DOCUMENT IS SUBJECT TO THE TERMS AND CONDITIONS OF A LICENSE AGREEMENT FOUND IN EITHER A SEPARATELY EXECUTED SOFTWARE LICENSE AGREEMENT, OR, IF THERE IS NO SUCH SEPARATE AGREEMENT, THE CLICKWRAP END USER LICENSE AGREEMENT WHICH IS DISPLAYED DURING DOWNLOAD OR INSTALLATION OF THE SOFTWARE (AND WHICH IS DUPLICATED IN THE LICENSE FILE) OR IF THERE IS NO SUCH SOFTWARE LICENSE AGREEMENT OR CLICKWRAP END USER LICENSE AGREEMENT, THE LICENSE(S) LOCATED IN THE "LICENSE" FILE(S) OF THE SOFTWARE. USE OF THIS DOCUMENT IS SUBJECT TO THOSE TERMS AND CONDITIONS, AND YOUR USE HEREOF SHALL CONSTITUTE ACCEPTANCE OF AND AN AGREEMENT TO BE BOUND BY THE SAME.

This document contains confidential information that is subject to U.S. and international copyright laws and treaties. No part of this document may be reproduced in any form without the written authorization of TIBCO Software Inc.

TIBCO, Two-Second Advantage, The Power of Now, TIB, Information Bus, TIBCO Enterprise Message Service, TIBCO Rendezvous, TIBCO Enterprise, TIBCO SmartSockets, TIBCO ActiveMatrix BusinessWorks, and TIBCO Hawk are either registered trademarks or trademarks of TIBCO Software Inc. in the United States and/or other countries.

Enterprise Java Beans (EJB), Java Platform Enterprise Edition (Java EE), Java 2 Platform Enterprise Edition (J2EE), and all Java-based trademarks and logos are trademarks or registered trademarks of Oracle Corporation in the U.S. and other countries.

All other product and company names and marks mentioned in this document are the property of their respective owners and are mentioned for identification purposes only.

THIS SOFTWARE MAY BE AVAILABLE ON MULTIPLE OPERATING SYSTEMS. HOWEVER, NOT ALL OPERATING SYSTEM PLATFORMS FOR A SPECIFIC SOFTWARE VERSION ARE RELEASED AT THE SAME TIME. SEE THE README FILE FOR THE AVAILABILITY OF THIS SOFTWARE VERSION ON A SPECIFIC OPERATING SYSTEM PLATFORM.

THIS DOCUMENT IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENT COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THIS DOCUMENT. TIBCO SOFTWARE INC. MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S) AND/OR THE PROGRAM(S) DESCRIBED IN THIS DOCUMENT AT ANY TIME.

THE CONTENTS OF THIS DOCUMENT MAY BE MODIFIED AND/OR QUALIFIED, DIRECTLY OR INDIRECTLY, BY OTHER DOCUMENTATION WHICH ACCOMPANIES THIS SOFTWARE, INCLUDING BUT NOT LIMITED TO ANY RELEASE NOTES AND "READ ME" FILES.

Copyright © 1997-2014 TIBCO Software Inc. ALL RIGHTS RESERVED.

TIBCO Software Inc. Confidential Information

Contents

| | |
|--|--------------|
| Tables | .xvii |
| Preface | xix |
| Changes from the Previous Release of this Guide | xx |
| Related Documentation | xxi |
| TIBCO Enterprise Message Service Documentation | xxi |
| Other TIBCO Product Documentation | xxi |
| Third Party Documentation | xxii |
| Typographical Conventions | xxiii |
| Connecting with TIBCO Resources | xxvi |
| How to Join TIBCOCommunity | xxvi |
| How to Access TIBCO Documentation | xxvi |
| How to Contact TIBCO Support | xxvi |
| Chapter 1 Introduction | 1 |
| Overview | 2 |
| Excluded Features and Restrictions | 3 |
| Naming Conventions and Length Limitations | 3 |
| Strings and Character Encodings | 4 |
| IBM z/OS and IBM i (i5)—COBOL and C | 4 |
| Configuring C and COBOL Clients for Fault-Tolerant Connections | 5 |
| Chapter 2 Messages | 7 |
| Parts of a Message | 8 |
| Body Types | 9 |
| Headers | 10 |
| Properties | 14 |
| Setting Message Properties | 14 |
| EMS Properties | 14 |
| JMS Properties | 16 |
| Message Selectors | 17 |
| Data Type Conversion | 20 |
| tibemsMsg | 21 |
| tibemsMsg_Acknowledge | 25 |

| | |
|--|----|
| tibemsMsg_ClearBody | 27 |
| tibemsMsg_ClearProperties | 28 |
| tibemsMsg_Create | 29 |
| tibemsMsg_CreateCopy | 30 |
| tibemsMsg_CreateFromBytes | 31 |
| tibemsMsg_Destroy | 32 |
| tibemsMsg_GetAsBytes | 33 |
| tibemsMsg_GetAsBytesCopy | 34 |
| tibemsMsg_GetBodyType | 36 |
| tibemsMsg_GetByteSize | 37 |
| tibemsMsg_GetCorrelationID | 38 |
| tibemsMsg_GetDeliveryMode | 40 |
| tibemsMsg_GetDeliveryTime | 41 |
| tibemsMsg_GetDestination | 42 |
| tibemsMsg_GetEncoding | 43 |
| tibemsMsg_GetExpiration | 44 |
| tibemsMsg_GetMessageID | 45 |
| tibemsMsg_GetPriority | 46 |
| tibemsMsg_Get Property | 47 |
| tibemsMsg_GetPropertyNames | 50 |
| tibemsMsg_GetRedelivered | 51 |
| tibemsMsg_GetReplyTo | 52 |
| tibemsMsg_GetTimestamp | 53 |
| tibemsMsg_GetType | 54 |
| tibemsMsg_MakeWriteable | 55 |
| tibemsMsg_Print | 56 |
| tibemsMsg_PrintToBuffer | 57 |
| tibemsMsg_PropertyExists | 58 |
| tibemsMsg_Recover | 59 |
| tibemsMsg_SetCorrelationID | 60 |
| tibemsMsg_SetDeliveryMode | 62 |
| tibemsMsg_SetDestination | 63 |
| tibemsMsg_SetEncoding | 64 |
| tibemsMsg_SetExpiration | 65 |
| tibemsMsg_SetMessageID | 66 |
| tibemsMsg_SetPriority | 67 |
| tibemsMsg_Set Property | 68 |
| tibemsMsg_SetRedelivered | 71 |
| tibemsMsg_SetReplyTo | 72 |
| tibemsMsg_SetTimestamp | 73 |
| tibemsMsg_SetType | 74 |
| tibemsBytesMsg | 75 |
| tibemsBytesMsg_Create | 76 |
| tibemsBytesMsg_GetBodyLength | 77 |
| tibemsBytesMsg_GetBytes | 78 |

| | |
|--|-----|
| tibemsBytesMsg_Read | 79 |
| tibemsBytesMsg_ReadBytes | 82 |
| tibemsBytesMsg_Reset | 84 |
| tibemsBytesMsg_SetBytes | 85 |
| tibemsBytesMsg_Write | 86 |
| tibemsBytesMsg_WriteBytes | 89 |
| tibemsMapMsg | 90 |
| tibemsMapMsg_Create | 91 |
| tibemsMapMsg_Get | 92 |
| tibemsMapMsg_GetMapNames | 96 |
| tibemsMapMsg_ItemExists | 97 |
| tibemsMapMsg_Set | 98 |
| tibemsMapMsg_SetBytes | 103 |
| tibemsObjectMsg | 105 |
| tibemsObjectMsg_Create | 106 |
| tibemsObjectMsg_GetObjectBytes | 107 |
| tibemsObjectMsg_SetObjectBytes | 108 |
| tibemsStreamMsg | 109 |
| tibemsStreamMsg_Create | 111 |
| tibemsStreamMsg_FreeField | 112 |
| tibemsStreamMsg_Read | 113 |
| tibemsStreamMsg_ReadBytes | 116 |
| tibemsStreamMsg_ReadField | 117 |
| tibemsStreamMsg_Reset | 118 |
| tibemsStreamMsg_Write | 119 |
| tibemsStreamMsg_WriteBytes | 123 |
| tibemsTextMsg | 124 |
| tibemsTextMsg_Create | 125 |
| tibemsTextMsg_GetText | 126 |
| tibemsTextMsg_SetText | 127 |
| tibemsData | 128 |
| tibemsDeliveryMode | 129 |
| tibemsNpCheckMode | 130 |
| tibemsMsgCompletionCallback | 131 |
| tibemsMsgEnum | 132 |
| tibemsMsgEnum_Destroy | 133 |
| tibemsMsgEnum_GetNextName | 134 |
| tibemsMsgField | 135 |
| tibemsMsgField_Print | 138 |
| tibemsMsgField_PrintToBuffer | 139 |
| tibemsMsgType | 140 |

| | |
|---------------------------------------|------------|
| Chapter 3 Destination | 141 |
| Destination Overview | 142 |
| tibemsDestinationType | 145 |
| tibemsDestination | 146 |
| tibemsDestination_Copy | 147 |
| tibemsDestination_Create | 148 |
| tibemsDestination_Destroy | 149 |
| tibemsDestination_GetName | 150 |
| tibemsDestination_GetType | 151 |
| tibemsQueue | 152 |
| tibemsQueue_Create | 153 |
| tibemsQueue_Destroy | 154 |
| tibemsQueue_GetQueueName | 155 |
| tibemsTemporaryQueue | 156 |
| tibemsTemporaryTopic | 157 |
| tibemsTopic | 158 |
| tibemsTopic_Create | 159 |
| tibemsTopic_Destroy | 160 |
| tibemsTopic_GetTopicName | 161 |
| Chapter 4 Consumer | 163 |
| tibemsMsgConsumer | 164 |
| tibemsMsgConsumer_Close | 165 |
| tibemsMsgConsumer_GetDestination | 166 |
| tibemsMsgConsumer_GetMsgListener | 167 |
| tibemsMsgConsumer_GetMsgSelector | 168 |
| tibemsMsgConsumer_GetNoLocal | 169 |
| tibemsMsgConsumer_Receive | 170 |
| tibemsMsgConsumer_ReceiveNoWait | 171 |
| tibemsMsgConsumer_ReceiveTimeout | 172 |
| tibemsMsgConsumer_SetMsgListener | 173 |
| tibemsMsgCallback | 174 |
| Chapter 5 Producer | 175 |
| tibemsMsgProducer | 176 |
| tibemsMsgProducer_AsyncSend | 178 |
| tibemsMsgProducer_Close | 182 |
| tibemsMsgProducer_GetDeliveryDelay | 183 |
| tibemsMsgProducer_GetDeliveryMode | 184 |
| tibemsMsgProducer_GetDestination | 185 |
| tibemsMsgProducer_GetDisableMessageID | 186 |

| | |
|--|------------|
| tibemsMsgProducer_GetDisableMessageTimestamp | 187 |
| tibemsMsgProducer_GetNPSTransmitCheckMode | 188 |
| tibemsMsgProducer_GetPriority | 189 |
| tibemsMsgProducer_GetTimeToLive | 190 |
| tibemsMsgProducer_Send | 191 |
| tibemsMsgProducer_SetDeliveryDelay | 194 |
| tibemsMsgProducer_SetDeliveryMode | 195 |
| tibemsMsgProducer_SetDisableMessageID | 196 |
| tibemsMsgProducer_SetDisableMessageTimestamp | 197 |
| tibemsMsgProducer_SetNPSTransmitCheckMode | 198 |
| tibemsMsgProducer_SetPriority | 200 |
| tibemsMsgProducer_SetTimeToLive | 201 |
| Chapter 6 Requestor | 203 |
| tibemsMsgRequestor | 204 |
| tibemsMsgRequestor_Close | 205 |
| tibemsMsgRequestor_Create | 206 |
| tibemsMsgRequestor_Request | 208 |
| Chapter 7 Connection | 209 |
| tibemsConnection | 210 |
| tibemsConnection_Close | 212 |
| tibemsConnection_Create | 214 |
| tibemsConnection_CreateSession | 216 |
| tibemsConnection_GetActiveURL | 217 |
| tibemsConnection_GetClientId | 218 |
| tibemsConnection_GetExceptionListener | 219 |
| tibemsConnection_GetMetaData | 220 |
| tibemsConnection_IsDisconnected | 221 |
| tibemsConnection_SetClientId | 222 |
| tibemsConnection_SetExceptionListener | 223 |
| tibemsConnection_Start | 224 |
| tibemsConnection_Stop | 225 |
| tibemsConnectionMetaData | 227 |
| tibemsConnectionMetaData_GetEMS | 228 |
| tibemsConnectionMetaData_GetProvider | 230 |
| tibemsConnectionMetaData_GetEMSProviderName | 232 |
| tibemsExceptionCallback | 233 |
| tibemsMulticastExceptionCallback | 234 |
| tibemsSSL | 235 |
| tibemsSSL_GetTrace | 236 |
| tibemsSSL_OpenSSLVersion | 237 |
| tibemsSSL_SetTrace | 238 |

| | |
|--|----------------|
| tibemsSSLParams | 239 |
| tibemsSSLParams_AddIssuerCert | 240 |
| tibemsSSLParams_AddTrustedCert | 241 |
| tibemsSSLParams_Create | 242 |
| tibemsSSLParams_Destroy | 243 |
| tibemsSSLParams_GetIdentity | 244 |
| tibemsSSLParams_GetPrivateKey | 245 |
| tibemsSSLParams_SetAuthOnly | 246 |
| tibemsSSLParams_SetCiphers | 247 |
| tibemsSSLParams_SetExpectedHostName | 248 |
| tibemsSSLParams_SetHostNameVerifier | 249 |
| tibemsSSLParams_SetIdentity | 250 |
| tibemsSSLParams_SetPrivateKey | 251 |
| tibemsSSLParams_SetRandData | 252 |
| tibemsSSLParams_SetVerifyHost | 253 |
| tibemsSSLHostNameVerifier | 254 |
| Chapter 8 Connection Factory | 257 |
| tibemsConnectionFactory | 258 |
| tibemsConnectionFactory_Create | 261 |
| tibemsConnectionFactory_CreateConnection | 262 |
| tibemsConnectionFactory_CreateXAConnection | 263 |
| tibemsConnectionFactory_Destroy | 264 |
| tibemsConnectionFactory_GetSSLProxyHost | 265 |
| tibemsConnectionFactory_GetSSLProxyPort | 266 |
| tibemsConnectionFactory_GetSSLProxyUser | 267 |
| tibemsConnectionFactory_GetSSLProxyPassword | 268 |
| tibemsConnectionFactory_Print | 269 |
| tibemsConnectionFactory_PrintToBuffer | 270 |
| tibemsConnectionFactory_SetClientID | 271 |
| tibemsConnectionFactory_SetConnectAttemptCount | 272 |
| tibemsConnectionFactory_SetConnectAttemptDelay | 273 |
| tibemsConnectionFactory_SetConnectAttemptTimeout | 274 |
| tibemsConnectionFactory_SetMetric | 275 |
| tibemsConnectionFactory_SetMulticastDaemon | 276 |
| tibemsConnectionFactory_SetMulticastEnabled | 277 |
| tibemsConnectionFactory_SetPkPassword | 278 |
| tibemsConnectionFactory_SetReconnectAttemptCount | 279 |
| tibemsConnectionFactory_SetReconnectAttemptDelay | 280 |
| tibemsConnectionFactory_SetReconnectAttemptTimeout | 281 |
| tibemsConnectionFactory_SetServerURL | 282 |
| tibemsConnectionFactory_SetSSLParams | 283 |
| tibemsConnectionFactory_SetSSLProxy | 284 |
| tibemsConnectionFactory_SetSSLProxyAuth | 285 |

| | |
|--|------------|
| tibemsConnectionFactory_SetUserName | 286 |
| tibemsConnectionFactory_SetUserPassword | 287 |
| tibemsUFOConnectionFactory_Create | 288 |
| tibemsUFOConnectionFactory_CreateFromConnectionFactory | 289 |
| tibemsUFOConnectionFactory_RecoverConnection | 290 |
| tibemsFactoryLoadBalanceMetric | 291 |
| Chapter 9 Session | 293 |
| tibemsSession | 294 |
| tibemsSession_Close | 297 |
| tibemsSession_Commit | 298 |
| tibemsSession_CreateBrowser | 299 |
| tibemsSession_CreateBytesMessage | 300 |
| tibemsSession_CreateConsumer | 301 |
| tibemsSession_CreateDurableSubscriber | 303 |
| tibemsSession_CreateMapMessage | 306 |
| tibemsSession_CreateMessage | 307 |
| tibemsSession_CreateProducer | 308 |
| tibemsSession_CreateSharedConsumer | 309 |
| tibemsSession_CreateSharedDurableConsumer | 311 |
| tibemsSession_CreateStreamMessage | 313 |
| tibemsSession_CreateTemporaryQueue | 314 |
| tibemsSession_CreateTemporaryTopic | 315 |
| tibemsSession_CreateTextMessage | 316 |
| tibemsSession_DeleteTemporaryQueue | 317 |
| tibemsSession_DeleteTemporaryTopic | 318 |
| tibemsSession_GetAcknowledgeMode | 319 |
| tibemsSession_GetTransacted | 320 |
| tibemsSession_Recover | 321 |
| tibemsSession_Rollback | 322 |
| tibemsSession_Unsubscribe | 323 |
| tibemsAcknowledgeMode | 324 |
| Chapter 10 Queue Browser | 327 |
| tibemsQueueBrowser | 328 |
| tibemsQueueBrowser_Close | 329 |
| tibemsQueueBrowser_GetMsgSelector | 330 |
| tibemsQueueBrowser_GetNext | 331 |
| tibemsQueueBrowser_GetQueue | 332 |
| Chapter 11 Name Server Lookup | 333 |
| tibemsLookupContext | 334 |
| tibemsLookupContext_Create | 335 |

| | |
|---|------------|
| tibemsLookupContext_CreateExternal | 337 |
| tibemsLookupContext_Destroy | 338 |
| tibemsLookupContext_Lookup | 339 |
| tibemsLookupParams | 341 |
| tibemsLookupParams_Create | 342 |
| tibemsLookupParams_Destroy | 343 |
| tibemsLookupParams_GetLdapServerUrl | 344 |
| tibemsLookupParams_SetLdapBaseDN | 345 |
| tibemsLookupParams_SetLdapCAFile | 346 |
| tibemsLookupParams_SetLdapCAPath | 347 |
| tibemsLookupParams_SetLdapCertFile | 348 |
| tibemsLookupParams_SetLdapCiphers | 349 |
| tibemsLookupParams_SetLdapConnType | 350 |
| tibemsLookupParams_SetLdapCredential | 351 |
| tibemsLookupParams_SetLdapKeyFile | 352 |
| tibemsLookupParams_SetLdapPrincipal | 353 |
| tibemsLookupParams_SetLdapRandFile | 354 |
| tibemsLookupParams_SetLdapSearchScope | 355 |
| tibemsLookupParams_SetLdapServerUrl | 356 |
| Chapter 12 XA—External Transaction Manager | 357 |
| tibemsXAConnection | 358 |
| tibemsXAConnection_Close | 359 |
| tibemsXAConnection_Create | 361 |
| tibemsXAConnection_CreateXASession | 363 |
| tibemsXAConnection_Get | 364 |
| tibemsXAConnection_GetXASession | 365 |
| XID | 366 |
| tibemsXAResource | 367 |
| tibemsXAResource_Commit | 368 |
| tibemsXAResource_End | 369 |
| tibemsXAResource_Forget | 370 |
| tibemsXAResource_GetRMID | 371 |
| tibemsXAResource_GetTransactionTimeout | 372 |
| tibemsXAResource_isSameRM | 373 |
| tibemsXAResource_Prepate | 374 |
| tibemsXAResource_Recover | 375 |
| tibemsXAResource_Rollback | 377 |
| tibemsXAResource_SetRMID | 378 |
| tibemsXAResource_SetTransactionTimeout | 379 |
| tibemsXAResource_Start | 380 |
| tibemsXASession | 381 |
| tibemsXASession_Close | 382 |

| | |
|--|------------|
| tibemsXASession_GetSession | 383 |
| tibemsXASession_GetXAResource | 384 |
| Chapter 13 Types | 385 |
| Uniform Types | 386 |
| Chapter 14 Utilities | 387 |
| Utility Functions | 388 |
| tibems_Close | 391 |
| tibems_GetAllowCloseInCallback | 392 |
| tibems_GetConnectAttemptCount | 393 |
| tibems_GetConnectAttemptDelay | 394 |
| tibems_GetConnectAttemptTimeout | 395 |
| tibems_GetExceptionOnFTEvents | 396 |
| tibems_GetExceptionOnFTSwitch | 397 |
| tibems_GetMulticastDaemon | 398 |
| tibems_GetMulticastEnabled | 399 |
| tibems_GetReconnectAttemptCount | 400 |
| tibems_GetReconnectAttemptDelay | 401 |
| tibems_GetReconnectAttemptTimeout | 402 |
| tibems_GetSocketReceiveBufferSize | 403 |
| tibems_GetSocketSendBufferSize | 404 |
| tibems_IsConsumerMulticast | 405 |
| tibems_Open | 406 |
| tibems_SetAllowCloseInCallback | 407 |
| tibems_SetConnectAttemptCount | 408 |
| tibems_SetConnectAttemptDelay | 409 |
| tibems_SetConnectAttemptTimeout | 410 |
| tibems_SetExceptionOnFTEvents | 411 |
| tibems_setExceptionOnFTSwitch | 412 |
| tibems_SetMulticastDaemon | 413 |
| tibems_SetMulticastEnabled | 414 |
| tibems_SetMulticastExceptionListener | 415 |
| tibems_SetReconnectAttemptCount | 416 |
| tibems_SetReconnectAttemptDelay | 417 |
| tibems_SetReconnectAttemptTimeout | 418 |
| tibems_SetSocketReceiveBufferSize | 419 |
| tibems_SetSocketSendBufferSize | 420 |
| tibems_SetTraceFile | 421 |
| tibems_Sleep | 422 |
| tibems_Version | 423 |

| | |
|--|------------|
| Chapter 15 Administration | 425 |
| Administration Overview | 426 |
| tibemsAdmin | 427 |
| tibemsAdmin_Close | 429 |
| tibemsAdmin_Create | 430 |
| tibemsAdmin_GetCommandTimeout | 432 |
| tibemsAdmin_GetConsumer | 433 |
| tibemsAdmin_GetConsumers | 434 |
| tibemsAdmin_GetInfo | 437 |
| tibemsAdmin_GetProducerStatistics | 438 |
| tibemsAdmin_GetQueue | 440 |
| tibemsAdmin_GetQueues | 441 |
| tibemsAdmin_GetSubscriptions | 443 |
| tibemsAdmin_GetTopic | 445 |
| tibemsAdmin_GetTopics | 446 |
| tibemsAdmin_SetCommandTimeout | 448 |
| tibemsAdmin_SetExceptionListener | 449 |
| tibemsCollection | 450 |
| tibemsCollection_Destroy | 451 |
| tibemsCollection_GetCount | 452 |
| tibemsCollection_GetFirst | 453 |
| tibemsCollection_GetNext | 454 |
| tibemsConsumerInfo | 455 |
| tibemsConsumerInfo_Destroy | 458 |
| tibemsConsumerInfo_GetCreateTime | 459 |
| tibemsConsumerInfo_GetCurrentMsgCountSentByServer | 460 |
| tibemsConsumerInfo_GetCurrentMsgSizeSentByServer | 461 |
| tibemsConsumerInfo_GetDestinationName | 462 |
| tibemsConsumerInfo_GetDestinationType | 463 |
| tibemsConsumerInfo_GetDetailedStatistics | 464 |
| tibemsConsumerInfo_GetDurableName | 465 |
| tibemsConsumerInfo_GetElapsedSinceLastAcknowledged | 466 |
| tibemsConsumerInfo_GetElapsedSinceLastSent | 467 |
| tibemsConsumerInfo_GetID | 468 |
| tibemsConsumerInfo_GetPendingMessageCount | 469 |
| tibemsConsumerInfo_GetPendingMessageSize | 470 |
| tibemsConsumerInfo_GetSharedSubscriptionName | 471 |
| tibemsConsumerInfo_GetStatistics | 472 |
| tibemsConsumerInfo_GetTotalAcknowledgedCount | 473 |
| tibemsConsumerInfo_GetTotalMsgCountSentByServer | 474 |
| tibemsConsumerInfo_IsActive | 475 |
| tibemsConsumerInfo_IsConnected | 476 |
| tibemsConsumerInfo_IsConnectionConsumer | 477 |
| tibemsConsumerInfo_IsShared | 478 |

| | |
|--|-----|
| tibemsDetailedDestStat | 479 |
| tibemsDetailedDestStat_GetDestinationName | 480 |
| tibemsDetailedDestStat_GetDestinationType | 481 |
| tibemsDetailedDestStat_GetStatData | 482 |
| tibemsProducerInfo | 483 |
| tibemsProducerInfo_Destroy | 484 |
| tibemsProducerInfo_GetCreateTime | 485 |
| tibemsProducerInfo_GetDestinationName | 486 |
| tibemsProducerInfo_GetDestinationType | 487 |
| tibemsProducerInfo_GetDetailedStatistics | 488 |
| tibemsProducerInfo_GetID | 489 |
| tibemsProducerInfo_GetStatistics | 490 |
| tibemsQueueInfo | 491 |
| tibemsQueueInfo_Create | 493 |
| tibemsQueueInfo_Destroy | 494 |
| tibemsQueueInfo_GetDeliveredMessageCount | 495 |
| tibemsQueueInfo_GetFlowControlMaxBytes | 496 |
| tibemsQueueInfo_GetInboundStatistics | 497 |
| tibemsQueueInfo_GetMaxBytes | 498 |
| tibemsQueueInfo_GetMaxMsgs | 499 |
| tibemsQueueInfo_GetName | 500 |
| tibemsQueueInfo_GetOutboundStatistics | 501 |
| tibemsQueueInfo_GetOverflowPolicy | 502 |
| tibemsQueueInfo_GetPendingMessageCount | 503 |
| tibemsQueueInfo_GetPendingMessageSize | 504 |
| tibemsQueueInfo_GetPendingPersistentMessageCount | 505 |
| tibemsQueueInfo_GetPendingPersistentMessageSize | 506 |
| tibemsQueueInfo_GetReceiverCount | 507 |
| tibemsServerInfo | 508 |
| tibemsServerInfo_Destroy | 509 |
| tibemsServerInfo_GetConsumerCount | 510 |
| tibemsServerInfo_GetProducerCount | 511 |
| tibemsServerInfo_GetQueueCount | 512 |
| tibemsServerInfo_GetTopicCount | 513 |
| tibemsStatData | 514 |
| tibemsStatData_GetByteRate | 515 |
| tibemsStatData_GetMessageRate | 516 |
| tibemsStatData_GetTotalBytes | 517 |
| tibemsStatData_GetTotalMessages | 518 |
| tibemsSubscriptionInfo | 519 |
| tibemsSubscriptionInfo_Destroy | 520 |
| tibemsSubscriptionInfo_GetConsumerCount | 521 |
| tibemsSubscriptionInfo_GetCreateTime | 522 |
| tibemsSubscriptionInfo_GetID | 523 |

| | |
|--|------------|
| tibemsSubscriptionInfo_GetName | 524 |
| tibemsSubscriptionInfo_GetPendingMessageCount | 525 |
| tibemsSubscriptionInfo_GetPendingMessageSize | 526 |
| tibemsSubscriptionInfo_GetSelector | 527 |
| tibemsSubscriptionInfo_GetTopicName | 528 |
| tibemsSubscriptionInfo_HasSelector | 529 |
| tibemsSubscriptionInfo_IsDurable | 530 |
| tibemsSubscriptionInfo_IsShared | 531 |
| tibemsTopicInfo | 532 |
| tibemsTopicInfo_Create | 534 |
| tibemsTopicInfo_Destroy | 535 |
| tibemsTopicInfo_GetActiveDurableCount | 536 |
| tibemsTopicInfo_GetDurableCount | 537 |
| tibemsTopicInfo_GetDurableSubscriptionCount | 538 |
| tibemsTopicInfo_GetFlowControlMaxBytes | 539 |
| tibemsTopicInfo_GetInboundStatistics | 540 |
| tibemsTopicInfo_GetMaxBytes | 541 |
| tibemsTopicInfo_GetMaxMsgs | 542 |
| tibemsTopicInfo_GetName | 543 |
| tibemsTopicInfo_GetOutboundStatistics | 544 |
| tibemsTopicInfo_GetOverflowPolicy | 545 |
| tibemsTopicInfo_GetPendingMessageCount | 546 |
| tibemsTopicInfo_GetPendingMessageSize | 547 |
| tibemsTopicInfo_GetPendingPersistentMessageCount | 548 |
| tibemsTopicInfo_GetPendingPersistentMessageSize | 549 |
| tibemsTopicInfo_GetSubscriberCount | 550 |
| tibemsTopicInfo_GetSubscriptionCount | 551 |
| Chapter 16 Exception | 553 |
| tibems_status | 554 |
| tibemsStatus_GetText | 560 |
| tibemsErrorContext | 561 |
| tibemsErrorContext_Create | 562 |
| tibemsErrorContext_Close | 563 |
| tibemsErrorContext_GetLastErrorString | 564 |
| tibemsErrorContext_GetLastErrorStackTrace | 565 |
| Chapter 17 IBM z/OS and IBM i | 567 |
| IBM EBCDIC Platform Calls | 568 |
| tibems_SetCodePages() | 569 |
| IBM z/OS Functions | 571 |
| tibx_MVSConsole_SetConsumer() | 572 |
| tibx_MVSConsole_Create() | 573 |

| | |
|--|------------|
| Console_Response | 575 |
| SSL Implementation on IBM EBCDIC Systems..... | 576 |
| IBM System SSL Environment Variables on z/OS | 576 |
| Call Summary | 577 |
| tibemsSSL_System_GetTrace | 579 |
| tibemsSSL_System_SetFipsMode | 580 |
| tibemsSSL_System_SetTrace | 581 |
| tibemsSSL_System_Version | 582 |
| tibemsSSLParams_System_Create | 583 |
| tibemsSSLParams_System_Destroy | 584 |
| tibemsSSLParams_System_SetApplicationId | 585 |
| tibemsSSLParams_System_SetAuthOnly | 586 |
| tibemsSSLParams_System_SetCiphers | 587 |
| tibemsSSLParams_System_SetEnableSSLV3..... | 590 |
| tibemsSSLParams_System_SetEnableTLS1 | 591 |
| tibemsSSLParams_System_SetExpectedHostName..... | 592 |
| tibemsSSLParams_System_SetKeyRingFile | 593 |
| tibemsSSLParams_System_SetLabel | 594 |
| tibemsSSLParams_System_SetLdapServerPassword..... | 595 |
| tibemsSSLParams_System_SetLdapServerUrl | 596 |
| tibemsSSLParams_System_SetLdapServerUserid | 597 |
| tibemsSSLParams_System_SetVerifyHostName..... | 598 |
| Index | 599 |

Tables

| | | |
|----------|---|-------|
| Table 1 | General Typographical Conventions | xxiii |
| Table 2 | Syntax Typographical Conventions | xxiv |
| Table 3 | Feature Support | 3 |
| Table 4 | JMS Message Headers | 10 |
| Table 5 | Message Property Names | 14 |
| Table 6 | Data Type Conversion | 20 |
| Table 7 | Message Constants | 24 |
| Table 8 | BytesMessage Read Functions | 81 |
| Table 9 | BytesMessage Write Functions | 88 |
| Table 10 | Message Field Type Indicators | 136 |
| Table 11 | Destination Overview | 142 |
| Table 12 | Functions | 235 |
| Table 13 | Certificate Encodings | 235 |
| Table 14 | EMS Types | 386 |
| Table 15 | Status Codes | 554 |
| Table 16 | IBM System SSL Calls | 577 |
| Table 17 | Ciphers Supported in IBM System SSL | 588 |

Preface

TIBCO is proud to announce the latest release of TIBCO Enterprise Message Service™. This release is the latest in a long history of TIBCO products that leverage the power of the Information Bus® to enable truly event-driven IT environments. To find out more about how TIBCO Enterprise Message Service and other TIBCO products are powered by TIB® technology, please visit us at www.tibco.com.

TIBCO Enterprise Message Service software lets application programs send and receive messages according to the Java Message Service (JMS) protocol. It also integrates with TIBCO Rendezvous and TIBCO SmartSockets messaging products.

Topics

- [Changes from the Previous Release of this Guide, page xx](#)
- [Related Documentation, page xxi](#)
- [Typographical Conventions, page xxiii](#)
- [Connecting with TIBCO Resources, page xxvi](#)

Changes from the Previous Release of this Guide

This section itemizes the major changes from the previous release of this guide.

Feature Enhancements

The following enhancements are documented in the sections shown:

- **Shared Subscriptions** The following new functions are added to the Shared Subscriptions feature:
 - [tibemsSession_CreateSharedConsumer on page 309](#)
 - [tibemsSession_CreateSharedDurableConsumer on page 311](#)
 - [tibemsAdmin_GetSubscriptions on page 443](#)
 - [tibemsSubscriptionInfo on page 519](#)
- **Asynchronous Sending** The C API now supports the asynchronous sending feature, which permits message producers to send messages asynchronously, offloading the notification of the success or failure to another thread.
 - [tibemsMsgProducer_AsyncSend on page 178](#)
 - [tibemsMsgProducer_AsyncSendEx](#)
 - [tibemsMsgProducer_AsyncSendToDestination](#)
 - [tibemsMsgProducer_AsyncSendToDestinationEx](#)
 - [tibemsMsgCompletionCallback on page 131](#)
- **Delivery Delay** The C API now supports the Delivery Delay feature, which permits message publisher to specify a delivery time for messages. The EMS server will only deliver the message after the delivery time specified when the message is published.
 - [tibemsMsgProducer_SetDeliveryDelay on page 194](#)
 - [tibemsMsgProducer_GetDeliveryDelay on page 183](#)
 - [tibemsMsg_GetDeliveryTime on page 41](#)

Removed Features

- Because the C API does not support character conversion, `tibemsBytesMsg_ReadUTF` and `tibemsBytesMsg_WriteUTF` have been removed.

Related Documentation

This section lists documentation resources you may find useful.

TIBCO Enterprise Message Service Documentation

The following documents form the TIBCO Enterprise Message Service documentation set:

- *TIBCO Enterprise Message Service User's Guide* Read this manual to gain an overall understanding of the product, its features, and configuration.
- *TIBCO Enterprise Message Service Central Administration* Read this manual for information on the central administration interface.
- *TIBCO Enterprise Message Service Installation* Read the relevant sections of this manual before installing this product.
- *TIBCO Enterprise Message Service C & COBOL Reference* The C API reference is available in HTML and PDF formats.
- *TIBCO Enterprise Message Service Java API Reference* The Java API reference can be accessed only through the HTML documentation interface.
- *TIBCO Enterprise Message Service .NET API Reference* The .NET API reference can be accessed only through the HTML documentation interface.
- *TIBCO Enterprise Message Service Release Notes* Read the release notes for a list of new and changed features. This document also contains lists of known issues and closed issues for this release. This document is available only in PDF format.

Other TIBCO Product Documentation

You may find it useful to read the documentation for the following TIBCO products:

- TIBCO Rendezvous®
- TIBCO SmartSockets®
- TIBCO Hawk®
- TIBCO EMS® Client for z/OS (CICS)
- TIBCO EMS® Client for z/OS (MVS)
- TIBCO EMS® Client for IBM i

Third Party Documentation

- Java™ Message Service specification, available through <http://www.oracle.com/technetwork/java/jms/index.html>.
- *Java™ Message Service* by Richard Monson-Haefel and David A. Chappell, O'Reilly and Associates, Sebastopol, California, 2001.
- Java™ Authentication and Authorization Service (JAAS) *LoginModule Developer's Guide* and *Reference Guide*, available through <http://www.oracle.com/technetwork/java/javase/jaas/index.html>.

Typographical Conventions

The following typographical conventions are used in this manual.

Table 1 General Typographical Conventions

| Convention | Use |
|---|---|
| <i>TIBCO_HOME</i> <i>ENV_NAME</i> <i>EMS_HOME</i> | <p>TIBCO products are installed into an installation environment. A product installed into an installation environment does not access components in other installation environments. Incompatible products and multiple instances of the same product must be installed into different installation environments.</p> <p>An installation environment consists of the following properties:</p> <ul style="list-style-type: none"> • Name Identifies the installation environment. This name is referenced in documentation as <i>ENV_NAME</i>. If you specify a custom environment name, on Microsoft Windows the name becomes a component of the path to the product shortcut in the Windows Start > All Programs menu. • Path The folder into which the product is installed. This folder is referenced in documentation as <i>TIBCO_HOME</i>. The value of <i>TIBCO_HOME</i> depends on the operating system. For example, on Windows systems, the default value is C:\tibco. <p>TIBCO Enterprise Message Service installs into a directory within <i>TIBCO_HOME</i>. This directory is referenced in documentation as <i>EMS_HOME</i>. The value of <i>EMS_HOME</i> depends on the operating system. For example on Windows systems, the default value is C:\tibco\ems\8.1.</p> |
| code font | <p>Code font identifies commands, code examples, filenames, pathnames, and output displayed in a command window. For example:</p> <p>Use MyCommand to start the foo process.</p> |
| bold code font | <p>Bold code font is used in the following ways:</p> <ul style="list-style-type: none"> • In procedures, to indicate what a user types. For example: Type admin. • In large code samples, to indicate the parts of the sample that are of particular interest. • In command syntax, to indicate the default parameter for a command. For example, if no parameter is specified, MyCommand is enabled: MyCommand [enable disable] |

Table 1 General Typographical Conventions (Cont'd)




| Convention | Use |
|---|--|
| <i>italic font</i> | <p>Italic font is used in the following ways:</p> <ul style="list-style-type: none">• To indicate a document title. For example: See <i>TIBCO ActiveMatrix BusinessWorks Concepts</i>.• To introduce new terms For example: A portal page may contain several portlets. <i>Portlets</i> are mini-applications that run in a portal.• To indicate a variable in a command or code syntax that you must replace. For example: <code>MyCommand <i>PathName</i></code> |
| Key combinations | <p>Key name separated by a plus sign indicate keys pressed simultaneously. For example: <code>Ctrl+C</code>.</p> <p>Key names separated by a comma and space indicate keys pressed one after the other. For example: <code>Esc, Ctrl+Q</code>.</p> |
|  | <p>The note icon indicates information that is of special interest or importance, for example, an additional action required only in certain circumstances.</p> |
|  | <p>The tip icon indicates an idea that could be useful, for example, a way to apply the information provided in the current section to achieve a specific result.</p> |
|  | <p>The warning icon indicates the potential for a damaging situation, for example, data loss or corruption if certain steps are taken or not taken.</p> |

Table 2 Syntax Typographical Conventions

| Convention | Use |
|------------|--|
| [] | <p>An optional item in a command or code syntax.</p> <p>For example:</p> <pre>MyCommand [optional_parameter] required_parameter</pre> |
| | <p>A logical OR that separates multiple items of which only one may be chosen.</p> <p>For example, you can select only one of the following parameters:</p> <pre>MyCommand para1 param2 param3</pre> |

Table 2 Syntax Typographical Conventions

| Convention | Use |
|------------|---|
| { } | <p>A logical group of items in a command. Other syntax notations may appear within each logical group.</p> <p>For example, the following command requires two parameters, which can be either the pair param1 and param2, or the pair param3 and param4.</p> <pre>MyCommand {param1 param2} {param3 param4}</pre> <p>In the next example, the command requires two parameters. The first parameter can be either param1 or param2 and the second can be either param3 or param4:</p> <pre>MyCommand {param1 param2} {param3 param4}</pre> <p>In the next example, the command can accept either two or three parameters. The first parameter must be param1. You can optionally include param2 as the second parameter. And the last parameter is either param3 or param4.</p> <pre>MyCommand param1 [param2] {param3 param4}</pre> |

Connecting with TIBCO Resources

How to Join TIBCOCommunity

TIBCOCommunity is an online destination for TIBCO customers, partners, and resident experts. It is a place to share and access the collective experience of the TIBCO community. TIBCOCommunity offers forums, blogs, and access to a variety of resources. To register, go to <http://www.tibcommunity.com>.

How to Access TIBCO Documentation

You can access TIBCO documentation here:

<http://docs.tibco.com>

How to Contact TIBCO Support

For comments or problems with this manual or the software it addresses, contact TIBCO Support as follows:

- For an overview of TIBCO Support, and information about getting started with TIBCO Support, visit this site:

<http://www.tibco.com/services/support>

- If you already have a valid maintenance or support contract, visit this site:

<https://support.tibco.com>

Entry to this site requires a user name and password. If you do not have a user name, you can request one.

Chapter 1 Introduction

This chapter presents concepts specific to the TIBCO Enterprise Message Service™ C API and COBOL API. For more general information and concepts pertaining to TIBCO Enterprise Message Service (EMS) software, see the book *TIBCO Enterprise Message Service User's Guide*.

Topics

- [Overview, page 2](#)
- [Excluded Features and Restrictions, page 3](#)
- [Naming Conventions and Length Limitations, page 3](#)
- [Strings and Character Encodings, page 4](#)

Overview

TIBCO Enterprise Message Service Java API implements (and extends) the JMS 1.1 specification. TIBCO Enterprise Message Service C API closely mimics the Java API.

EMS COBOL API brings the power of EMS to z/OS systems. Its entry points parallel those of the C API, with identical function names and similar parameters.

Excluded Features and Restrictions

This section summarizes features that are not available in either the C library, or the COBOL library.

Table 3 Feature Support

| Feature | C | COBOL |
|--|-----|-------|
| XA protocols for external transaction managers | Yes | — |
| ConnectionConsumer, ServerSession, ServerSessionPool | — | — |

Naming Conventions and Length Limitations

The rules that govern naming conventions and length limitations in TIBCO Enterprise Message Service are described in the *TIBCO Enterprise Message Service User's Guide*. For detailed information, see the Naming Conventions section in that book.

Strings and Character Encodings

C programs represent strings within messages as byte arrays. Before sending an outbound message, EMS programs translate strings to their byte representation using an encoding, which the program specifies. Conversely, when EMS programs receive inbound messages, they reconstruct strings from byte arrays using the same encoding.

When a program specifies an encoding, it applies to all strings in message bodies (names and values), and properties (names and values). It does *not* apply to header names nor values.

For a list of standard encoding names, see www.iana.org.

| | |
|--------------------------------------|---|
| Outbound Messages | <p>C programs can determine the encoding of strings in outbound messages in two ways:</p> <ul style="list-style-type: none"> • Use the default global encoding—namely, UTF-8. • Set the encoding for an individual message using <code>tibemsMsg_SetEncoding</code> on page 64. |
| Inbound Messages | An inbound message from another EMS client contains its encoding type, so the receiving client can properly decode strings inside the message. |
| Character Limits for Connection URLs | Connection URLs are limited to a length of 1000 characters. Note that this limit pertains to the C client library, as well as the administration tool and the <code>factories.conf</code> configuration file. |

IBM z/OS and IBM i (i5)—COBOL and C

In EBCDIC environments, the EMS client library automatically converts message strings. To client programs, all strings appear in the host code page. On the network, all strings appear in the network host page. For details, see `tibems_SetCodePages()` on page 569.

All the COBOL calls documented in this reference refer to COBOL on the z/OS and IBM i platforms.

Configuring C and COBOL Clients for Fault-Tolerant Connections

When connecting a fault-tolerant client to EMS, you must specify two or more EMS servers, as described in [Configuring Clients for Shared State Failover Connections](#) in the *TIBCO Enterprise Message Service User's Guide*.

C clients list the primary and backup server URLs in the `brokerURL` argument to a connection constructor, separated by a comma.

Example

In this example, the first server is `tcp://server0:7222`, and the second server is `tcp://server1:7344` (if first server is not available).

```
tibemsConnection_Create(  
    &connection,  
    "tcp://server0:7222,  
    tcp://server1:7344",  
    NULL, "admin", NULL );
```


Chapter 2 **Messages**

Message objects carry application data between client program processes. This chapter presents the structure of messages, JMS message selector syntax to specify a subset of messages based on their property values, the message types and their functions.

Topics

- [Parts of a Message, page 8](#)
- [Body Types, page 9](#)
- [Headers, page 10](#)
- [Properties, page 14](#)
- [Message Selectors, page 17](#)
- [tibemsMsg, page 21](#)
- [tibemsBytesMsg, page 75](#)
- [tibemsMapMsg, page 90](#)
- [tibemsObjectMsg, page 105](#)
- [tibemsStreamMsg, page 109](#)
- [tibemsTextMsg, page 124](#)
- [tibemsData, page 128](#)
- [tibemsDeliveryMode, page 129](#)
- [tibemsNpCheckMode, page 130](#)
- [tibemsMsgCompletionCallback, page 131](#)
- [tibemsMsgEnum, page 132](#)
- [tibemsMsgField, page 135](#)
- [tibemsMsgType, page 140](#)

Parts of a Message

Messages consist of three parts:

- **Body** The body of a message bears the information content of an application. Several types of message body organize that information in different ways; see [Body Types on page 9](#).
- **Header** Headers associate a fixed set of header field names with values. Clients and providers use headers to identify and route messages.
- **Properties** Properties associate an extensible set of property names with values. The EMS server uses properties to attach ancillary information to messages. Client applications can also use properties—for example, to customize message filtering.

Body Types

EMS follows JMS in defining five types of message body:

- [tibemsMapMsg](#) The message body is a mapping from field names to values. Field names are strings. EMS supports an extended set of values types (extending JMS). Programs can access fields either by name, or sequentially (though the order of that sequence is indeterminate).
- [tibemsObjectMsg](#) The message body is one serializable object.
- [tibemsStreamMsg](#) The message body is a stream of values. Programs write the values sequentially into the stream, and read values sequentially from the stream.
- [tibemsTextMsg](#) The message body is one character string (of any length). This text string can represent any text, including an XML document.
- [tibemsBytesMsg](#) The message body is a stream of uninterpreted bytes. Programs can use this body type to emulate body types that do not map naturally to one of the other body types.

See Also [tibemsMsgType on page 140](#)
[tibemsMsg_GetBodyType on page 36](#)

Headers

Headers associate a fixed set of header field names with values. Clients and providers use headers to identify and route messages.

Programs can access header values using the function calls in [Table 4](#).

However, programs can effectively set only three message header properties—Reply To, Correlation ID and Type. For all other header properties, the provider ignores or overwrites values set by client programs.

Table 4 JMS Message Headers

| Description |
|---|
| Correlation ID Correlation ID refers to a related message. For example, when a consumer responds to a request message by sending a reply, it can set the correlation ID of the reply to indicate the request message. The JMS specification allows three categories of values for the correlation ID property: <ul style="list-style-type: none">Message ID A message ID is a unique string that the provider assigns to a message. Programs can use these IDs to correlate messages. For example, a program can link a response to a request by setting the correlation ID of a response message to the message ID of the corresponding request message. Message ID strings begin with the prefix ID: (which is reserved for this purpose).String Programs can also correlate messages using arbitrary strings, with semantics determined by the application. These strings must <i>not</i> begin with the prefix ID: (which is reserved for message IDs).Byte Array This implementation does not support byte array values for the correlation ID property. The JMS specification does not require support. tibemsMsg_GetCorrelationID on page 38 tibemsMsg_SetCorrelationID on page 60 |

Delivery Delay

A producer can specify that a message must not be delivered until after a specified time interval, which directs the server to delay delivery of the message. For detailed information on delivery delay, see the *TIBCO Enterprise Message Service User's Guide*.

Sending calls can set the delivery delay for each message based on a property of the producer. To set the producer property, see [tibemsMsgProducer_SetDeliveryDelay on page 194](#).

[tibemsMsg_GetDeliveryTime on page 41](#)

Table 4 JMS Message Headers

| Description |
|--|
| <p>Delivery Mode</p> <p>Delivery Mode instructs the server concerning persistent storage for the message. For detailed information on delivery modes, see the <i>TIBCO Enterprise Message Service User's Guide</i>.</p> <p>Sending calls set the delivery mode for each message, based on either a property of the producer, or on a parameter to the sending call. To set the producer property, see tibemsMsgProducer_SetDeliveryMode on page 195.</p> <p>tibemsMsg_GetDeliveryMode on page 40</p> <p>tibemsMsg_SetDeliveryMode on page 62</p> <p>For values, see tibemsDeliveryMode on page 129.</p> |
| <p>Destination</p> <p>Sending calls set the destination (queue or topic) of the message in this header and will overwrite any existing value. The value is based on either a property of the producer, or on a parameter to the send call.</p> <p>Listeners that consume messages from wildcard destinations can use this property to determine the actual destination of a message.</p> <p>tibemsMsg_GetDestination on page 42</p> <p>tibemsMsg_SetDestination on page 63</p> |
| <p>Expiration</p> <p>Sending calls set the expiration time (in milliseconds) of the message in this field:</p> <ul style="list-style-type: none"> • If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client's current time (GMT). • If the time-to-live is zero, then expiration is also zero—indicating that the message never expires. <p>The server discards a message when its expiration time has passed. However, the JMS specification does not guarantee that clients do not receive expired messages.</p> <p>tibemsMsg_GetExpiration on page 44</p> <p>tibemsMsg_SetExpiration on page 65</p> |

Table 4 JMS Message Headers

| Description |
|--|
| Message ID Sending calls assign a unique ID to each message, and record it in this header. All message ID values start with the 3-character prefix ID: (which is reserved for this purpose). Applications that do not require message IDs can reduce overhead costs by disabling IDs; see tibemsMsgProducer_SetDisableMessageID on page 196 . When the producer disables IDs, the value of this header is null. tibemsMsg_GetMessageID on page 45 tibemsMsg_SetMessageID on page 66 |
| Priority Sending calls set the priority of a message in this header, based on either a property of the producer (tibemsMsgProducer_SetPriority on page 200), or on a parameter to the send call. The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority. Priority affects the order in which the server delivers messages to consumers (higher values first). The JMS specification does not require all providers to implement priority ordering of messages. (EMS supports priorities, but other JMS providers might not.) tibemsMsg_GetPriority on page 46 tibemsMsg_SetPriority on page 67 |
| Redelivered The server sets this header to indicate whether a message might duplicate a previously delivered message: <ul style="list-style-type: none">• <code>false</code>—The server has <i>not</i> previously attempted to deliver this message to the consumer.• <code>true</code>—It is likely (but not guaranteed) that the server has previously attempted to deliver this message to the consumer, but the consumer did not return timely acknowledgement. tibemsMsg_GetRedelivered on page 51 tibemsMsg_SetRedelivered on page 71 See also, tibemsAcknowledgeMode on page 324 |

Table 4 JMS Message Headers

| Description |
|--|
| <p>Reply To</p> <p>Sending clients can set this header to request that recipients reply to the message:</p> <ul style="list-style-type: none"> When the value is a destination object, recipients can send replies to that destination. Such a message is called a <i>request</i>. When the value is null, the sender does not expect a reply. <p>When sending a reply, clients can refer to the corresponding request by setting the Correlation ID.</p> <p>tibemsMsg_GetReplyTo on page 52</p> <p>tibemsMsg_SetReplyTo on page 72</p> |
| <p>Timestamp</p> <p>Sending calls record a UTC timestamp in this header, indicating the approximate time that the server accepted the message.</p> <p>The value is in milliseconds since January 1, 1970 (as in Java).</p> <p>Applications that do not require timestamps can reduce overhead costs by disabling timestamps; see tibemsMsgProducer_SetDisableMessageTimestamp on page 197. When the producer disables timestamps, the value of this header is zero.</p> <p>tibemsMsg_GetTimestamp on page 53</p> <p>tibemsMsg_SetTimestamp on page 73</p> |
| <p>Type</p> <p>Some JMS providers use a message repository to store message type definitions. Client programs can store a value in this field to reference a definition in the repository. EMS support this header, but does not use it.</p> <p>The JMS specification does not define a standard message definition repository, nor does it define a naming policy for message type definitions.</p> <p>Some providers require message type definitions for each application message. To ensure compatibility with such providers, client programs can set this header, even if the client application does not use it.</p> <p>To ensure portability, clients can set this header with symbolic values (rather than literals), and configure them to match the provider's repository.</p> <p>tibemsMsg_GetType on page 54</p> <p>tibemsMsg_SetType on page 74</p> |

Properties

Properties associate an extensible set of property field names with values. The EMS server uses properties to attach ancillary information to messages.

Client applications can also use properties—for example, to customize message filtering; see [Message Selectors on page 17](#).

Setting Message Properties

Property names must conform to the syntax for message selector identifiers; see [Identifiers on page 17](#).

Property values cannot be null or an empty string.

Sending programs can set property values before sending a message.

Receiving programs cannot ordinarily set property values on inbound messages. However, `tibemsMsg_ClearProperties` removes all existing the properties from a message, and lets the program set property values.

EMS Properties

The JMS specification reserves the property name prefix `JMS_vendor_name_` for provider-specific properties (for EMS, this prefix is `JMS_TIBCO_`). Properties that begin with this prefix refer to features of EMS; client programs may use these properties to access those features, but not for communicating application-specific information among client programs.

Table 5 Message Property Names

| Property | Description |
|------------------------|---|
| JMS_TIBCO_CM_PUBLISHER | Correspondent name of an RVCМ sender for messages imported from TIBCO Rendezvous. |
| JMS_TIBCO_CM_SEQUENCE | Sequence number of an RVCМ message imported from TIBCO Rendezvous. |
| JMS_TIBCO_COMPRESS | Senders may set this property to request that EMS compress the message before sending it to the server. The .NET client API does not support this feature at this time. |

Table 5 Message Property Names

| Property | Description |
|--------------------------------|---|
| JMS_TIBCO_DISABLE_SENDER | Senders may set this property to prevent the EMS server from including the sender name in the message when the server sends it to consumers; see JMS_TIBCO_SENDER . |
| JMS_TIBCO_IMPORTED | When the EMS server imports a message from an external message service (such as TIBCO Rendezvous or TIBCO SmartSockets), it sets this property to true. |
| JMS_TIBCO_MSG_EXT | <p>Producers can set this property to true to indicate that a message uses EMS extensions to the JMS specification for messages.</p> <p>The server sets this property to true when importing a message from an external message service, since the message might use those extensions.</p> |
| JMS_TIBCO_MSG_TRACE | <p>When a producer sets this property, the EMS server generates trace output when the message arrives from the producer, and whenever a consumer receives it.</p> <ul style="list-style-type: none"> • When the property value is null, the trace output contains the message ID and sequence number. • When the property value is body, the trace output includes the message body as well. |
| JMS_TIBCO_PRESERVE_UNDELIVERED | When this property is true, the server preserves a record of undeliverable messages by delivering them to the undelivered message queue, <code>\$sys.undelivered</code> . |
| JMS_TIBCO_SENDER | The EMS server fills this property with the <i>user name</i> (string) of the client that sent the message. This feature applies only when the <code>sender_name</code> property of the message's destination is non-null. The sender can disable this feature (overriding the destination property <code>sender_name</code>) by setting a non-null value for the message property JMS_TIBCO_DISABLE_SENDER . |
| JMS_TIBCO_SS_SENDER | When the EMS server imports a message from TIBCO SmartSockets, it sets this property to the SmartSockets sender header field (in SmartSockets syntax). |

| | | | |
|----------------------------|------------------------------------|--------------------------------|-----------------|
| COBOL Constants | 01 | TIBEMS-PROPERTIES. | |
| | 05 | JMS-TIBCO-CM-PUBLISHER | PIC X(23) VALUE |
| | | Z'JMS_TIBCO_CM_PUBLISHER'. | |
| | 05 | JMS-TIBCO-CM-SEQUENCE | PIC X(22) VALUE |
| | | Z'JMS_TIBCO_CM_SEQUENCE'. | |
| | 05 | JMS-TIBCO-COMPRESS | PIC X(19) VALUE |
| | | Z'JMS_TIBCO_COMPRESS'. | |
| | 05 | JMS-TIBCO-DISABLE-SENDER | PIC X(25) VALUE |
| | | Z'JMS_TIBCO_DISABLE_SENDER'. | |
| | 05 | JMS-TIBCO-IMPORTED | PIC X(19) VALUE |
| | | Z'JMS_TIBCO_IMPORTED'. | |
| | 05 | JMS-TIBCO-MSG-EXT | PIC X(19) VALUE |
| | | Z'JMS_TIBCO_MSG_EXT'. | |
| | 05 | JMS-TIBCO-MSG-TRACE | PIC X(20) VALUE |
| | | Z'JMS_TIBCO_MSG_TRACE'. | |
| | 05 | JMS-TIBCO-PRESERVE-UNDELIVERED | PIC X(31) VALUE |
| | Z'JMS_TIBCO_PRESERVE_UNDELIVERED'. | | |
| 05 | JMS-TIBCO-SENDER | PIC X(17) VALUE | |
| | Z'JMS_TIBCO_SENDER'. | | |
| 05 | JMS-TIBCO-SS-SENDER | PIC X(20) VALUE | |
| | Z'JMS_TIBCO_SS_SENDER'. | | |

JMS Properties

The JMS specification reserves the property name prefix JMSX for properties defined by JMS. Client programs may use these properties to access those features, but not for communicating application-specific information among client programs.

For information about these properties, see the JMS specification.

Message Selectors

A message selector is string that lets a client program specify a set of messages, based on the values of message headers and properties. A selector *matches* a message if, after substituting header and property values from the message into the selector string, the string evaluates to `true`. Consumers can request that the server deliver only those messages that match a selector.

The syntax of selectors is based on a subset of SQL92 conditional expression syntax.

Identifiers

Identifiers can refer to the values of message headers and properties, but not to the message body. Identifiers are case-sensitive.

| | |
|--------------|---|
| Basic Syntax | An identifier is a sequence of letters and digits, of any length, that begins with a letter. As in Java, the set of letters includes <code>_</code> (underscore) and <code>\$</code> (dollar). |
| Illegal | Certain names are exceptions, which cannot be used as identifiers. In particular, <code>NULL</code> , <code>TRUE</code> , <code>FALSE</code> , <code>NOT</code> , <code>AND</code> , <code>OR</code> , <code>BETWEEN</code> , <code>LIKE</code> , <code>IN</code> , <code>IS</code> , and <code>ESCAPE</code> are defined to have special meaning in message selector syntax. |
| Value | Identifiers refer either to message header names or property names. The type of an identifier in a message selector corresponds to the type of the header or property value. If an identifier refers to a header or property that does not exist in a message, its value is <code>NULL</code> . |

Literals

| | |
|-----------------------------|---|
| String Literal | A string literal is enclosed in single quotes. To represent a single quote within a literal, use two single quotes; for example, <code>'literal''s'</code> . String literals use the Unicode character encoding. String literals are case sensitive. |
| Exact Numeric Literal | An exact numeric literal is a numeric value without a decimal point, such as <code>57</code> , <code>-957</code> , and <code>+62</code> ; numbers in the range of <code>long</code> are supported. |
| Approximate Numeric Literal | An approximate numeric literal is a numeric value with a decimal point (such as <code>7.</code> , <code>-95.7</code> , and <code>+6.2</code>), or a numeric value in scientific notation (such as <code>7E3</code> and <code>-57.9E2</code>); numbers in the range of <code>double</code> are supported. Approximate literals use the floating-point literal syntax of the Java programming language. |

Boolean Literal The boolean literals are `TRUE` and `FALSE` (case insensitive).

Internal computations of expression values use a 3-value boolean logic similar to SQL. However, the final value of an expression is always either `TRUE` or `FALSE`—never `UNKNOWN`.

Expressions

Selectors as Expressions Every selector is a conditional expression. A selector that evaluates to `true` matches the message; a selector that evaluates to `false` or `unknown` does not match.

Arithmetic Expression Arithmetic expressions are composed of numeric literals, identifiers (that evaluate to numeric literals), arithmetic operations, and smaller arithmetic expressions.

Conditional Expression Conditional expressions are composed of comparison operations, logical operations, and smaller conditional expressions.

Order of Evaluation Order of evaluation is left-to-right, within precedence levels. Parentheses override this order.

Operators

Case Insensitivity Operator names are case-insensitive.

Logical Operators Logical operators in precedence order: `NOT`, `AND`, `OR`.

Comparison Operators Comparison operators: `=`, `>`, `>=`, `<`, `<=`, `<>` (not equal).

These operators can compare only values of comparable types. (Exact numeric values and approximate numerical values are comparable types.) Attempting to compare incomparable types yields `false`. If either value in a comparison evaluates to `NULL`, then the result is `unknown` (in SQL 3-valued logic).

Comparison of string values is restricted to `=` and `<>`. Two strings are equal if and only if they contain the same sequence of characters. Comparison of boolean values is restricted to `=` and `<>`.

Arithmetic Operators Arithmetic operators in precedence order:

- `+`, `-` (unary)
- `*`, `/` (multiplication and division)
- `+`, `-` (addition and subtraction)

Arithmetic operations obey numeric promotion rules of the Java programming language.

| | |
|-------------------------|---|
| Between Operator | <p><i>arithmetic-expr1</i> [NOT] BETWEEN <i>arithmetic-expr2</i> AND <i>arithmetic-expr3</i></p> <p>The BETWEEN comparison operator includes its endpoints. For example:</p> <ul style="list-style-type: none"> • <i>age</i> BETWEEN 5 AND 9 is equivalent to <i>age</i> >= 5 AND <i>age</i> <= 9 • <i>age</i> NOT BETWEEN 5 AND 9 is equivalent to <i>age</i> < 5 OR <i>age</i> > 9 |
| String Set Membership | <p><i>identifier</i> [NOT] IN (<i>string-literal1</i>, <i>string-literal2</i>, ...)</p> <p>The <i>identifier</i> must evaluate to either a string or NULL. If it is NULL, then the value of this expression is unknown.</p> |
| Pattern Matching | <p><i>identifier</i> [NOT] LIKE <i>pattern-value</i> [ESCAPE <i>escape-character</i>]</p> <p>The <i>identifier</i> must evaluate to a string.</p> <p>The <i>pattern-value</i> is a string literal, in which some characters bear special meaning:</p> <ul style="list-style-type: none"> • <i>_</i> (underscore) can match any single character. • <i>%</i> (percent) can match any sequence of zero or more characters. • <i>escape-character</i> preceding either of the special characters changes them into ordinary characters (which match only themselves). |
| Null Header or Property | <p><i>identifier</i> IS NULL</p> <p>This comparison operator tests whether a message header is null, or a message property is absent.</p> <p><i>identifier</i> IS NOT NULL</p> <p>This comparison operator tests whether a message header or message property is non-null.</p> |

White Space

White space is any of the characters space, horizontal tab, form feed, or line terminator—or any contiguous run of characters in this set.

Data Type Conversion

Table 6 summarizes legal datatype conversions. The symbol X in Table 6 indicates that a value written into a message as the row type can be extracted as the column type. This table applies to all message values—including map pairs, headers and properties—except as noted below.

Table 6 Data Type Conversion

| | bool | byte | short | char | int | long | float | double | string | byte[] |
|--------|------|------|-------|------|-----|------|-------|--------|--------|--------|
| bool | X | | | | | | | | X | |
| byte | | X | X | | X | X | | | X | |
| short | | | X | | X | X | | | X | |
| char | | | | X | | | | | X | |
| int | | | | | X | X | | | X | |
| long | | | | | | X | | | X | |
| float | | | | | | | X | X | X | |
| double | | | | | | | | X | X | |
| string | X | X | X | | X | X | X | X | X | |
| byte[] | | | | | | | | | | X |

- Notes
- Message properties cannot have byte array values.
 - Values written as strings can be extracted as a numeric or boolean type only when it is possible to parse the string as a number of that type.

tibemsMsg

Type

Purpose Messages carry information among EMS client programs.

Related Types [tibemsBytesMsg](#), [tibemsMapMsg](#), [tibemsObjectMsg](#), [tibemsStreamMsg](#), [tibemsTextMsg](#)

| Function | Description | Page |
|---|---|------|
| Receipt | | |
| tibemsMsg_Acknowledge | Acknowledge messages. | 25 |
| Body | | |
| tibemsMsg_GetBodyType | Get the body type of a message. | 36 |
| Message Life Cycle | | |
| tibemsMsg_ClearBody | Clear the body of a message. | 27 |
| tibemsMsg_ClearProperties | Clear the properties of a message. | 28 |
| tibemsMsg_Create | Create a message object. | 29 |
| tibemsMsg_CreateCopy | Create a copy of the message object. | 30 |
| tibemsMsg_CreateFromBytes | Create a message object from data in a byte sequence. | 31 |
| tibemsMsg_Destroy | Destroy a message. | 32 |
| tibemsMsg_MakeWriteable | Make a message writeable. | 55 |
| tibemsMsg_Recover | Recover a single message. | 59 |
| Output | | |
| tibemsMsg_GetAsBytes | Get a byte sequence representation of the message object. | 33 |
| tibemsMsg_GetAsBytesCopy | Copies a byte sequence representation of the message object into storage supplied by the program. | 34 |
| tibemsMsg_GetByteSize | Computes the size of the byte sequence representation of the message. | 37 |

| Function | Description | Page |
|--|--|------|
| tibemsMsg_Print | Print a message. | 56 |
| tibemsMsg_PrintToBuffer | Prints a message into a buffer. | 57 |
| Headers and Properties | | |
| For details, see Headers on page 10. | | |
| tibemsMsg_ClearProperties | Clear the properties of a message. | 28 |
| tibemsMsg_GetCorrelationID | Get the correlation ID header of a message. | 38 |
| tibemsMsg_GetDeliveryMode | Get the delivery mode header from a message. | 40 |
| tibemsMsg_GetDeliveryTime | Get the delivery time header from a message. | 41 |
| tibemsMsg_GetDestination | Get the destination header from a message. | 42 |
| tibemsMsg_GetEncoding | Get the character encoding header from a message. | 43 |
| tibemsMsg_GetExpiration | Get the expiration header from a message. | 44 |
| tibemsMsg_GetMessageID | Get the message ID header from a message. | 45 |
| tibemsMsg_GetPriority | Get the priority header from a message. | 46 |
| tibemsMsg_Get_Property | Get the value of a message property. | 47 |
| tibemsMsg_GetPropertyNames | Get a list of property names from a message. | 50 |
| tibemsMsg_GetRedelivered | Get the redelivered header from a message. | 51 |
| tibemsMsg_GetReplyTo | Get the reply-to header from a message. | 52 |
| tibemsMsg_GetTimestamp | Get the timestamp header from a message. | 53 |
| tibemsMsg_GetType | Get the type header of a message. | 54 |
| tibemsMsg_PropertyExists | Test whether a named property has been set on a message. | 58 |
| tibemsMsg_SetCorrelationID | Set the correlation ID header of a message. | 60 |
| tibemsMsg_SetDeliveryMode | Set the delivery mode header of a message. | 62 |
| tibemsMsg_SetDestination | Set the destination header of a message. | 63 |

| Function | Description | Page |
|--|--|--------------------|
| tibemsMsg_Print | Print a message. | 56 |
| tibemsMsg_PrintToBuffer | Prints a message into a buffer. | 57 |
| Headers and Properties | | |
| For details, see Headers on page 10. | | |
| tibemsMsg_ClearProperties | Clear the properties of a message. | 28 |
| tibemsMsg_GetCorrelationID | Get the correlation ID header of a message. | 38 |
| tibemsMsg_GetDeliveryMode | Get the delivery mode header from a message. | 40 |
| tibemsMsg_GetDeliveryTime | Get the delivery time header from a message. | 41 |
| tibemsMsg_GetDestination | Get the destination header from a message. | 42 |
| tibemsMsg_GetEncoding | Get the character encoding header from a message. | 43 |
| tibemsMsg_GetExpiration | Get the expiration header from a message. | 44 |
| tibemsMsg_GetMessageID | Get the message ID header from a message. | 45 |
| tibemsMsg_GetPriority | Get the priority header from a message. | 46 |
| tibemsMsg_Get_Property | Get the value of a message property. | 47 |
| tibemsMsg_GetPropertyNames | Get a list of property names from a message. | 50 |
| tibemsMsg_GetRedelivered | Get the redelivered header from a message. | 51 |
| tibemsMsg_GetReplyTo | Get the reply-to header from a message. | 52 |
| tibemsMsg_GetTimestamp | Get the timestamp header from a message. | 53 |
| tibemsMsg_GetType | Get the type header of a message. | 54 |
| tibemsMsg_PropertyExists | Test whether a named property has been set on a message. | 58 |
| tibemsMsg_SetCorrelationID | Set the correlation ID header of a message. | 60 |
| tibemsMsg_SetDeliveryMode | Set the delivery mode header of a message. | 62 |
| tibemsMsg_SetDestination | Set the destination header of a message. | 63 |

| Function | Description | Page |
|--|---|------|
| tibemsMsg_SetEncoding | Set the character encoding header of a message. | 64 |
| tibemsMsg_SetExpiration | Set the expiration header of a message. | 65 |
| tibemsMsg_SetMessageID | Set the message ID header of a message. | 66 |
| tibemsMsg_SetPriority | Set the priority header of a message. | 67 |
| tibemsMsg_SetRedelivered | Set the redelivered header of a message. | 71 |
| tibemsMsg_SetReplyTo | Set the reply-to header of a message. | 72 |
| tibemsMsg_SetTimestamp | Set the timestamp header of a message. | 73 |
| tibemsMsg_SetType | Set the type header of a message. | 74 |
| tibemsMsg_Set_Property | Set the value of a message property. | 68 |

Table 7 Message Constants

| Constant | Description |
|------------------------------|--|
| TIBEMS_DEFAULT_DELIVERY_MODE | TIBEMS_PERSISTENT When neither the sending call nor the producer supplies a delivery mode, this default applies. |
| TIBEMS_DEFAULT_PRIORITY | 4 When neither the sending call nor the producer supplies a priority, this default applies. See also, Priority on page 12 . |
| TIBEMS_DEFAULT_TIME_TO_LIVE | 0 When neither the sending call nor the producer supplies a priority, this default applies. The default value, zero, indicates that messages do not expire. See also Expiration on page 11 . |

tibemsMsg_Acknowledge

Function

Purpose Acknowledge messages.

C Declaration `tibems_status tibemsMsg_Acknowledge(
tibemsMsg message);`

COBOL Call `CALL "tibemsMsg_Acknowledge"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Acknowledge this message (but for the actual behavior of this call, see the Remarks below). |

Remarks

The behavior of this call depends on the acknowledgement mode of the `tibemsSession`.

- In `TIBEMS_CLIENT_ACKNOWLEDGE` mode, this call acknowledges *all* messages that the program has consumed within the *session*. (This behavior complies with the JMS specification.)
- In `TIBEMS_EXPLICIT_CLIENT_ACKNOWLEDGE` mode, this call acknowledges *only* the individual message. (This mode and behavior are proprietary extensions, specific to TIBCO EMS.)
- In `TIBEMS_EXPLICIT_CLIENT_DUPS_OK_ACKNOWLEDGE` mode, this call lazily acknowledges *only* the individual message. *Lazy* means that the provider client library can delay transferring the acknowledgement to the server until a convenient time; meanwhile the server might redeliver the message. (This mode and behavior are proprietary extensions, specific to TIBCO EMS.)
- In all other modes, this call has no effect. In particular, modes that specify transactions or implicit acknowledgement do not require the consuming program to call this function. However, calling it does not produce an exception. (This behavior complies with the JMS specification.)

| | |
|-------------|---|
| Consumed | <p>Two events mark a message as <i>consumed</i>—that is, eligible for acknowledgment using this function:</p> <ul style="list-style-type: none">• Just before the provider calls an tibemsMsgCallback function, it marks the message argument as consumed.• Just before a receive call returns a message, it marks that message as consumed. |
| Redelivery | <p>The server might redeliver unacknowledged messages.</p> |
| Restriction | <p>It is illegal to call this function after closing the session, the connection or the consumer through which the message arrived.</p> |
| See Also | <p>tibemsMsgConsumer_Receive on page 170 tibemsSession on page 294 tibemsAcknowledgeMode on page 324</p> |

tibemsMsg_ClearBody

Function

Purpose Clear the body of a message.

C Declaration `tibems_status tibemsMsg_ClearBody(
tibemsMsg message);`

COBOL Call `CALL "tibemsMsg_ClearBody"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|------------------------|
| message | Message to be cleared. |

Remarks Clearing the body of a message leaves its header and property values unchanged. If the message body was read-only, this function makes it writeable. The message body appears and behaves identically to an empty body in a newly created message.

tibemsMsg_ClearProperties

Function

Purpose Clear the properties of a message.

C Declaration `tibems_status tibemsMsg_ClearProperties(
tibemsMsg message);`

COBOL Call `CALL "tibemsMsg_ClearProperties"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|------------------------|
| message | Message to be cleared. |

Remarks Clearing the property values of a message leaves its header values and body unchanged.

tibemsMsg_Create

Function

Purpose Create a message object.

C Declaration `tibems_status tibemsMsg_Create(
tibemsMsg* message);`

COBOL Call CALL "tibemsMsg_Create"
USING BY REFERENCE message,
RETURNING tibems-status
END-CALL.



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |

Remarks This call creates a new message.

When your application creates a message, it also allocates storage for that message. This storage must subsequently be freed by a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Destroy on page 32](#)

tibemsMsg_CreateCopy

Function

Purpose Create a copy of the message object.

C Declaration `tibems_status tibemsMsg_CreateCopy(
const tibemsMsg message,
tibemsMsg* copy);`

COBOL Call `CALL "tibemsMsg_CreateCopy"
USING BY VALUE message,
BY REFERENCE copy,
RETURNING tibems-status
END-CALL.`



message and copy have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Copy this message. |
| copy | The function stores a pointer to the new copy in this location. |

Remarks This call creates a new message by copying an existing message.

The copy is completely independent of the original message. Pointer data in fields are independent copies of the original values.

This function copies the entire message, including headers, properties, and body data.

This function allocates the storage for the copy. The duration of the copy is independent of the original message. Your program owns the messages that it creates, and must destroy those messages to reclaim the storage. That is, each call to this function must be paired with a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Destroy on page 32](#)

tibemsMsg_CreateFromBytes

Function

Purpose Create a message object from data in a byte sequence.

C Declaration `tibems_status tibemsMsg_CreateFromBytes(
tibemsMsg* message,
const void* bytes);`

COBOL Call `CALL "tibemsMsg_CreateFromBytes"
USING BY REFERENCE message,
BY REFERENCE bytes,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |
| bytes | Create a message from the data in this byte sequence. This data buffer represents the message in EMS wire format. To produce this type of buffer, use either tibemsMsg_GetAsBytes or tibemsMsg_GetAsBytesCopy . |

Remarks This call creates a new message from a byte sequence and populates the message with data.

This function allocates the storage for the new message. Your program owns the messages that it creates, and must destroy those messages to reclaim the storage. That is, each call to this function must be paired with a call to [tibemsMsg_Destroy](#).

The new message is independent of the original byte sequence. They do not share any storage.

The newly created message is read-only; to enable modification without erasing the content, call [tibemsMsg_MakeWriteable](#).

See Also [tibemsMsg_Destroy](#) on page 32
[tibemsMsg_GetAsBytes](#) on page 33
[tibemsMsg_GetAsBytesCopy](#) on page 34
[tibemsMsg_MakeWriteable](#) on page 55

tibemsMsg_Destroy

Function

Purpose Destroy a message.

C Declaration `tibems_status tibemsMsg_Destroy(
tibemsMsg message);`

COBOL Call CALL "tibemsMsg_Destroy"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|-----------------------|
| message | Destroy this message. |

tibemsMsg_GetAsBytes

Function

Purpose Get a byte sequence representation of the message object.

C Declaration

```
tibems_status tibemsMsg_GetAsBytes(
    const tibemsMsg message,
    const void** bytes,
    tibems_int* actual_size );
```

COBOL Call

```
CALL "tibemsMsg_GetAsBytes"
    USING BY VALUE message,
         BY REFERENCE bytes,
         BY REFERENCE actual-size,
         RETURNING tibems-status
END-CALL.
```



message and bytes have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| message | Fill the byte array with the content of this message. |
| bytes | The function allocates a byte sequence, and stores a pointer to it in this location. |
| actual_size | The function stores the length of the byte sequence in this location. |

Remarks This call formats the data of the message as a byte sequence in EMS wire format, which is suitable for archiving in a file.

The function allocates storage for the byte sequence, and associates it with the message; the byte sequence storage persists until your program destroys the message object.

Your program *must not* modify the byte sequence. To make a modifiable byte sequence, use [tibemsMsg_GetAsBytesCopy](#) instead.

The byte sequence includes data from the message header, message properties, and all message fields.

The byte sequence might contain interior null bytes.

See Also [tibemsMsg_CreateFromBytes](#) on page 31
[tibemsMsg_GetAsBytesCopy](#) on page 34
[tibemsMsg_GetByteSize](#) on page 37

tibemsMsg_GetAsBytesCopy

Function

Purpose Copies a byte sequence representation of the message object into storage supplied by the program.

C Declaration `tibems_status tibemsMsg_GetAsBytesCopy(
const tibemsMsg message,
const void* bytes,
tibems_int avail_size,
tibems_int* actual_size);`

COBOL Call `CALL "tibemsMsg_GetAsBytesCopy"
USING BY VALUE message,
BY REFERENCE bytes,
BY VALUE avail-size,
BY REFERENCE actual-size,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| message | Fill the byte array with the content of this message. |
| bytes | Your program must supply storage suitable for a byte sequence. The function stores the byte sequence in this location. |
| avail_size | The length of the storage available for the byte sequence. |
| actual_size | The function stores the length of the byte sequence in this location. |

Remarks This call formats the data of the message as a byte sequence in EMS wire format, which is suitable for archiving in a file.

Your program must allocate storage for the byte sequence, and supply a pointer to it as an argument.

The byte sequence includes data from the message header, message properties, and all message fields.

The byte sequence might contain interior null bytes.


| Status Code | Description |
|--|---|
| TIBEMS_INSUFFICIENT_BUFFER | The buffer is not large enough for the data. The return parameter <code>actual_size</code> indicates the size of the required buffer. |

See Also [tibemsMsg_CreateFromBytes on page 31](#)
[tibemsMsg_GetAsBytes on page 33](#)
[tibemsMsg_GetByteSize on page 37](#)

tibemsMsg_GetBodyType

Function


Purpose Get the body type of a message.



Message body type is distinct from message type—even though they have similar names. Contrast [tibemsMsg_GetType on page 54](#).

C Declaration `tibems_status tibemsMsg_GetBodyType(
tibemsMsg message,
tibemsMsgType* type);`

COBOL Call `CALL "tibemsMsg_GetBodyType"
USING BY VALUE message,
BY REFERENCE type,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | message | Get the body type of this message. |
| | type | The function stores the body type in this location. |

See Also [Body Types on page 9](#)
[tibemsMsgType on page 140](#)

tibemsMsg_GetByteSize

Function

Purpose Computes the size of the byte sequence representation of the message.

C Declaration `tibems_status tibemsMsg_GetByteSize(
tibemsMsg message,
tibems_int* size);`

COBOL Call `CALL "tibemsMsg_GetByteSize"
USING BY VALUE message,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Compute the size of this message. |
| size | The function stores the message size in this location. |

Remarks This call computes the size of a message in bytes. This measurement accounts for the actual space that the wire format message occupies, including its header, properties, and body data. (It does not include allocated storage that remains unused.)

Before calling [tibemsMsg_GetAsBytesCopy](#), use this call to measure the size of a message, then allocate sufficient space to store a copy.

You can also use this call to measure network throughput, or to limit a program’s output rate (also called *throttling*).

Deprecated Form `tibems_int tibemsMsg_ByteSize(
tibemsMsg message);`



Do not use this deprecated form. It will become obsolete in a future release.

See Also [tibemsMsg_GetAsBytesCopy on page 34](#)

tibemsMsg_GetCorrelationID

Function

Purpose Get the correlation ID header of a message.

C Declaration `tibems_status tibemsMsg_GetCorrelationID(
tibemsMsg message,
const char** value);`

COBOL Call `CALL "tibemsMsg_GetCorrelationID"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the correlation ID of this message. |
| value | The function stores the correlation ID in this location. |

Remarks Correlation ID refers to a related message. For example, when a consumer responds to a request message by sending a reply, it can set the correlation ID of the reply to indicate the request message.

The JMS specification allows three categories of values for the correlation ID property:

- **Message ID** A message ID is a unique string that the provider assigns to a message. Programs can use these IDs to correlate messages. For example, a program can link a response to a request by setting the correlation ID of a response message to the message ID of the corresponding request message.

Message ID strings begin with the prefix ID: (which is reserved for this purpose).

- **String** Programs can also correlate messages using arbitrary strings, with semantics determined by the application.

These strings must *not* begin with the prefix ID: (which is reserved for message IDs).

- **Byte Array** This implementation does not support byte array values for the correlation ID property. The JMS specification does not require support.

See Also [tibemsMsg_GetMessageID on page 45](#)
 [tibemsMsg_SetCorrelationID on page 60](#)

tibemsMsg_GetDeliveryMode

Function

Purpose Get the delivery mode header from a message.

C Declaration `tibems_status tibemsMsg_GetDeliveryMode(
tibemsMsg message,
tibemsDeliveryMode* value);`

COBOL Call `CALL "tibemsMsg_GetDeliveryMode"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get the delivery mode from this message. |
| value | The function stores the delivery mode in this location. |

Remarks Delivery mode is a header property of message objects.

See Also [tibemsDeliveryMode on page 129](#)
[tibemsMsg_SetDeliveryMode on page 62](#)

tibemsMsg_GetDeliveryTime

Function

Purpose Get the delivery time header from a message.

C Declaration `tibems_status tibemsMsg_GetDeliveryTime(
tibemsMsg message,
tibems_long* time);`

COBOL Call `CALL "tibemsMsg_GetDeliveryTime"
USING BY VALUE message,
BY REFERENCE time,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get the delivery time from this message. |
| time | The function stores the delivery time in this location. |

Remarks Sending calls record the delivery time of the message in this field.

The delivery time is the difference, measured in milliseconds, between the delivery time and midnight, January 1, 1970 UTC.

A message's delivery time is the earliest time when a JMS provider may deliver the message to a consumer. The provider must not deliver messages before the delivery time has been reached.

See Also [tibemsMsgProducer_GetDeliveryDelay on page 183](#)
[tibemsMsgProducer_SetDeliveryDelay on page 194](#)

tibemsMsg_GetDestination

Function

Purpose Get the destination header from a message.

C Declaration `tibems_status tibemsMsg_GetDestination(
tibemsMsg message,
tibemsDestination* value);`

COBOL Call `CALL "tibemsMsg_GetDestination"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get the destination from this message. |
| value | The function stores the destination in this location. |

Remarks Sending calls record the destination (queue or topic) of the message in this header (ignoring and overwriting any existing value). The value is based on either a property of the producer, or on a parameter to the send call.

Listeners that consume messages from several destinations can use this property to determine the actual destination of a message.

See Also [tibemsDestination on page 146](#)
[tibemsMsg_SetDestination on page 63](#)

tibemsMsg_GetEncoding

Function

Purpose Get the character encoding header from a message.

C Declaration `tibems_status tibemsMsg_GetEncoding(
const tibemsMsg message,
const char** value);`

COBOL Call `CALL "tibemsMsg_GetEncoding"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the character encoding from this message. |
| value | The function stores the character encoding in this location. |

Remarks This call extends the JMS specification.

This encoding applies to all strings in message bodies (names and values), and properties (names and values). It does *not* apply to header names nor values. The function `tibemsBytesMsg_ReadUTF` is exempt from message encoding settings.

See Also [Strings and Character Encodings on page 4](#)
[tibemsMsg_SetEncoding on page 64](#)

tibemsMsg_GetExpiration

Function

Purpose Get the expiration header from a message.

C Declaration `tibems_status tibemsMsg_GetExpiration(
tibemsMsg message,
tibems_long* value);`

COBOL Call `CALL "tibemsMsg_GetExpiration"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the expiration from this message. |
| value | The function stores the expiration in this location. |

Remarks Sending calls record the expiration time (in milliseconds) of the message in this field:

- If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client’s current time (GMT).
- If the time-to-live is zero, then expiration is also zero—indicating that the message never expires.

The server discards a message when its expiration time has passed. However, the JMS specification does not guarantee that clients do not receive expired messages.

See Also [tibemsMsg_SetExpiration on page 65](#)
[tibemsMsgProducer_GetTimeToLive on page 190](#)

tibemsMsg_GetMessageID

Function

Purpose Get the message ID header from a message.

C Declaration `tibems_status tibemsMsg_GetMessageID(
tibemsMsg message,
const char** value);`

COBOL Call `CALL "tibemsMsg_GetMessageID"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the message ID from this message. |
| value | The function stores the message ID in this location. |

Remarks Sending calls assign a unique ID to each message, and record it in this header. All message ID values start with the 3-character prefix ID: (which is reserved for this purpose). Applications that do not require message IDs can reduce overhead costs by disabling IDs; see [tibemsMsgProducer_SetDisableMessageID on page 196](#). When the producer disables IDs, the value of this header is null.

See Also [tibemsMsg_GetCorrelationID on page 38](#)
[tibemsMsg_SetMessageID on page 66](#)
[tibemsMsgProducer_SetDisableMessageID on page 196](#)

tibemsMsg_GetPriority

Function

Purpose Get the priority header from a message.

C Declaration `tibems_status tibemsMsg_GetPriority(
tibemsMsg message,
tibems_int* value);`

COBOL Call `CALL "tibemsMsg_GetPriority"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the priority from this message. |
| value | The function stores the priority in this location. |

Remarks Sending calls record the priority of a message in this header, based on either a property of the producer, or on a parameter to the send call.

The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.

Priority affects the order in which the server delivers messages to consumers (higher values first). The JMS specification does not require all providers to implement priority ordering of messages. (EMS supports priorities, but other JMS providers might not.)

See Also [tibemsMsg_SetPriority on page 67](#)
[tibemsMsgProducer_Send on page 191](#)
[tibemsMsgProducer_SetPriority on page 200](#)

tibemsMsg_Get Property

Function

Purpose Get the value of a message property.

C Declaration

```

tibems_status tibemsMsg_GetProperty(
    tibemsMsg message,
    const char* name,
    tibemsMsgField* value );

tibems_status tibemsMsg_GetBooleanProperty(
    tibemsMsg message,
    const char* name,
    tibems_bool* value );

tibems_status tibemsMsg_GetByteProperty(
    tibemsMsg message,
    const char* name,
    tibems_byte* value );

tibems_status tibemsMsg_GetDoubleProperty(
    tibemsMsg message,
    const char* name,
    tibems_double* value );

tibems_status tibemsMsg_GetFloatProperty(
    tibemsMsg message,
    const char* name,
    tibems_float* value );

tibems_status tibemsMsg_GetIntProperty(
    tibemsMsg message,
    const char* name,
    tibems_int* value );

tibems_status tibemsMsg_GetLongProperty(
    tibemsMsg message,
    const char* name,
    tibems_long* value );

tibems_status tibemsMsg_GetShortProperty(
    tibemsMsg message,
    const char* name,
    tibems_short* value );

tibems_status tibemsMsg_GetStringProperty(
    tibemsMsg message,
    const char* name,
    char** value );

```

```

COBOL Call    CALL "tibemsMsg_GetProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetBooleanProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetByteProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetDoubleProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetFloatProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetIntProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetLongProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

                CALL "tibemsMsg_GetShortProperty"
                USING BY VALUE message,
                    BY REFERENCE name,
                    BY REFERENCE value,
                    RETURNING tibems-status
                END-CALL.

```

```
CALL "tibemsMsg_GetStringProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY REFERENCE value,
        RETURNING tibems-status
END-CALL.
```



message has usage pointer.

value has usage pointer only in `tibemsMsg_GetStringProperty` (but not in the other calls documented in this group).

Parameters

| Parameter | Description |
|-----------|--|
| message | Get a property from this message. |
| name | Get the property with this name (case sensitive). Property names must obey the JMS rules for a message selector identifier (see Message Selectors on page 17). Property names must not be null, and must not be empty strings. |
| value | The call stores the value in this location. |

Remarks

The JMS specification defines eight calls to get properties with different value types—converting between compatible types. All of these functions convert property values to the corresponding type (if possible).

| Status Code | Description |
|--|--|
| TIBEMS_CONVERSION_FAILED | The actual type of the property is not compatible with the requested type. |
| TIBEMS_NOT_FOUND | The property is not set in this message. |

See Also

[tibemsMsg_Set Property on page 68](#)

tibemsMsg_GetPropertyNames

Function

Purpose Get a list of property names from a message.

C Declaration `tibems_status tibemsMsg_GetPropertyNames(
tibemsMsg message,
tibemsMsgEnum* enumeration);`

COBOL Call `CALL "tibemsMsg_GetPropertyNames"
USING BY VALUE message,
BY REFERENCE enumeration,
RETURNING tibems-status
END-CALL.`



message and enumeration have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| message | Get the property names from this message. |
| enumeration | The function stores the property names in this location. |

See Also [tibemsMsgEnum on page 132](#)

tibemsMsg_GetRedelivered

Function

Purpose Get the redelivered header from a message.

C Declaration `tibems_status tibemsMsg_GetRedelivered(
tibemsMsg message,
tibems_bool* value);`

COBOL Call `CALL "tibemsMsg_GetRedelivered"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get the redelivered indicator from this message. |
| value | The function stores the redelivered indicator in this location. |

Remarks The server sets this header to indicate whether a message might duplicate a previously delivered message:

- false—The server has *not* previously attempted to deliver this message to the consumer.
- true—It is likely, but not guaranteed, that this message was delivered earlier but that its receipt was not acknowledged at that time.

See Also [tibemsMsg_SetRedelivered on page 71](#)

tibemsMsg_GetReplyTo

Function

Purpose Get the reply-to header from a message.

C Declaration `tibems_status tibemsMsg_GetReplyTo(
tibemsMsg message,
tibemsDestination* value);`

COBOL Call `CALL "tibemsMsg_GetReplyTo"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get the reply-to header from this message. |
| value | The function stores the reply-to header in this location. |

Remarks Sending clients can set this header to request that recipients reply to the message:

- When the value is a destination object, recipients can send replies to that destination. Such a message is called a *request*.
- When the value is null, the sender does not expect a reply.

When sending a reply, clients can refer to the corresponding request by setting the correlation ID field.

See Also [tibemsMsg_SetCorrelationID on page 60](#)
[tibemsMsg_SetReplyTo on page 72](#)

tibemsMsg_GetTimestamp

Function

Purpose Get the timestamp header from a message.

C Declaration `tibems_status tibemsMsg_GetTimestamp(
tibemsMsg message,
tibems_long* value);`

COBOL Call `CALL "tibemsMsg_GetTimestamp"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get the timestamp from this message. |
| value | The function stores the timestamp in this location. |

Remarks Sending calls record a UTC timestamp in this header, indicating the approximate time that the server accepted the message.

The value is in milliseconds since January 1, 1970 (as in Java).


Applications that do not require timestamps can reduce overhead costs by disabling timestamps; see [tibemsMsgProducer_SetDisableMessageTimestamp on page 197](#). When the producer disables timestamps, the value of this header is zero.

See Also [tibemsMsg_SetTimestamp on page 73](#)
[tibemsMsgProducer_SetDisableMessageTimestamp on page 197](#)

tibemsMsg_GetType

Function

Purpose Get the type header of a message.




Message type is distinct from message body type—even though they have similar names. Contrast [tibemsMsg_GetBodyType on page 36](#).

C Declaration

```
tibems_status tibemsMsg_GetType(  
    tibemsMsg message,  
    const char** value );
```

COBOL Call

```
CALL "tibemsMsg_GetType"  
    USING BY VALUE message,  
          BY REFERENCE value,  
          RETURNING tibems-status  
END-CALL.
```



message and value have usage pointer.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | message | Get the type header of this message. |
| | value | The function stores the type in this location. |

Remarks

Some JMS providers use a message repository to store message type definitions. Client programs can store a body type that references a definition in the repository. EMS supports this header, but does not use it.

The JMS specification does not define a standard message definition repository, nor does it define a naming policy for message type definitions.

Some providers require message type definitions for each application message. To ensure compatibility with such providers, client programs can set this header, even if the client application does not use it.

To ensure portability, clients can set this header with symbolic values (rather than literals), and configure them to match the provider’s repository.

See Also [tibemsMsg_SetType on page 74](#)

tibemsMsg_MakeWriteable

Function

Purpose Make a message writeable.

C Declaration `tibems_status tibemsMsg_MakeWriteable(
 tibemsMsg message);`

COBOL Call `CALL "tibemsMsg_MakeWriteable"
 USING BY VALUE message,
 RETURNING tibems-status
 END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|------------------------------|
| message | Make this message writeable. |

tibemsMsg_Print

Function

- Purpose**
- Print a message.
- C Declaration**
- ```
void tibemsMsg_Print(
 tibemsMsg message);
```
- COBOL Call**
- ```
CALL "tibemsMsg_Print"  
    USING BY VALUE message,  
    END-CALL.
```



message has usage pointer.

| Parameters | Parameter | Description |
|------------|---|---------------------|
| | message | Print this message. |
| Remarks | <p>This call prints a string that includes the body type, headers (name-value pairs), properties (name-value pairs), and body content.</p> <p>tibemsMsg_Print prints the message to stdout.</p> | |
| See Also | tibemsMsg_PrintToBuffer on page 57 | |

tibemsMsg_PrintToBuffer

Function

Purpose Prints a message into a buffer.

C Declaration `tibems_status tibemsMsg_PrintToBuffer(
tibemsMsg message,
char* buffer,
tibems_int maxlen);`

COBOL Call `CALL "tibemsMsg_PrintToBuffer"
USING BY VALUE message,
BY REFERENCE buffer,
BY VALUE maxlen,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Print this message. |
| buffer | Location to store the string representation of the message. |
| maxlen | The size of the buffer. |

Remarks This call prints a string that includes the body type, headers (name-value pairs), properties (name-value pairs), and body content.

tibemsMsg_PrintToBuffer prints the message to a buffer.

| Status Code | Description |
|----------------------------|---|
| TIBEMS_INSUFFICIENT_BUFFER | The buffer is too small to hold the data. |

See Also [tibemsMsg_Print on page 56](#)

tibemsMsg_PropertyExists

Function

Purpose Test whether a named property has been set on a message.

C Declaration `tibems_status tibemsMsg_PropertyExists(
tibemsMsg message,
const char* name,
tibems_bool* result);`

COBOL Call `CALL "tibemsMsg_PropertyExists"
USING BY VALUE message,
BY REFERENCE name,
BY REFERENCE result,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Test this message for the property. |
| name | Test whether the message has a property with this name. |
| result | The function stores the boolean result of the test in this location: <ul style="list-style-type: none">TIBEMS_TRUE if the property has a value on the messageTIBEMS_FALSE otherwise |

tibemsMsg_Recover

Function

- Purpose

Recover a single message.
- C Declaration

`tibems_status tibemsMsg_Recover(
tibemsMsg message);`
- COBOL Call

`CALL "tibemsMsg_Recover"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--------------------------------|
| message | Recover the specified message. |

- Remarks

When the application calls this function, TIBCO Enterprise Message Service puts this message back on the queue or topic and makes it available for redelivery. The JMSRedelivered header is set to true.

This call is only legal for the [TIBEMS_EXPLICIT_CLIENT_ACKNOWLEDGE](#) and [TIBEMS_EXPLICIT_CLIENT_DUPS_OK_ACKNOWLEDGE](#) acknowledgement modes. In all other modes, this call returns [TIBEMS_ILLEGAL_STATE](#).

This function recovers only the specified message. To recover all unacknowledged messages from a session, use [tibemsSession_Recover](#).
- Restriction

It is illegal to call this function on an acknowledged message or on a message that is included in a transaction.

Additionally, it is illegal to call this function twice on the same message, or again on a message that was previously recovered using [tibemsSession_Recover](#).
- See Also

[tibemsSession_Recover](#) on page 321
[tibemsAcknowledgeMode](#) on page 324

tibemsMsg_SetCorrelationID

Function

Purpose Set the correlation ID header of a message.

C Declaration `tibems_status tibemsMsg_SetCorrelationID(
tibemsMsg message,
const char* value);`

COBOL Call `CALL "tibemsMsg_SetCorrelationID"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Set the correlation ID of this message. |
| value | Set the correlation ID to this value. |

Remarks Correlation ID refers to a related message. For example, when a consumer responds to a request message by sending a reply, it can set the correlation ID of the reply to indicate the request message.

The JMS specification allows three categories of values for the correlation ID property:

- **Message ID** A message ID is a unique string that the provider assigns to a message. Programs can use these IDs to correlate messages. For example, a program can link a response to a request by setting the correlation ID of a response message to the message ID of the corresponding request message.

Message ID strings begin with the prefix ID: (which is reserved for this purpose).

- **String** Programs can also correlate messages using arbitrary strings, with semantics determined by the application.

These strings must *not* begin with the prefix ID: (which is reserved for message IDs).

- **Byte Array** This implementation does not support byte array values for the correlation ID property. The JMS specification does not require support.

See Also [tibemsMsg_GetCorrelationID on page 38](#)
 [tibemsMsg_GetMessageID on page 45](#)

tibemsMsg_SetDeliveryMode

Function

Purpose Set the delivery mode header of a message.

C Declaration `tibems_status tibemsMsg_SetDeliveryMode(
tibemsMsg message,
tibemsDeliveryMode value);`

COBOL Call `CALL "tibemsMsg_SetDeliveryMode"
USING BY VALUE message,
BY VALUE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Set the delivery mode of this message. |
| value | Set the delivery mode to this value. |

Remarks Sending calls set the delivery mode header automatically. The JMS specification defines this call for symmetry.

See Also [tibemsDeliveryMode on page 129](#)
[tibemsMsg_GetDeliveryMode on page 40](#)

tibemsMsg_SetDestination

Function

Purpose Set the destination header of a message.

C Declaration `tibems_status tibemsMsg_SetDestination(
tibemsMsg message,
tibemsDestination value);`

COBOL Call `CALL "tibemsMsg_SetDestination"
USING BY VALUE message,
BY VALUE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|--------------------------------------|
| message | Set the destination of this message. |
| value | Set the destination to this value. |

Remarks Sending calls set the delivery mode header automatically. The JMS specification defines this call for symmetry.

Sending calls record the destination (queue or topic) of the message in this header (ignoring and overwriting any existing value). The value is based on either a property of the producer, or on a parameter to the send call.

See Also [tibemsDestination on page 146](#)
[tibemsMsg_GetDestination on page 42](#)
[tibemsMsgProducer_Send on page 191](#)
[tibemsMsgProducer_GetDestination on page 185](#)

tibemsMsg_SetEncoding

Function

Purpose Set the character encoding header of a message.

C Declaration `tibems_status tibemsMsg_SetEncoding(
tibemsMsg message,
const char* value);`

COBOL Call `CALL "tibemsMsg_SetEncoding"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Set the character encoding of this message. |
| value | Set the character encoding to this value. For a list of standard encoding names, see www.iana.org . |

Remarks This call extends the JMS specification.
Programs can set the encoding for individual messages.
This encoding applies to all strings in message bodies (names and values), and properties (names and values). It does *not* apply to header names nor values. The function `tibemsBytesMsg_ReadUTF` is exempt from message encoding settings.

See Also [Strings and Character Encodings on page 4](#)
[tibemsMsg_GetEncoding on page 43](#)

tibemsMsg_SetExpiration

Function

Purpose Set the expiration header of a message.

C Declaration `tibems_status tibemsMsg_SetExpiration(
tibemsMsg message,
tibems_long value);`

COBOL Call `CALL "tibemsMsg_SetExpiration"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|-------------------------------------|
| message | Set the expiration of this message. |
| value | Set the expiration to this value. |

Remarks Sending calls set the expiration header automatically. The JMS specification defines this call for symmetry.

Sending calls record the expiration time (in milliseconds) of the message in this field:

- If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client’s current time (GMT).
- If the time-to-live is zero, then expiration is also zero—indicating that the message never expires.

The server discards a message when its expiration time has passed. However, the JMS specification does not guarantee that clients do not receive expired messages.

See Also [tibemsMsg_GetExpiration on page 44](#)
[tibemsMsgProducer_GetTimeToLive on page 190](#)
[tibemsMsgProducer_SetTimeToLive on page 201](#)

tibemsMsg_SetMessageID

Function

Purpose Set the message ID header of a message.

C Declaration `tibems_status tibemsMsg_SetMessageID(
tibemsMsg message,
const char* value);`

COBOL Call `CALL "tibemsMsg_SetMessageID"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|-------------------------------------|
| message | Set the message ID of this message. |
| value | Set the message ID to this value. |

Remarks Sending calls set the message ID header automatically. The JMS specification defines this call for symmetry.

Sending calls assign a unique ID to each message, and record it in this header.

All message ID values start with the 3-character prefix ID: (which is reserved for this purpose).

Applications that do not require message IDs can reduce overhead costs by disabling IDs; see [tibemsMsgProducer_SetDisableMessageID on page 196](#). When the producer disables IDs, the value of this header is null.

See Also [tibemsMsg_GetCorrelationID on page 38](#)
[tibemsMsg_GetMessageID on page 45](#)
[tibemsMsg_SetCorrelationID on page 60](#)
[tibemsMsgProducer_SetDisableMessageID on page 196](#)

tibemsMsg_SetPriority

Function

Purpose Set the priority header of a message.

C Declaration `tibems_status tibemsMsg_SetPriority(
tibemsMsg message,
tibems_int value);`

COBOL Call `CALL "tibemsMsg_SetPriority"
USING BY VALUE message,
BY VALUE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|-----------------------------------|
| message | Set the priority of this message. |
| value | Set the priority to this value. |

Remarks Sending calls set the priority header automatically. The JMS specification defines this call for symmetry.

Sending calls record the priority of a message in this header, based on either a property of the producer, or on a parameter to the send call.

The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.

Priority affects the order in which the server delivers messages to consumers (higher values first). The JMS specification does not require all providers to implement priority ordering of messages. (EMS supports priorities, but other JMS providers might not.)

See Also [tibemsMsg_GetPriority on page 46](#)
[tibemsMsgProducer_GetPriority on page 189](#)
[tibemsMsgProducer_SetPriority on page 200](#)

tibemsMsg_Set Property

Function

Purpose Set the value of a message property.

C Declaration

```

tibems_status tibemsMsg_SetBooleanProperty(
    tibemsMsg message,
    const char* name,
    tibems_bool value );

tibems_status tibemsMsg_SetByteProperty(
    tibemsMsg message,
    const char* name,
    tibems_byte value );

tibems_status tibemsMsg_SetDoubleProperty(
    tibemsMsg message,
    const char* name,
    tibems_double value );

tibems_status tibemsMsg_SetFloatProperty(
    tibemsMsg message,
    const char* name,
    tibems_float value );

tibems_status tibemsMsg_SetIntProperty(
    tibemsMsg message,
    const char* name,
    tibems_int value );

tibems_status tibemsMsg_SetLongProperty(
    tibemsMsg message,
    const char* name,
    tibems_long value );

tibems_status tibemsMsg_SetShortProperty(
    tibemsMsg message,
    const char* name,
    tibems_short value );

tibems_status tibemsMsg_SetStringProperty(
    tibemsMsg message,
    const char* name,
    const char* value );

```

COBOL Call

```

CALL "tibemsMsg_SetBooleanProperty"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

```

```
CALL "tibemsMsg_SetByteProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMsg_SetDoubleProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMsg_SetFloatProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMsg_SetIntProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMsg_SetLongProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMsg_SetShortProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMsg_SetStringProperty"
  USING BY VALUE message,
        BY REFERENCE name,
        BY REFERENCE value,
        RETURNING tibems-status
END-CALL.
```



message has usage pointer.

value has usage pointer only in tibemsMsg_SetStringProperty (but not in the other calls documented in this group).

| Parameters | Parameter | Description |
|------------|---|--|
| | message | Set a property on this message. Property names must obey the JMS rules for a message selector identifier (see Message Selectors on page 17). Property names must not be null, and must not be empty strings. |
| | name | Set a property with this name. Property names must obey the JMS rules for a message selector identifier (see Message Selectors on page 17). Property names must not be null, and must not be empty strings. |
| | value | Set the property to this value. |
| Remarks | The JMS specification defines eight calls to set properties with different primitive value types. | |
| | Status Code | Description |
| | TIBEMS_MSG_NOT_WRITEABLE | The message is read-only. |
| See Also | tibemsMsg_Get Property on page 47 | |

tibemsMsg_SetRedelivered

Function

Purpose Set the redelivered header of a message.

C Declaration `tibems_status tibemsMsg_SetRedelivered(
tibemsMsg message,
tibems_bool value);`

COBOL Call `CALL "tibemsMsg_SetRedelivered"
USING BY VALUE message,
BY VALUE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Set the redelivered indicator of this message. |
| value | Set the redelivered indicator to this value. |

Remarks Sending calls set the redelivered header automatically. The JMS specification defines this call for symmetry.

The server sets this header to indicate whether a message might duplicate a previously delivered message:

- false—The server has *not* previously attempted to deliver this message to the consumer.
- true—It is likely (but not guaranteed) that the server has previously attempted to deliver this message to the consumer, but the consumer did not return timely acknowledgement.

See Also [tibemsMsg_GetRedelivered on page 51](#)

tibemsMsg_SetReplyTo

Function

Purpose Set the reply-to header of a message.

C Declaration `tibems_status tibemsMsg_SetReplyTo(
tibemsMsg message,
tibemsDestination value);`

COBOL Call `CALL "tibemsMsg_SetReplyTo"
USING BY VALUE message,
BY VALUE value,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Set the reply-to header of this message. |
| value | Set the reply-to header to this value. |

Remarks Sending clients can set this header to request that recipients reply to the message:

- When the value is a destination object, recipients can send replies to that destination. Such a message is called a *request*.
- When the value is null, the sender does not expect a reply.

When sending a reply, clients can refer to the corresponding request by setting the correlation ID field.

See Also [tibemsMsg_GetReplyTo on page 52](#)
[tibemsMsg_SetCorrelationID on page 60](#)

tibemsMsg_SetTimestamp

Function

Purpose Set the timestamp header of a message.

C Declaration `tibems_status tibemsMsg_SetTimestamp(
tibemsMsg message,
tibems_long value);`

COBOL Call `CALL "tibemsMsg_SetTimestamp"
USING BY VALUE message,
BY VALUE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|------------------------------------|
| message | Set the timestamp of this message. |
| value | Set the timestamp to this value. |

Remarks Sending calls set the timestamp header automatically. The JMS specification defines this call for symmetry.

Sending calls record a UTC timestamp in this header, indicating the approximate time that the server accepted the message.

The value is in milliseconds since January 1, 1970 (as in Java).


Applications that do not require timestamps can reduce overhead costs by disabling timestamps; see [tibemsMsgProducer_SetDisableMessageTimestamp on page 197](#). When the producer disables timestamps, the value of this header is zero.

See Also [tibemsMsg_GetTimestamp on page 53](#)
[tibemsMsgProducer_SetDisableMessageTimestamp on page 197](#)

tibemsMsg_SetType

Function

Purpose Set the type header of a message.




Message type is distinct from message body type—even though they have similar names. Contrast [tibemsMsg_GetBodyType on page 36](#).

C Declaration

```
tibems_status tibemsMsg_SetType(  
    tibemsMsg message,  
    const char* value );
```

COBOL Call

```
CALL "tibemsMsg_SetType"  
    USING BY VALUE message,  
          BY REFERENCE value,  
          RETURNING tibems-status  
END-CALL.
```



message has usage pointer.

| Parameters | Parameter | Description |
|------------|-----------|--------------------------------------|
| | message | Set the type header of this message. |
| | value | Set the type to this value. |

Remarks

Some JMS providers use a message repository to store message type definitions. Client programs can store a body type that references a definition in the repository. EMS supports this header, but does not use it.

The JMS specification does not define a standard message definition repository, nor does it define a naming policy for message type definitions.

Some providers require message type definitions for each application message. To ensure compatibility with such providers, client programs can set this header, even if the client application does not use it.

To ensure portability, clients can set this header with symbolic values (rather than literals), and configure them to match the provider’s repository.

See Also [tibemsMsg_GetType on page 54](#)

tibemsBytesMsg

Type

Purpose A message containing a stream of uninterpreted bytes.

Related Types [tibemsMsg on page 21](#)

Remarks Messages with this body type contain a single value, which is a byte sequence.

| Function | Description | Page |
|--|--|------|
| tibemsBytesMsg_Create | Create a bytes message. | 76 |
| tibemsBytesMsg_GetBodyLength | Get the body length (in bytes) of a bytes message. | 77 |
| tibemsBytesMsg_GetBytes | Get the body data of a bytes message. | 78 |
| tibemsBytesMsg_Read | Read primitive datatypes from the byte stream in the message body. | 79 |
| tibemsBytesMsg_ReadBytes | Read bytes to a byte sequence from the byte stream in the message body. | 82 |
| tibemsBytesMsg_Reset | Set the read position to the beginning of the byte stream, and mark the message body as read-only. | 84 |
| tibemsBytesMsg_SetBytes | Set the body data of a bytes message from a byte sequence. | 85 |
| tibemsBytesMsg_Write | Write primitive datatypes to the byte stream in the message body. | 86 |
| tibemsBytesMsg_WriteBytes | Write bytes from a byte array to the byte stream in the message body. | 89 |

tibemsBytesMsg_Create

Function

Purpose Create a bytes message.

C Declaration `tibems_status tibemsBytesMsg_Create(
tibemsBytesMsg* message);`

COBOL Call CALL "tibemsBytesMsg_Create"
USING BY REFERENCE message,
RETURNING tibems-status
END-CALL.



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |

Remarks This call creates a new bytes message.

When your application creates a message, it also allocates storage for that message. This storage must subsequently be freed by a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Create on page 29](#)
[tibemsMsg_Destroy on page 32](#)

tibemsBytesMsg_GetBodyLength

Function

Purpose Get the body length (in bytes) of a bytes message.

C Declaration `tibems_status tibemsBytesMsg_GetBodyLength(
tibemsMsg message,
tibems_int* return_length);`

COBOL Call `CALL "tibemsBytesMsg_GetBodyLength"
USING BY VALUE message,
BY REFERENCE return-length,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|---------------|---|
| message | Get the body length of this message. |
| return_length | The function stores the body length in this location. |

tibemsBytesMsg_GetBytes

Function

Purpose Get the body data of a bytes message.

C Declaration `tibems_status tibemsBytesMsg_GetBytes(
tibemsBytesMsg message,
void** bytes,
tibems_uint* byteSize);`

COBOL Call `CALL "tibemsBytesMsg_GetBytes"
USING BY VALUE message,
BY REFERENCE bytes,
BY REFERENCE byteSize,
RETURNING tibems-status
END-CALL.`



message and bytes have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the byte sequence of this bytes message. |
| bytes | The function stores a pointer to the bytes of the message in this location. Your program must not change the bytes, which belong to the message; if you must modify the bytes, make a private copy first. |
| byteSize | The function stores the length of the byte sequence in this location. |

Remarks This call extracts a pointer to the body data of a bytes message.

The byte sequence storage persists until your program destroys the message object.

tibemsBytesMsg_Read

Function

Purpose Read primitive datatypes from the byte stream in the message body.

C Declaration

```

tibems_status tibemsBytesMsg_ReadBoolean(
    tibemsBytesMsg message,
    tibems_bool* value );

tibems_status tibemsBytesMsg_ReadByte(
    tibemsBytesMsg message,
    tibems_byte* value );

tibems_status tibemsBytesMsg_ReadChar(
    tibemsBytesMsg message,
    tibems_wchar* value );

tibems_status tibemsBytesMsg_ReadDouble(
    tibemsBytesMsg message,
    tibems_double* value );

tibems_status tibemsBytesMsg_ReadFloat(
    tibemsBytesMsg message,
    tibems_float* value );

tibems_status tibemsBytesMsg_ReadInt(
    tibemsBytesMsg message,
    tibems_int* value );

tibems_status tibemsBytesMsg_ReadLong(
    tibemsBytesMsg message,
    tibems_long* value );

tibems_status tibemsBytesMsg_ReadShort(
    tibemsBytesMsg message,
    tibems_short* value );

tibems_status tibemsBytesMsg_ReadUnsignedByte(
    tibemsBytesMsg message,
    tibems_int* value );

tibems_status tibemsBytesMsg_ReadUnsignedShort(
    tibemsBytesMsg message,
    tibems_int* value );

```

```

COBOL Call    CALL "tibemsBytesMsg_ReadBoolean"
                USING BY VALUE message,
                   BY REFERENCE tibems-Boolean,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadByte"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadChar"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadDouble"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadFloat"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadInt"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadLong"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadShort"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

                CALL "tibemsBytesMsg_ReadUnsignedByte"
                USING BY VALUE message,
                   BY REFERENCE value,
                   RETURNING tibems-status
                END-CALL.

```

```
CALL "tibemsBytesMsg_ReadUnsignedShort"
  USING BY VALUE message,
        BY REFERENCE value,
        RETURNING tibems-status
END-CALL.
```



message has usage pointer in all calls.

Parameters

| Parameter | Description |
|-----------|---|
| message | Read a datum from the body byte stream of this message. |
| value | The function stores the datum in this location. |

Remarks

The JMS specification defines eleven calls to extract data from the byte stream body of a [tibemsBytesMsg](#). Each call reads a unit of data from the stream, and advances the read position so that the next read call gets the next datum.

Table 8 BytesMessage Read Functions

| Function | # Bytes | Interpret As |
|--|---------|-------------------------------|
| tibemsBytesMsg_ReadBoolean | 1 | tibems_bool |
| tibemsBytesMsg_ReadByte | 1 | tibems_byte |
| tibemsBytesMsg_ReadUnsignedByte | 1 | tibems_int |
| tibemsBytesMsg_ReadShort | 2 | tibems_short |
| tibemsBytesMsg_ReadUnsignedShort | 2 | tibems_int |
| tibemsBytesMsg_ReadChar | 2 | tibems_wchar |
| tibemsBytesMsg_ReadInt | 4 | tibems_int |
| tibemsBytesMsg_ReadLong | 8 | tibems_long |
| tibemsBytesMsg_ReadFloat | 4 | tibems_float |
| tibemsBytesMsg_ReadDouble | 8 | tibems_double |
| tibemsBytesMsg_ReadUTF | varies | char* Encoded as UTF. |

See Also

[tibemsBytesMsg_ReadBytes](#) on page 82

tibemsBytesMsg_ReadBytes

Function

Purpose Read bytes to a byte sequence from the byte stream in the message body.

C Declaration `tibems_status tibemsBytesMsg_ReadBytes(
tibemsBytesMsg message,
const void** value,
tibems_int requested_length,
tibems_int* return_length);`

COBOL Call `CALL "tibemsBytesMsg_ReadBytes"
USING BY VALUE message,
BY REFERENCE value,
BY VALUE requested-length,
BY REFERENCE return-length,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|------------------|--|
| message | Read bytes from the body of this message. |
| value | <p>The program supplies a location. In that location, this call stores a pointer to the next block of bytes within the bytes message.</p> <p>Your program must not change the bytes, which belong to the message; if you must modify the bytes, make a private copy first.</p> |
| requested_length | <p>Read (at most) this number of bytes from the stream.</p> <p>This argument must be greater than zero.</p> |

| Parameter | Description |
|---------------|---|
| return_length | <p>The function stores in this location the actual number of bytes that it read. (If the number of bytes remaining in the message is less than the requested_length, then this location indicates that number of remaining bytes. Your program must not use bytes beyond this limit.)</p> <p>When the function cannot read even one byte, it stores -1 in this location (and returns a successful status code).</p> |

Remarks Each call reads bytes from the stream into the byte array, and advances the read position.

tibemsBytesMsg_Reset

Function

Purpose Set the read position to the beginning of the byte stream, and mark the message body as read-only.

C Declaration `tibems_status tibemsBytesMsg_Reset(
tibemsBytesMsg message);`

COBOL Call CALL "tibemsBytesMsg_Reset"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.



message has usage pointer.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | message | Reset the read position for this message. |

Remarks This call prepares a message body for reading, as if the message were newly received. Contrast [tibemsMsg_ClearBody on page 27](#), which clears a message body in preparation for writing, as if it were newly created.

tibemsBytesMsg_SetBytes

Function

Purpose Set the body data of a bytes message from a byte sequence.

C Declaration

```
tibems_status tibemsBytesMsg_SetBytes(
    tibemsBytesMsg message,
    const void* bytes,
    tibems_uint byteSize );
```

COBOL Call

```
CALL "tibemsBytesMsg_SetBytes"
  USING BY VALUE message,
        BY REFERENCE bytes,
        BY VALUE byteSize,
        RETURNING tibems-status
END-CALL.
```



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Set the body data of this bytes message. |
| bytes | Copy this byte sequence into the message body. |
| byteSize | Copy this number of bytes into the message. |

tibemsBytesMsg_Write

Function

Purpose Write primitive datatypes to the byte stream in the message body.

C Declaration

```

tibems_status tibemsBytesMsg_WriteBoolean(
    tibemsBytesMsg message,
    tibems_bool value );

tibems_status tibemsBytesMsg_WriteByte(
    tibemsBytesMsg message,
    tibems_byte value );

tibems_status tibemsBytesMsg_WriteChar(
    tibemsBytesMsg message,
    tibems_wchar value );

tibems_status tibemsBytesMsg_WriteDouble(
    tibemsBytesMsg message,
    tibems_double value );

tibems_status tibemsBytesMsg_WriteFloat(
    tibemsBytesMsg message,
    tibems_float value );

tibems_status tibemsBytesMsg_WriteInt(
    tibemsBytesMsg message,
    tibems_int value );

tibems_status tibemsBytesMsg_WriteLong(
    tibemsBytesMsg message,
    tibems_long value );

tibems_status tibemsBytesMsg_WriteShort(
    tibemsBytesMsg message,
    tibems_short value );

```

COBOL Call

```

CALL "tibemsBytesMsg_WriteBoolean"
  USING BY VALUE message,
        BY VALUE tibems-Boolean,
        RETURNING tibems-status
END-CALL.

CALL "tibemsBytesMsg_WriteByte"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

```



```
CALL "tibemsBytesMsg_WriteChar"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsBytesMsg_WriteDouble"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsBytesMsg_WriteFloat"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsBytesMsg_WriteInt"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsBytesMsg_WriteLong"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsBytesMsg_WriteShort"
  USING BY VALUE message,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.
```



message has usage pointer in all calls.

Parameters

| Parameter | Description |
|-----------|---|
| message | Write data to the body of this bytes message. |
| value | Write this value to the message. |

Remarks

The JMS specification defines these nine calls to insert data into the byte stream of a `BytesMessage`.

Each call writes a data value to the stream, and advances the write position so that the next write call appends to the new end of the stream.

Table 9 *BytesMessage Write Functions*

| Function | # Bytes | Notes |
|-----------------------------|---------|---|
| tibemsBytesMsg_WriteBoolean | 1 | This function writes true as (byte)1, and false as (byte)0. |
| tibemsBytesMsg_WriteByte | 1 | |
| tibemsBytesMsg_WriteShort | 2 | |
| tibemsBytesMsg_WriteChar | 2 | This function writes a 2-byte character—high byte first. |
| tibemsBytesMsg_WriteInt | 4 | |
| tibemsBytesMsg_WriteLong | 8 | |
| tibemsBytesMsg_WriteFloat | 4 | |
| tibemsBytesMsg_WriteDouble | 8 | |

See Also [tibemsBytesMsg_WriteBytes on page 89](#)

tibemsBytesMsg_WriteBytes

Function

Purpose Write bytes from a byte array to the byte stream in the message body.

C Declaration `tibems_status tibemsBytesMsg_WriteBytes(
tibemsBytesMsg message,
const void* value,
tibems_uint length);`

COBOL Call `CALL "tibemsBytesMsg_WriteBytes"
USING BY VALUE message,
BY REFERENCE value,
BY VALUE size,
RETURNING tibems-status
END-CALL.`



message has usage pointer in all calls.

Parameters

| Parameter | Description |
|-----------|---|
| message | Write bytes into the body data of this bytes message. |
| value | Write bytes from this byte array into the message. |
| length | Write this number of bytes from the byte array. |

Remarks Each call writes bytes from the byte array into the stream, and advances the write position.

tibemsMapMsg

Type

- Purpose** A message containing a set of name-value pairs.
- Related Types** [tibemsMsg on page 21](#)
- Remarks** Messages with this body type contain several values, indexed by name.

| Function | Description | Page |
|--|---|--------------------|
| tibemsMapMsg_Create | Create a map message. | 91 |
| tibemsMapMsg_Get | Get an enumeration of the field names in a map message. | 92 |
| tibemsMapMsg_GetMapNames | Create a map message. | 96 |
| tibemsMapMsg_ItemExists | Test if a named pair exists. | 97 |
| tibemsMapMsg_Set | Set a name-value pair in a map message. | 98 |

- Extensions** TIBCO Enterprise Message Service extends the JMS `MapMessage` and `StreamMessage` body types in two ways. These extensions allow TIBCO Enterprise Message Service to exchange messages with TIBCO Rendezvous and TIBCO SmartSockets programs, which have certain features not available within the JMS specification.
- You can insert another `MapMessage` or `StreamMessage` instance as a submessage into a `MapMessage` or `StreamMessage`, generating a series of nested messages, instead of a flat message.
 - You can use arrays as well as primitive types for the values.

These extensions add considerable flexibility to the two body types. However, they are extensions and therefore not compliant with JMS specifications. Extended messages are tagged as extensions with the vendor property tag `JMS_TIBCO_MSG_EXT`.

For more information on message compatibility with Rendezvous messages, see [Message Body on page 455](#) in *TIBCO Enterprise Message Service Release Notes*.

tibemsMapMsg_Create

Function

Purpose Create a map message.

C Declaration `tibems_status tibemsMapMsg_Create(
tibemsMapMsg* message);`

COBOL Call `CALL "tibemsMapMsg_Create"
USING BY REFERENCE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |

Remarks This call creates a new map message.

When your application creates a message, it also allocates storage for that message. This storage must subsequently be freed by a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Create on page 29](#)
[tibemsMsg_Destroy on page 32](#)

tibemsMapMsg_Get

Function

Purpose Get data values from a map message.

C Declaration

```

tibems_status tibemsMapMsg_GetBoolean(
    tibemsMapMsg message,
    const char* name,
    tibems_bool* value );

tibems_status tibemsMapMsg_GetByte(
    tibemsMapMsg message,
    const char* name,
    tibems_byte* value );

tibems_status tibemsMapMsg_GetBytes(
    tibemsMapMsg message,
    const char* name,
    void** bytes,
    tibems_uint* bytesSize );

tibems_status tibemsMapMsg_GetChar(
    tibemsMapMsg message,
    const char* name,
    tibems_wchar* value );

tibems_status tibemsMapMsg_GetDouble(
    tibemsMapMsg message,
    const char* name,
    tibems_double* value );

tibems_status tibemsMapMsg_GetField(
    tibemsMapMsg message,
    const char* name,
    tibemsMsgField* value );

tibems_status tibemsMapMsg_GetFloat(
    tibemsMapMsg message,
    const char* name,
    tibems_float* value );

tibems_status tibemsMapMsg_GetInt(
    tibemsMapMsg message,
    const char* name,
    tibems_int* value );

tibems_status tibemsMapMsg_GetLong(
    tibemsMapMsg message,
    const char* name,
    tibems_long* value );

```

```

tibems_status tibemsMapMsg_GetMapMsg(
    tibemsMapMsg message,
    const char* name,
    tibemsMapMsg* value );

tibems_status tibemsMapMsg_GetShort(
    tibemsMapMsg message,
    const char* name,
    tibems_short* value );

tibems_status tibemsMapMsg_GetString(
    tibemsMapMsg message,
    const char* name,
    const char** value );

```

COBOL Call

```

CALL "tibemsMapMsg_GetBoolean"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetBytes"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE bytes,
          BY REFERENCE bytesSize,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetByte"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetChar"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetDouble"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

```

```

CALL "tibemsMapMsg_GetField"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetFloat"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetInt"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetLong"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetMapMsg"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetShort"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_GetString"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

```



message and bytes have usage pointer.

value has usage pointer only in `tibemsMapMsg_GetMapMsg` and `tibemsMapMsg_GetString` (but not in the other calls documented in this group).

Parameters

| Parameter | Description |
|-----------|---|
| message | Get a value from this map message. |
| name | Get the value associated with this name. |
| value | For unitary values, the function copies the value into this location. For strings, nested messages and fields, the function stores (in this location) a pointer to the value within the message. |
| bytes | <code>tibemsMapMsg_GetBytes</code> stores a pointer to the byte sequence in this location. |
| bytesSize | <code>tibemsMapMsg_GetBytes</code> stores the length of the byte sequence in this location. |

Remarks

The JMS specification defines these calls to extract data from the name-value pairs of a map message.

To get array values from a map message, call `tibemsMapMsg_GetField`, then extract the array value from the field; see [tibemsMsgField on page 135](#).

When the message does not have a field set for the name, these calls return [TIBEMS_NOT_FOUND](#).

tibemsMapMsg_GetMapNames

Function

Purpose Get an enumeration of the field names in a map message.

C Declaration `tibems_status tibemsMapMsg_GetMapNames(
tibemsMsg message,
tibemsMsgEnum* enumeration);`

COBOL Call CALL "tibemsMapMsg_GetMapNames"
USING BY VALUE message,
BY REFERENCE enumeration,
RETURNING tibems-status
END-CALL.



message and enumeration have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| message | Get the field names of this message. |
| enumeration | The function stores a pointer to the enumeration in this location. |

See Also [tibemsMsgEnum on page 132](#)

tibemsMapMsg_ItemExists

Function

Purpose Test if a named pair exists.

C Declaration `tibems_status tibemsMapMsg_ItemExists(
tibemsMapMsg message,
const char* name,
tibems_bool* exists);`

COBOL Call `CALL "tibemsMapMsg_ItemExists"
USING BY VALUE message,
BY REFERENCE name,
BY REFERENCE exists,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Test in the body of this map message. |
| name | Test for a pair with this name. |
| exists | The function stores the boolean result of the test in this location. |

tibemsMapMsg—Set

Function

Purpose Set a name-value pair in a map message.

Single Value `tibems_status` `tibemsMapMsg_SetBoolean(`
C Declarations `tibemsMapMsg` `message,`
`const char* name,`
`tibems_bool value);`

`tibems_status` `tibemsMapMsg_SetByte(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_byte value);`

`tibems_status` `tibemsMapMsg_SetChar(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_wchar value);`

`tibems_status` `tibemsMapMsg_SetDouble(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_double value);`

`tibems_status` `tibemsMapMsg_SetFloat(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_float value);`

`tibems_status` `tibemsMapMsg_SetInt(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_int value);`

`tibems_status` `tibemsMapMsg_SetLong(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_long value);`

`tibems_status` `tibemsMapMsg_SetShort(`
`tibemsMapMsg` `message,`
`const char* name,`
`tibems_short value);`

`tibems_status` `tibemsMapMsg_SetString(`
`tibemsMapMsg` `message,`
`const char* name,`
`const char* value);`

**Array
C Declarations**

```

tibems_status tibemsMapMsg_SetDoubleArray(
    tibemsMapMsg message,
    const char* name,
    const tibems_double* value,
    tibems_uint count );

tibems_status tibemsMapMsg_SetFloatArray(
    tibemsMapMsg message,
    const char* name,
    const tibems_float* value,
    tibems_uint count );

tibems_status tibemsMapMsg_SetIntArray(
    tibemsMapMsg message,
    const char* name,
    const tibems_int* value,
    tibems_uint count );

tibems_status tibemsMapMsg_SetLongArray(
    tibemsMapMsg message,
    const char* name,
    const tibems_long* value,
    tibems_uint count );

tibems_status tibemsMapMsg_SetShortArray(
    tibemsMapMsg message,
    const char* name,
    const tibems_short* value,
    tibems_uint count );

```

**Nested Message
C Declarations**

```

tibems_status tibemsMapMsg_SetMapMsg(
    tibemsMapMsg message,
    const char* name,
    tibemsMsg mapMsg,
    tibems_bool takeOwnership );

tibems_status tibemsMapMsg_SetStreamMsg(
    tibemsMsg message,
    const char* name,
    tibemsMsg streamMsg,
    tibems_bool takeOwnership);

```

COBOL Call

```

CALL "tibemsMapMsg_SetBoolean"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetByte"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

```

```
CALL "tibemsMapMsg_SetChar"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMapMsg_SetDouble"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMapMsg_SetDoubleArray"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMapMsg_SetFloat"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMapMsg_SetFloatArray"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMapMsg_SetInt"
    USING BY VALUE message,
          BY REFERENCE name,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.
```

```
CALL "tibemsMapMsg_SetIntArray"
    USING BY VALUE message,
          BY REFERENCE name,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.
```

```

CALL "tibemsMapMsg_SetLong"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetLongArray"
  USING BY VALUE message,
        BY REFERENCE name,
        BY REFERENCE value,
        BY VALUE count,
        RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetMapMsg"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE mapMsg,
        BY VALUE tibems-Boolean,
        RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetShort"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetShortArray"
  USING BY VALUE message,
        BY REFERENCE name,
        BY REFERENCE value,
        BY VALUE count,
        RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetStreamMsg"
  USING BY VALUE message,
        BY REFERENCE name,
        BY VALUE streamMsg,
        BY VALUE tibems-Boolean,
        RETURNING tibems-status
END-CALL.

CALL "tibemsMapMsg_SetString"
  USING BY VALUE message,
        BY REFERENCE name,
        BY REFERENCE value,
        RETURNING tibems-status
END-CALL.

```



message, streamMsg and mapMsg have usage pointer.

Parameters

| Parameter | Description |
|---------------|--|
| message | Set the pair in the body of this map message. |
| name | Set the pair with this name. Field names must not be null, and must not be empty strings. |
| value | Associate this value with the name. |
| count | Array functions set array values of this size (must be a positive number). |
| mapMsg | <code>tibemsMapMsg_SetMapMsg</code> sets this map message as a nested value. |
| takeOwnership | Nested message functions use this parameter to control ownership of nested messages. When this argument is <code>TIBEMS_TRUE</code> , the call increments the reference count of the nested message. This action prevents other calls from destroying the nested message improperly. We recommend that all calls supply <code>TIBEMS_TRUE</code> . |

Remarks The JMS specification defines functions to set name-value pairs in a `MapMessage`.

Extensions Array functions and nested message functions extend the JMS specification. Use them only with `SmartSockets` or `Rendezvous` messages. Programs that use these extensions might be non-compliant, and cannot interoperate with other JMS providers.

See Also [tibemsMapMsg_Get on page 92](#)
[tibemsMapMsg_SetBytes on page 103](#)

tibemsMapMsg_SetBytes

Function

Purpose Set a byte array as a named value in a map message.

C Declaration

```
tibems_status tibemsMapMsg_SetBytes(  
    tibemsMapMsg message,  
    const char* name,  
    void* bytes,  
    tibems_uint bytesSize );  
  
tibems_status tibemsMapMsg_SetReferencedBytes(  
    tibemsMapMsg message,  
    const char* name,  
    void* bytes,  
    tibems_uint bytesSize );
```

COBOL Call

```
CALL "tibemsMapMsg_SetBytes"  
  USING BY VALUE message,  
        BY REFERENCE name,  
        BY REFERENCE bytes,  
        BY VALUE bytesSize,  
        RETURNING tibems-status  
END-CALL.  
  
CALL "tibemsMapMsg_SetReferencedBytes"  
  USING BY VALUE message,  
        BY REFERENCE name,  
        BY REFERENCE bytes,  
        BY VALUE bytesSize,  
        RETURNING tibems-status  
END-CALL.
```



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Set the name and value pair in the body of this map message. |
| name | Set the pair with this name. |
| bytes | Associate this byte array value with the name. |
| bytesSize | Set a byte array value of this length. |

Remarks `tibemsMapMsg_SetBytes` copies the byte array into the map message field. The program may free the original byte array after this call returns.

`tibemsMapMsg_SetReferencedBytes` adds a reference to the byte array, but does not copy the bytes. When the byte array is very large, it can be more efficient to avoid making a copy. However, the program must not free nor modify the original byte array until after freeing the map message.

tibemsObjectMsg

Type

Purpose A message containing a serializable object.

Related Types [tibemsMsg on page 21](#)

| Function | Description | Page |
|--|--|------|
| tibemsObjectMsg_Create | Create an object message. | 106 |
| tibemsObjectMsg_GetObjectBytes | Get the byte sequence representing a serialized object from a message. | 107 |
| tibemsObjectMsg_SetObjectBytes | Set the byte sequence of an object message. | 108 |

Object Messages in C Object messages are used for objects created in .NET or Java. A C program can create, receive, and send object messages. For example, a C application can forward or store an object generated from a Java or .NET application.

C programs cannot create object messages. However, a C program can receive an object message from a Java or .NET program, and forward it, or store it for later resending.

Serialization The C library neither serializes objects nor reassembles them from bytes.

tibemsObjectMsg_Create

Function

Purpose Create an object message.

C Declaration `tibems_status tibemsObjectMsg_Create(
tibemsObjectMsg* message);`

COBOL Call CALL "tibemsObjectMsg_Create"
USING BY REFERENCE message,
RETURNING tibems-status
END-CALL.



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |

Remarks This call creates a new object message.

When your application creates a message, it also allocates storage for that message. This storage must subsequently be freed by a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Create on page 29](#)
[tibemsMsg_Destroy on page 32](#)

tibemsObjectMsg_GetObjectBytes

Function

Purpose Get the byte sequence representing a serialized object from a message.

C Declaration

```
tibems_status tibemsObjectMsg_GetObjectBytes(  
    tibemsObjectMsg message,  
    void** bytes,  
    tibems_uint* byteSize );
```

COBOL Call

```
CALL "tibemsObjectMsg_GetObjectBytes"  
    USING BY VALUE message,  
          BY REFERENCE bytes,  
          BY REFERENCE byteSize,  
          RETURNING tibems-status  
END-CALL.
```



message and bytes have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Get bytes (representing an object) from this message. |
| bytes | The function stores a pointer to the byte sequence (within the message) in this location. |
| byteSize | The function stores the length of the byte sequence in this location. |

Remarks When the message does not contain an object (because none has been set), this function places null in the bytes argument, and zero in the byteSize argument.

tibemsObjectMsg_SetObjectBytes

Function

Purpose Set the byte sequence of an object message.

C Declaration `tibems_status tibemsObjectMsg_SetObjectBytes(
tibemsObjectMsg message,
const void* bytes,
tibems_uint byteSize);`

COBOL Call CALL "tibemsObjectMsg_SetObjectBytes"
USING BY VALUE message,
BY REFERENCE bytes,
BY VALUE byteSize,
RETURNING tibems-status
END-CALL.



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Put bytes (representing an object) into this message. |
| bytes | Use these bytes (representing a serialized object) as the message body data. |
| byteSize | Length of the byte sequence. |

Remarks Setting the content of an object message stores a snapshot of the object. subsequent changes to the original object or its serialized representation (as a byte sequence) do not affect the message.

tibemsStreamMsg

Type

Purpose A message containing a stream of data items.

Related Types [tibemsMsg](#) on page 21

| Member | Description | Page |
|---|---|------|
| tibemsStreamMsg_Create | Create a stream message. | 111 |
| tibemsStreamMsg_FreeField | Free storage allocated during the reading of a stream message. | 112 |
| tibemsStreamMsg_Read | Read primitive datatypes from a stream message. | 113 |
| tibemsStreamMsg_ReadBytes | Read a byte array from a stream message. | 116 |
| tibemsStreamMsg_ReadField | Read a field from a stream message. | 117 |
| tibemsStreamMsg_Reset | Set the read position to the beginning of the stream, and mark the message body as read-only. | 118 |
| tibemsStreamMsg_Write | Write data to a stream message. | 119 |
| tibemsBytesMsg_WriteBytes | Write bytes from a byte array to a stream message. | 123 |

Remarks Each datum in the stream must be a primitive type, or an object representation of a primitive type.

Extensions TIBCO Enterprise Message Service extends the `MapMessage` and `StreamMessage` body types in two ways. These extensions allow TIBCO Enterprise Message Service to exchange messages with TIBCO Rendezvous and ActiveEnterprise formats that have certain features not available within the JMS specification.

- You can insert another `MapMessage` or `StreamMessage` instance as a submessage into a `MapMessage` or `StreamMessage`, generating a series of nested messages, instead of a flat message.
- You can use arrays as well as primitive types for the values.

These extensions add considerable flexibility to the two body types. However, they are extensions and therefore not compliant with JMS specifications. Extended messages are tagged as extensions with the vendor property tag `JMS_TIBCO_MSG_EXT`.

For more information on message compatibility with Rendezvous messages, see [Message Body on page 455](#) in *TIBCO Enterprise Message Service User's Guide*.

tibemsStreamMsg_Create

Function

Purpose Create a stream message.

C Declaration `tibems_status tibemsStreamMsg_Create(
tibemsStreamMsg* message);`

COBOL Call `CALL "tibemsStreamMsg_Create"
USING BY REFERENCE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |

Remarks This call creates a new stream message.

When your application creates a message, it also allocates storage for that message. This storage must subsequently be freed by a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Create on page 29](#)
[tibemsMsg_Destroy on page 32](#)

tibemsStreamMsg_FreeField

Function

Purpose Free storage allocated during the reading of a stream message.

C Declaration `void tibemsStreamMsg_FreeField(
tibemsMsgField* field);`

COBOL Call `CALL "tibemsStreamMsg_FreeField"
USING BY REFERENCE field
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | field | Free the storage associated with this field struct. |

Remarks Each successful call to `tibemsStreamMsg_ReadField` allocates storage for a `tibemsMsgField`. Programs that call `tibemsStreamMsg_ReadField` must subsequently call this function to free that allocated storage.

This function does not need to be called after `tibemsMapMsg_GetField`.

See Also [tibemsMsgField on page 135](#)
[tibemsStreamMsg_ReadField on page 117](#)

tibemsStreamMsg_Read

Function

Purpose Read primitive datatypes from a stream message.

C Declaration

```

tibems_status tibemsStreamMsg_ReadBoolean(
    tibemsStreamMsg message,
    tibems_bool* value );

tibems_status tibemsStreamMsg_ReadByte(
    tibemsStreamMsg message,
    tibems_byte* value );

tibems_status tibemsStreamMsg_ReadChar(
    tibemsStreamMsg message,
    tibems_wchar* value );

tibems_status tibemsStreamMsg_ReadDouble(
    tibemsStreamMsg message,
    tibems_double* value );

tibems_status tibemsStreamMsg_ReadFloat(
    tibemsStreamMsg message,
    tibems_float* value );

tibems_status tibemsStreamMsg_ReadInt(
    tibemsStreamMsg message,
    tibems_int* value );

tibems_status tibemsStreamMsg_ReadLong(
    tibemsStreamMsg message,
    tibems_long* value );

tibems_status tibemsStreamMsg_ReadShort(
    tibemsStreamMsg message,
    tibems_short* value );

tibems_status tibemsStreamMsg_ReadString(
    tibemsStreamMsg message,
    char** value );

```

COBOL Call

```

CALL "tibemsStreamMsg_ReadBoolean"
  USING BY VALUE message,
        BY REFERENCE value,
        RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadByte"
  USING BY VALUE message,
        BY REFERENCE value,
        RETURNING tibems-status
END-CALL.

```

```
CALL "tibemsStreamMsg_ReadChar"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadDouble"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadFloat"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadInt"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadLong"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadShort"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_ReadString"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.
```



message has usage pointer.

value has usage pointer only in tibemsStreamMsg_ReadString (but not in the other calls documented in this group).

Parameters

| Parameter | Description |
|-----------|---|
| message | Read a field struct from this message. |
| value | The function stores a pointer to the field struct in this location. |

Remarks Each call reads a unit of data from the stream, and advances the read position so that the next read call gets the next datum. (Other read functions are documented on separate pages.)

See Also [tibemsStreamMsg_ReadBytes on page 116](#)
[tibemsStreamMsg_ReadField on page 117](#)

tibemsStreamMsg_ReadBytes

Function

Purpose Read a byte array from a stream message.

C Declaration `tibems_status tibemsStreamMsg_ReadBytes(
tibemsStreamMsg message,
void** value,
tibems_uint* length);`

COBOL Call `CALL "tibemsStreamMsg_ReadBytes"
USING BY VALUE message,
BY REFERENCE value,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`



message and value have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Read a byte array from this message. |
| value | The function stores a pointer to the byte sequence (within the message) in this location. |
| length | The function stores the actual number of bytes read in this location. |

Remarks Each call reads bytes from the stream into the byte array, and advances the read position so that the next read call gets the next datum. (Other read functions are documented on separate pages.)

This call uses the length parameter to return the actual number of bytes read. When the call cannot read even one byte, the length is -1.

A program that calls this function must call it repeatedly until it returns -1, indicating that the program has extracted the complete set of bytes. Only then may the program call another read function.

See Also [tibemsStreamMsg_Read on page 113](#)
[tibemsStreamMsg_ReadField on page 117](#)

tibemsStreamMsg_ReadField

Function

Purpose Read a field from a stream message.

C Declaration `tibems_status tibemsStreamMsg_ReadField(
tibemsStreamMsg message,
tibemsMsgField* value);`

COBOL Call `CALL "tibemsStreamMsg_ReadField"
USING BY VALUE message,
BY REFERENCE value,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Read a field struct from this message. |
| value | The function stores a pointer to the field struct in this location. |

Remarks Each call reads a field from the stream, and advances the read position so that the next read call gets the next datum. (Other read functions are documented on separate pages.)

Freeing Fields Each successful call to `tibemsStreamMsg_ReadField` creates a field struct. Field structs can contain data in allocated storage. Programs that call `tibemsStreamMsg_ReadField` *must* subsequently call `tibemsStreamMsg_FreeField` to free that allocated storage.

See Also [tibemsStreamMsg_FreeField on page 112](#)

tibemsStreamMsg_Reset

Function

Purpose Set the read position to the beginning of the stream, and mark the message body as read-only.

C Declaration `tibems_status tibemsStreamMsg_Reset(
tibemsStreamMsg message);`

COBOL Call `CALL "tibemsStreamMsg_Reset"
USING BY VALUE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Reset the read position of this message. |

Remarks This call prepares a message body for reading, as if the message were newly received. Contrast [tibemsMsg_ClearBody on page 27](#), which clears a message body in preparation for writing, as if it were newly created.

tibemsStreamMsg_Write

Function

| | |
|--|--|
| Purpose | Write data to a stream message. |
| Single Value C Declarations | <pre> tibems_status tibemsStreamMsg_WriteBoolean(tibemsStreamMsg message, tibems_bool value); tibems_status tibemsStreamMsg_WriteByte(tibemsStreamMsg message, tibems_byte value); tibems_status tibemsStreamMsg_WriteChar(tibemsStreamMsg message, tibems_wchar value); tibems_status tibemsStreamMsg_WriteDouble(tibemsStreamMsg message, tibems_double value); tibems_status tibemsStreamMsg_WriteFloat(tibemsStreamMsg message, tibems_float value); tibems_status tibemsStreamMsg_WriteInt(tibemsStreamMsg message, tibems_int value); tibems_status tibemsStreamMsg_WriteLong(tibemsStreamMsg message, tibems_long value); tibems_status tibemsStreamMsg_WriteShort(tibemsStreamMsg message, tibems_short value); tibems_status tibemsStreamMsg_WriteString(tibemsStreamMsg message, char* value); </pre> |
| Array C Declarations | <pre> tibems_status tibemsStreamMsg_WriteDoubleArray(tibemsMsg message, const tibems_double* value, tibems_int count); tibems_status tibemsStreamMsg_WriteFloatArray(tibemsMsg message, const tibems_float* value, tibems_int count); tibems_status tibemsStreamMsg_WriteIntArray(tibemsMsg message, const tibems_int* value, tibems_int count); </pre> |

```

tibems_status tibemsStreamMsg_WriteLongArray(
    tibemsMsg message,
    const tibems_long* value,
    tibems_int count );

tibems_status tibemsStreamMsg_WriteShortArray(
    tibemsMsg message,
    const tibems_short* value,
    tibems_int count );

```

Nested Message C Declarations

```

tibems_status tibemsStreamMsg_WriteMapMsg(
    tibemsMsg message,
    tibemsMsg value );

tibems_status tibemsStreamMsg_WriteStreamMsg(
    tibemsMsg message,
    tibemsMsg value );

```



Nested messages are an extension of the JMS specification. Programs that use this feature are non-compliant.

COBOL Call

```

CALL "tibemsStreamMsg_WriteBoolean"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteByte"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteChar"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteDouble"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteDoubleArray"
    USING BY VALUE message,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.

```

```

CALL "tibemsStreamMsg_WriteFloat"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteFloatArray"
    USING BY VALUE message,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteInt"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteIntArray"
    USING BY VALUE message,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteLong"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteLongArray"
    USING BY VALUE message,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteMapMsg"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteShort"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteShortArray"
    USING BY VALUE message,
          BY REFERENCE value,
          BY VALUE count,
          RETURNING tibems-status
END-CALL.

```

```
CALL "tibemsStreamMsg_WriteStreamMsg"
    USING BY VALUE message,
          BY VALUE value,
          RETURNING tibems-status
END-CALL.

CALL "tibemsStreamMsg_WriteString"
    USING BY VALUE message,
          BY REFERENCE value,
          RETURNING tibems-status
END-CALL.
```



message has usage pointer.

value has usage pointer only in `tibemsStreamMsg_WriteStreamMsg` and `tibemsStreamMsg_WriteMapMsg` (but not in the other calls documented in this group).

Parameters

| Parameter | Description |
|-----------|--|
| message | Write a datum to this stream message. |
| value | Write this datum. Arrays must not be null. |
| count | Array functions set array values of this size. |

Remarks Each call writes a data value to the stream, and advances the write position so that the next write call appends to the new end of the stream.

See Also [tibemsStreamMsg_WriteBytes](#) on page 123

tibemsStreamMsg_WriteBytes

Function

Purpose Write bytes from a byte array to a stream message.

C Declaration `tibems_status tibemsStreamMsg_WriteBytes(
tibemsStreamMsg message,
void* value,
tibems_uint length);`

COBOL Call `CALL "tibemsStreamMsg_WriteBytes"
USING BY VALUE message,
BY REFERENCE value,
BY VALUE length,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Write to the byte stream of this message. |
| value | Copy bytes from this byte array to the message. |
| length | Write this number of bytes from the byte array to the message. |

Remarks Each call writes bytes from the byte array into the stream, and advances the write position.

tibemsTextMsg

Type

- Purpose** A message containing a text string.
- Related Types** [tibemsMsg on page 21](#)
- Remarks** Messages with this body type contain a single value, which is a string.

| Function | Description | Page |
|---------------------------------------|--|------|
| tibemsTextMsg_Create | Create a text message. | 125 |
| tibemsTextMsg_GetText | Get the string data from a text message. | 126 |
| tibemsTextMsg_SetText | Set the data string of a text message. | 127 |

tibemsTextMsg_Create

Function

Purpose Create a text message.

C Declaration `tibems_status tibemsTextMsg_Create(
tibemsTextMsg* message);`

COBOL Call `CALL "tibemsTextMsg_Create"
USING BY REFERENCE message,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | The function stores a pointer to the new message in this location. |

Remarks This call creates a new text message.

When your application creates a message, it also allocates storage for that message. This storage must subsequently be freed by a call to `tibemsMsg_Destroy`.

See Also [tibemsMsg_Create on page 29](#)
[tibemsMsg_Destroy on page 32](#)

See Also [tibemsSession_CreateTextMessage on page 316](#)

tibemsTextMsg_GetText

Function

Purpose Get the string data from a text message.

C Declaration `tibems_status tibemsTextMsg_GetText(
tibemsTextMsg message,
const char** text);`

COBOL Call `CALL "tibemsTextMsg_GetText"
USING BY VALUE message,
BY REFERENCE text,
RETURNING tibems-status
END-CALL.`



message and text have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| message | Get the string from this message. |
| text | The function stores a pointer to the string (within the message) in this location. |

Remarks When the message does not contain any text (because none has been set), this function sets its text parameter to null.

tibemsTextMsg_SetText

Function

Purpose Set the data string of a text message.

C Declaration `tibems_status tibemsTextMsg_SetText(
tibemsTextMsg message,
const char* text);`

COBOL Call `CALL "tibemsTextMsg_SetText"
USING BY VALUE message,
BY REFERENCE text,
RETURNING tibems-status
END-CALL.`



message has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| message | Put the text into this message. |
| text | Copy this string into the message body. |

tibemsData

Type

Purpose Union type that covers all possible datatypes in a [tibemsMsgField](#) struct.

C Declaration

```
typedef union {
    tibems_bool boolValue;
    tibems_byte byteValue;
    tibems_short shortValue;
    tibems_wchar wcharValue;
    tibems_int intValue;
    tibems_long longValue;
    tibems_float floatValue;
    tibems_double doubleValue;
    char* utf8Value;
    void* bytesValue;
    struct __tibemsMsg* msgValue;
    void* arrayValue;
} tibemsData;
```

COBOL

```
05  MsgFld-data.
10  MFD                                PIC  X(8).
10  MFD-boolValue                      PIC  S9(8) BINARY.
    redefines MFD
10  MFD-byteValue                      PIC  X(1) USAGE DISPLAY.
    redefines MFD
10  MFD-shortValue                     PIC  S9(4) BINARY.
    redefines MFD
10  MFD-wcharValue                     PIC  9(4) COMPUTATIONAL-5.
    redefines MFD
10  MFD-intValue                       PIC  S9(9) BINARY.
    redefines MFD
10  MFD-longValue                      PIC  S9(18) COMPUTATIONAL-5.
    redefines MFD
10  MFD-floatValue                     USAGE  COMPUTATIONAL-1.
    redefines MFD
10  MFD-doubleValue                    USAGE  COMPUTATIONAL-2.
    redefines MFD
10  MFD-utf8Value                      USAGE  POINTER.
    redefines MFD
10  MFD-bytesValue                     USAGE  POINTER.
    redefines MFD
10  MFD-msgValue                       USAGE  POINTER.
    redefines MFD
10  MFD-arrayValue                     USAGE  POINTER.
    redefines MFD
```

See Also [tibemsMsgField on page 135](#)

tibemsDeliveryMode

Type

Purpose Define delivery mode constants.

C Declaration

```
typedef enum {
    TIBEMS_NON_PERSISTENT,
    TIBEMS_PERSISTENT,
    TIBEMS_RELIABLE
} tibemsDeliveryMode;
```

COBOL

```
01  TIBEMS-DELIVERY-MODES.
   05  tibemsDeliveryMode      PIC S9(8) BINARY.
      88  TIBEMS-NON-PERSISTENT VALUE 1.
      88  TIBEMS-PERSISTENT    VALUE 2.
      88  TIBEMS-RELIABLE      VALUE 22.
```

| Member | Description |
|-----------------------|---|
| TIBEMS_NON_PERSISTENT | Non-persistent delivery. |
| TIBEMS_PERSISTENT | Persistent delivery. |
| TIBEMS_RELIABLE | Reliable delivery mode is a TIBCO proprietary extension that offers increased performance of the message producers. See also RELIABLE_DELIVERY on page 27 in <i>TIBCO Enterprise Message Service User's Guide</i> . |

tibemsNpCheckMode

Type

Purpose Define when a producer should check the result of sending a NON_PERSISTENT message.

C Declaration

```
typedef enum
{
    NPSEND_CHECK_DEFAULT      = 0,
    NPSEND_CHECK_ALWAYS      = 1,
    NPSEND_CHECK_NEVER        = 2,
    NPSEND_CHECK_TEMP_DEST    = 3,
    NPSEND_CHECK_AUTH         = 4,
    NPSEND_CHECK_TEMP_AUTH    = 5
} tibemsNpCheckMode;
```

COBOL

```
01  TIBEMS-NPCHECK-MODES .
05  tibemsNpCheckMode      PIC S9(8) BINARY.
88  NPSEND_CHECK_DEFAULT   VALUE 0.
88  NPSEND_CHECK_ALWAYS    VALUE 1.
88  NPSEND_CHECK_NEVER     VALUE 2.
88  NPSEND_CHECK_TEMP_DEST VALUE 3.
88  NPSEND_CHECK_AUTH      VALUE 4.
88  NPSEND_CHECK_TEMP_AUTH VALUE 5.
```

| Member | Description |
|------------------------|---|
| NPSEND_CHECK_DEFAULT | Defines default check mode for sending a NON_PERSISTENT message. |
| NPSEND_CHECK_ALWAYS | Defines mode when producer always checks result of sending a NON_PERSISTENT message. |
| NPSEND_CHECK_NEVER | Defines mode when producer never checks result of sending a NON_PERSISTENT message. |
| NPSEND_CHECK_TEMP_DEST | Defines mode when producer checks result of sending a NON_PERSISTENT message only when sending into temporary destination. |
| NPSEND_CHECK_AUTH | Defines mode when producer checks result of sending a NON_PERSISTENT message only when server authorization is enabled. |
| NPSEND_CHECK_TEMP_AUTH | Defines mode when producer checks result of sending a NON_PERSISTENT message when sending into temporary destination or if server authorization is enabled. |

tibemsMsgCompletionCallback

Type

Purpose Asynchronously process a message after sending. This is equivalent to a completion listener in the Java and .NET API.

C Declaration

```
typedef void (*tibemsMsgCompletionCallback) (
    tibemsMsg msg,
    tibems_status status,
    void* closure );
```

Parameters

| Parameter | Description |
|-----------|---|
| msg | This parameter receives the message object. |
| status | This parameter receives the status of the associated send call. |
| closure | This parameter receives the closure argument, which your program registered in the call to the asynchronous send. |

Remarks To asynchronously send messages, your program can define callback functions of this type, and register them when sending asynchronously (using [tibemsMsgProducer_AsyncSend](#) or a related function).

If the send of the message was successful, the status parameter is TIBEMS_OK. If the send is not successful, the status is an error code indicating the type of failure that occurred.

See Also [tibemsMsgProducer on page 176](#)

The section on Sending Asynchronously in the *TIBCO Enterprise Message Service User's Guide*.

tibemsMsgEnum

Type

- Purpose**Enumerate the properties of a message, or the field names of a map message.
- Remarks**[tibemsMsg_GetPropertyNames](#) and [tibemsMapMsg_GetMapNames](#) create instances of this type.

| Function | Description | Page |
|---|--|------|
| tibemsMsgEnum_Destroy | Destroy a message enumerator. | 133 |
| tibemsMsgEnum_GetNextName | Get the next item from a message enumerator. | 134 |

- See Also**[tibemsMsg_GetPropertyNames](#) on page 50
- [tibemsMapMsg_GetMapNames](#) on page 96

tibemsMsgEnum_Destroy

Function

Purpose Destroy a message enumerator.

C Declaration `tibems_status tibemsMsgEnum_Destroy(
tibemsMsgEnum enumeration);`

COBOL Call `CALL "tibemsMsgEnum_Destroy"
USING BY VALUE enumeration,
RETURNING tibems-status
END-CALL.`



enumeration has usage pointer.

Parameters

| Parameter | Description |
|-------------|--------------------------|
| enumeration | Destroy this enumerator. |

tibemsMsgEnum_GetNextName

Function

Purpose Get the next item from a message enumerator.

C Declaration `tibems_status tibemsMsgEnum_GetNextName(
tibemsMsgEnum enumeration,
const char** name);`

COBOL Call `CALL "tibemsMsgEnum_GetNextName"
USING BY VALUE enumeration,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`



enumeration and name have usage pointer.

Parameters

| Parameter | Description |
|-------------|---|
| enumeration | Get the next item from this enumerator. |
| name | The function stores the next item in this location. |

tibemsMsgField

Type

Purpose Represents a message field or property.

C Declaration

```
typedef struct {
    tibems_byte type;
    tibems_int size;
    tibems_int count;
    tibemsData data;
} tibemsMsgField
```

COBOL

```
01 tibemsMsgField.
  05 MsgFld-type PIC X(1).
    88 TIBEMS-NULL VALUE X'00'.
    88 TIBEMS-BOOL VALUE X'01'.
    88 TIBEMS-BYTE VALUE X'02'.
    88 TIBEMS-WCHAR VALUE X'03'.
    88 TIBEMS-SHORT VALUE X'04'.
    88 TIBEMS-INT VALUE X'05'.
    88 TIBEMS-LONG VALUE X'06'.
    88 TIBEMS-FLOAT VALUE X'07'.
    88 TIBEMS-DOUBLE VALUE X'08'.
    88 TIBEMS-UTF8 VALUE X'09'.
    88 TIBEMS-BYTES VALUE X'0A'.
    88 TIBEMS-MAP-MSG VALUE X'0B'.
    88 TIBEMS-STREAM-MSG VALUE X'0C'.
    88 TIBEMS-SHORT-ARRAY VALUE X'14'.
    88 TIBEMS-INT-ARRAY VALUE X'15'.
    88 TIBEMS-LONG-ARRAY VALUE X'16'.
    88 TIBEMS-FLOAT-ARRAY VALUE X'17'.
    88 TIBEMS-DOUBLE-ARRAY VALUE X'18'.
  05 Filler PIC X(3).
  05 MsgFld-size PIC S9(9) BINARY.
  05 MsgFld-count PIC S9(9) BINARY.
  05 Filler PIC X(4).
  05 MsgFld-data.
    10 MFD PIC X(8).
```

Remarks Any message can have property values. Only map messages and stream messages can have fields.

| Field | Description |
|-------|--|
| type | A one-byte indicator of the field's datatype; for values, see Table 10 below. |
| size | The size of the data (in bytes). Zero is a special value, indicating that the size is unknown. |
| count | If the data is an array, this value is the number of elements in the array. |

| Field | Description |
|-------|--|
| data | The actual data in the field, or the property value. |

Table 10 Message Field Type Indicators

| Constant | Value | Comment |
|---------------------|-------|-------------------------|
| TIBEMS_NULL | 0 | |
| TIBEMS_BOOL | 1 | |
| TIBEMS_BYTE | 2 | |
| TIBEMS_WCHAR | 3 | wide character; 2 bytes |
| TIBEMS_SHORT | 4 | |
| TIBEMS_INT | 5 | |
| TIBEMS_LONG | 6 | |
| TIBEMS_FLOAT | 7 | |
| TIBEMS_DOUBLE | 8 | |
| TIBEMS_UTF8 | 9 | UTF8-encoded string |
| TIBEMS_BYTES | 10 | |
| TIBEMS_MAP_MSG | 11 | |
| TIBEMS_STREAM_MSG | 12 | |
| TIBEMS_SHORT_ARRAY | 20 | |
| TIBEMS_INT_ARRAY | 21 | |
| TIBEMS_LONG_ARRAY | 22 | |
| TIBEMS_FLOAT_ARRAY | 23 | |
| TIBEMS_DOUBLE_ARRAY | 24 | |

See Also [tibemsMsg_GetProperty](#), listed at [tibemsMsg_Get Property on page 47](#)
 [tibemsMapMsg_GetField](#), listed at [tibemsMapMsg_Get on page 92](#)
 [tibemsStreamMsg_FreeField](#) on page 112
 [tibemsStreamMsg_ReadField](#) on page 117
 [tibemsMsgEnum_GetNextName](#) on page 134

tibemsMsgField_Print

Function

Purpose Print a message field.

C Declaration `void tibemsMsgField_Print(
tibemsMsgField* field);`

COBOL Call `CALL "tibemsMsgField_Print"
USING BY REFERENCE field,
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|------------------------------------|
| | field | Print this message field instance. |

Remarks tibemsMsgField_Print prints to stdout in the format *FieldDataType:Value*.

tibemsMsgField_PrintToBuffer

Function

Purpose Print a message field into a buffer.

C Declaration `tibems_status tibemsMsgField_PrintToBuffer(
tibemsMsgField* field,
char* buffer,
tibems_int maxlen);`

COBOL Call `CALL "tibemsMsgField_PrintToBuffer"
USING BY REFERENCE field,
BY REFERENCE buffer,
BY VALUE maxlen,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | field | Print this message field instance. |
| | buffer | Location to store the string representation of the message. |
| | maxlen | The size of the buffer. |

Remarks tibemsMsgField_PrintToBuffer prints to a buffer, in the format *FieldDataType: Value*.

| Status Code | Description |
|----------------------------|---|
| TIBEMS_INSUFFICIENT_BUFFER | The buffer is too small to hold the data. |

tibemsMsgType

Purpose Enumerated constants representing message body types.

C Declaration

```
typedef enum {
    TIBEMS_MESSAGE_UNKNOWN,
    TIBEMS_MESSAGE,
    TIBEMS_BYTES_MESSAGE,
    TIBEMS_MAP_MESSAGE,
    TIBEMS_OBJECT_MESSAGE,
    TIBEMS_STREAM_MESSAGE,
    TIBEMS_TEXT_MESSAGE,
    TIBEMS_MESSAGE_UNDEFINED
} tibemsMsgType;
```

COBOL

```
01  TIBEMS-MSG-TYPES.
    05  tibemsMsgType          PIC S9(8) BINARY.
        88  TIBEMS-MESSAGE-UNKNOWN    VALUE 0.
        88  TIBEMS-MESSAGE             VALUE 1.
        88  TIBEMS-BYTES-MESSAGE       VALUE 2.
        88  TIBEMS-MAP-MESSAGE         VALUE 3.
        88  TIBEMS-OBJECT-MESSAGE      VALUE 4.
        88  TIBEMS-STREAM-MESSAGE      VALUE 5.
        88  TIBEMS-TEXT-MESSAGE        VALUE 6.
        88  TIBEMS-MESSAGE-UNDEFINED  VALUE 256.
```

See Also [tibemsMsg_GetBodyType on page 36](#)

Chapter 3 **Destination**

This chapter documents the functions that create and modify destination objects. The destination of a message determines where the message is sent.

Topics

- [Destination Overview, page 142](#)
- [tibemsDestination, page 146](#)
- [tibemsQueue, page 152](#)
- [tibemsTemporaryQueue, page 156](#)
- [tibemsTemporaryTopic, page 157](#)
- [tibemsTopic, page 158](#)

Destination Overview

Destination objects represent destinations within the EMS server—the queues and topics to which programs send messages, and from which they receive messages. Queues deliver each message to exactly one consumer. Topics deliver each message to every subscriber. Queues and topics can be static, dynamic or temporary.

Table 11 Destination Overview

| Aspect | Static | Dynamic | Temporary |
|-------------------|---|---|---|
| Purpose | Static destinations let administrators configure EMS behavior at the enterprise level. Administrators define these administered objects, and client programs use them—relieving program developers and end users of the responsibility for correct configuration. | Dynamic destinations give client programs the flexibility to define destinations as needed for short-term use. | Temporary destinations are ideal for limited-scope uses, such as reply subjects. |
| Scope of Delivery | Static destinations support concurrent use. That is, several client processes (and in several threads within a process) can create local objects denoting the destination, and consume messages from it. | Dynamic destinations support concurrent use. That is, several client processes (and in several threads within a process) can create local objects denoting the destination, and consume messages from it. | Temporary destinations support only local use. That is, only the client connection that created a temporary destination can consume messages from it. However, servers connected by routes do exchange messages sent to temporary topics. |

Table 11 Destination Overview

| Aspect | Static | Dynamic | Temporary |
|----------|--|--|--|
| Creation | Administrators create static destinations using EMS server administration tools or API. | <p>If the server configuration permits dynamic destinations, client programs can create one in two steps:</p> <ol style="list-style-type: none"> 1. Create a local destination object; see tibemsSession on page 294. 2. Send a message to that destination, or create a consumer for it. Either of these actions automatically creates the destination in the server. | Client programs create temporary destinations; see tibemsSession on page 294 . |
| Lookup | Client programs lookup static destinations by name. Successful lookup returns a local object representation of the destination; see tibemsLookupContext_Lookup on page 339 . | Not applicable. | Not applicable. |

Table 11 Destination Overview

| Aspect | Static | Dynamic | Temporary |
|----------|--|---|---|
| Duration | A static destination remains in the server until an administrator explicitly deletes it. | <p>A dynamic destination remains in the server as long as at least one client actively uses it. The server automatically deletes it (at a convenient time) when all applicable conditions are true:</p> <ul style="list-style-type: none">• Topic or Queue all client programs that access the destination have disconnected• Topic no offline durable subscribers exist for the topic• Queue queue, no messages are stored in the queue | A temporary destination remains in the server either until the client that created it explicitly deletes it, or until the client disconnects from the server. |

tibemsDestinationType

Type

Purpose Enumerated constants representing destination types.

C Declaration

```
typedef enum {
    TIBEMS_UNKNOWN,
    TIBEMS_QUEUE,
    TIBEMS_TOPIC
} tibemsDestinationType;
```

COBOL

| | | | |
|----|---------------------------|-------------------|------|
| 01 | TIBEMS-DESTINATION-TYPES. | | |
| 05 | tibemsDestinationType | PIC S9(8) BINARY. | |
| 88 | TIBEMS-UNKNOWN | VALUE | 0. |
| 88 | TIBEMS-QUEUE | VALUE | 1. |
| 88 | TIBEMS-TOPIC | VALUE | 2. |
| 88 | TIBEMS-UNDEFINED | VALUE | 256. |

See Also [tibemsDestination_Create on page 148](#)
[tibemsDestination_GetType on page 151](#)

tibemsDestination

Type

- Purpose**Represent a named queue or topic in the server.
- Remarks**Administrators define destinations in the server. Client programs access them using functions of [tibemsLookupContext](#).

| Function | Description | Page |
|---|---|------|
| tibemsDestination_Copy | Create an independent copy of a destination object. | 147 |
| tibemsDestination_Create | Create a destination object. | 148 |
| tibemsDestination_Destroy | Destroy a destination object. | 149 |
| tibemsDestination_GetName | Get the name of a destination object. | 150 |
| tibemsDestination_GetType | Get the type of a destination object. | 151 |

- Related Types**

[tibemsQueue](#) on page 152

[tibemsTemporaryQueue](#) on page 156

[tibemsTopic](#) on page 158

[tibemsTemporaryTopic](#) on page 157
- See Also**

[tibemsMsg_GetDestination](#) on page 42

[tibemsMsg_SetDestination](#) on page 63

[tibemsLookupContext](#) on page 334

tibemsDestination_Copy

Function

Purpose Create an independent copy of a destination object.

C Declaration `tibems_status tibemsDestination_Copy(
tibemsDestination destination,
tibemsDestination* copy);`

COBOL Call `CALL "tibemsDestination_Copy"
USING BY VALUE destination,
BY REFERENCE copy,
RETURNING tibems-status
END-CALL.`



destination has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| destination | Copy this existing destination object. |
| copy | The function stores the new copy in this location. |

tibemsDestination_Create

Function

Purpose Create a destination object.

C Declaration `tibems_status tibemsDestination_Create(
tibemsDestination* destination,
tibemsDestinationType type,
const char* name);`

COBOL Call `CALL "tibemsDestination_Create"
USING BY REFERENCE destination,
BY VALUE type,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`



destination has usage pointer.

Parameters

| Parameter | Description |
|-------------|---|
| destination | The function stores the new destination in this location. |
| type | Create a destination of this type (queue or topic). |
| name | Create a destination with this name. |

See Also [tibemsDestinationType on page 145](#)

tibemsDestination_Destroy

Function

Purpose Destroy a destination object.

C Declaration `tibems_status tibemsDestination_Destroy(
tibemsDestination destination);`

COBOL Call `CALL "tibemsDestination_Destroy"
USING BY VALUE destination,
RETURNING tibems-status
END-CALL.`



destination has usage pointer.

Parameters

| Parameter | Description |
|-------------|---------------------------|
| destination | Destroy this destination. |

tibemsDestination_GetName

Function

Purpose Get the name of a destination object.

C Declaration `tibems_status tibemsDestination_GetName(
tibemsDestination destination,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsDestination_GetName"
USING BY VALUE destination,
BY REFERENCE name,
BY VALUE name-len
RETURNING tibems-status
END-CALL.`



destination has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| destination | Get the name of this destination. |
| name | The function copies the name to this location. |
| name_len | Length of the name buffer. |

Remarks A null character terminates the copied name string.
Your program must allocate the name buffer, and pass its length to the function. If the length of the name is greater than the size of the buffer provided, the entire destination name may not be copied. The buffer size is determined by the TIBEMS_DESTINATION_MAX constant. Constants such as TIBEMS_DESTINATION_MAX are located in the tibems/types.h header file.

tibemsDestination_GetType

Function

Purpose Get the type of a destination object.

C Declaration `tibems_status tibemsDestination_GetType(
tibemsDestination destination,
tibemsDestinationType* type);`

COBOL Call `CALL "tibemsDestination_GetType"
USING BY VALUE destination,
BY REFERENCE type,
RETURNING tibems-status
END-CALL.`



destination has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| destination | Get the type of this destination. |
| type | The function stores the type in this location. |

See Also [tibemsDestinationType on page 145](#)

tibemsQueue

Type

Purpose Queues deliver each message to exactly one consumer.

| Function | Description | Page |
|--|---------------------------------|------|
| tibemsQueue_Create | Create a queue object. | 153 |
| tibemsQueue_Destroy | Destroy a queue object. | 154 |
| tibemsQueue_GetQueueName | Get the name of a queue object. | 155 |

Related Types [tibemsDestination](#) on page 146
 [tibemsTemporaryQueue](#) on page 156

tibemsQueue_Create

Function

Purpose Create a queue object.

C Declaration `tibems_status tibemsQueue_Create(
tibemsQueue* queue,
const char* queueName);`

COBOL Call `CALL "tibemsQueue_Create"
USING BY REFERENCE queue,
BY REFERENCE queueName,
RETURNING tibems-status
END-CALL.`



queue has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| queue | The function stores the queue object in this location. |
| queueName | Create a local queue instance with this name. |

Remarks

This call creates only local objects (within the program). It does not attempt to bind the local queue object to the corresponding server object until the program creates a [tibemsMsgConsumer](#) or a [tibemsMsgProducer](#) that uses the queue.

The bind can fail for the following reasons:

- Authorization is enabled for the queue and the user does not have the appropriate permissions.
- The queue does not exist and the server cannot dynamically create the queue.

See Also

[tibemsLookupContext](#) on page 334

tibemsQueue_Destroy

Function

Purpose Destroy a queue object.

C Declaration `tibems_status tibemsQueue_Destroy(
tibemsQueue queue);`

COBOL Call `CALL "tibemsQueue_Destroy"
USING BY VALUE queue,
RETURNING tibems-status
END-CALL.`



queue has usage pointer.

Parameters

| Parameter | Description |
|-----------|---------------------|
| queue | Destroy this queue. |

tibemsQueue_GetQueueName

Function

Purpose Get the name of a queue object.

C Declaration `tibems_status tibemsQueue_GetQueueName(
tibemsQueue queue,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsQueue_GetQueueName"
USING BY VALUE queue,
BY REFERENCE name,
BY VALUE name-len
RETURNING tibems-status
END-CALL.`



queue has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| queue | Get the name of this queue. |
| name | The function copies the name to this location. |
| name_len | Length of the name buffer. |

Remarks A null character terminates the copied name string.
Your program must allocate the name buffer, and pass its length to the function. If the length of the queue name is greater than the size of the buffer provided, the entire queue name may not be copied. The buffer size is determined by the TIBEMS_DESTINATION_MAX constant. Constants such as TIBEMS_DESTINATION_MAX are located in the `tibems/types.h` header file.

tibemsTemporaryQueue

Type

- Purpose** Programs can use temporary queues as reply destinations.
- Remarks** Programs create temporary queues using [tibemsSession_CreateTemporaryQueue](#).

A temporary queue exists only for the duration of the session’s connection, and is available only within that connection.

Only consumers associated with the same connection as the temporary queue can consume messages from it.

All functions that accept a queue or a generic destination as an argument also accept a temporary queue.

| Function | Description | Page |
|--|---------------------------|------|
| tibemsSession_CreateTemporaryQueue | Create a temporary queue. | 314 |
| tibemsSession_DeleteTemporaryQueue | Delete a temporary queue. | 317 |

Related Types [tibemsDestination](#) on page 146
[tibemsQueue](#) on page 152

tibemsTemporaryTopic

Type

- Purpose** Programs can use temporary topics as reply destinations.
- Remarks** Programs create temporary topics using [tibemsSession_CreateTemporaryTopic](#).

A temporary topic exists only for the duration of the session’s connection, and is available only within that connection.

Only consumers associated with the same connection as the temporary topic can consume messages from it.

Servers connected by routes do exchange messages sent to temporary topics.

All functions that accept a topic or a generic destination as an argument also accept a temporary queue.

| Function | Description | Page |
|--|---------------------------|------|
| tibemsSession_CreateTemporaryTopic | Create a temporary topic. | 315 |
| tibemsSession_DeleteTemporaryTopic | Delete a temporary topic. | 318 |

- Related Types** [tibemsDestination](#) on page 146
[tibemsTopic](#) on page 158

tibemsTopic

Type

Purpose Topics deliver each message to multiple consumers.

| Function | Description | Page |
|--|---------------------------------|------|
| tibemsTopic_Create | Create a topic object. | 159 |
| tibemsTopic_Destroy | Destroy a topic object. | 160 |
| tibemsTopic_GetTopicName | Get the name of a topic object. | 161 |

Related Types [tibemsDestination](#) on page 146
[tibemsTemporaryTopic](#) on page 157

tibemsTopic_Create

Function

Purpose Create a topic object.

C Declaration

```
tibems_status tibemsTopic_Create(
    tibemsTopic* topic,
    const char* topicName );
```

COBOL Call

```
CALL "tibemsTopic_Create"
    USING BY REFERENCE topic,
         BY REFERENCE topicName,
         RETURNING tibems-status
END-CALL.
```



topic has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| topic | The function stores the topic object in this location. |
| topicName | Create a local topic instance with this name. |

Remarks This constructor creates only local objects (within the program). It does not attempt to bind the local topic object to the corresponding server object until the program creates a [tibemsMsgConsumer](#) or a [tibemsMsgProducer](#) that uses the topic.

The bind can fail for the following reasons:

- Authorization is enabled for the topic and the user does not have the appropriate permissions.
- The topic does not exist and the server cannot dynamically create the topic.

See Also [tibemsLookupContext](#) on page 334

tibemsTopic_Destroy

Function

Purpose Destroy a topic object.

C Declaration `tibems_status tibemsTopic_Destroy(
tibemsTopic topic);`

COBOL Call `CALL "tibemsTopic_Destroy"
USING BY VALUE topic,
RETURNING tibems-status
END-CALL.`



topic has usage pointer.

Parameters

| Parameter | Description |
|-----------|----------------------------|
| topic | Destroy this topic object. |

tibemsTopic_GetTopicName

Function

Purpose Get the name of a topic object.

C Declaration `tibems_status tibemsTopic_GetTopicName(
tibemsTopic topic,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsTopic_GetTopicName"
USING BY VALUE topic,
BY REFERENCE name,
BY VALUE name-len,
RETURNING tibems-status
END-CALL.`



topic has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| topic | Get the name of this topic. |
| name | The function copies the name to this location. |
| name_len | Length of the name buffer. |

Remarks A null character terminates the copied name string.

Your program must allocate the name buffer, and pass its length to the function. If the length of the topic name is greater than the size of the buffer provided, the entire topic name may not be copied. The buffer size is determined by the TIBEMS_DESTINATION_MAX constant. Constants such as TIBEMS_DESTINATION_MAX are located in the `tibems/types.h` header file.

Chapter 4 **Consumer**

This chapter documents the functions that create and modify message consumers. A message consumer receives messages from a destination.

Topics

- [tibemsMsgConsumer](#), page 164

tibemsMsgConsumer

Type

- Purpose** Consume messages from a destination.
- Remarks** Consumers can receive messages synchronously (using the receive functions), or asynchronously.
Consumers can receive messages asynchronously using callback functions.
Clients create message consumers using functions of a `tibemsSession` object.

| Function | Description | Page |
|---|---|------|
| <code>tibemsMsgConsumer_Close</code> | Closes a message consumer and releases associated storage. | 165 |
| <code>tibemsMsgConsumer_GetDestination</code> | Get the destination from a message consumer. | 166 |
| <code>tibemsMsgConsumer_GetMsgListener</code> | Get the message callback and closure data from a consumer. | 167 |
| <code>tibemsMsgConsumer_GetMsgSelector</code> | Get the message selector from a consumer. | 168 |
| <code>tibemsMsgConsumer_GetNoLocal</code> | Get the no local property of a message consumer. | 169 |
| <code>tibemsMsgConsumer_Receive</code> | Receive a message (synchronous). | 170 |
| <code>tibemsMsgConsumer_ReceiveNoWait</code> | Receive a message (synchronous, non-blocking). | 171 |
| <code>tibemsMsgConsumer_ReceiveTimeout</code> | Receive a message (synchronous, blocks up to a time limit). | 172 |
| <code>tibemsMsgConsumer_SetMsgListener</code> | Set the message callback and closure data of a consumer. | 173 |

See Also `tibemsMsgCallback` on page 174
`tibemsSession_CreateConsumer` on page 301

tibemsMsgConsumer_Close

Function

Purpose Closes a message consumer and releases associated storage.

C Declaration `tibems_status tibemsMsgConsumer_Close(
tibemsMsgConsumer msgConsumer);`

COBOL Call `CALL "tibemsMsgConsumer_Close"
USING BY VALUE msgConsumer,
RETURNING tibems-status
END-CALL.`



msgConsumer has usage pointer.

Parameters

| Parameter | Description |
|-------------|----------------------|
| msgConsumer | Close this consumer. |

Remarks If a receive call or a message listener callback is in progress, then this function waits until that call returns, and then closes the consumer.

This call also notifies the server that the client program is closing the consumer. In response, the server stops sending message data to the consumer.

Your program must explicitly close all consumers that it creates.

See Also [tibemsMsgConsumer_Receive on page 170](#)
[tibemsSession_CreateConsumer on page 301](#)

tibemsMsgConsumer_GetDestination

Function

Purpose Get the destination from a message consumer.

C Declaration `tibems_status tibemsMsgConsumer_GetDestination(
tibemsMsgConsumer msgConsumer,
tibemsDestination* destination);`

COBOL Call `CALL "tibemsMsgConsumer_GetDestination"
USING BY VALUE msgConsumer,
BY REFERENCE destination,
RETURNING tibems-status
END-CALL.`



msgConsumer and destination have usage pointer.

Parameters

| Parameter | Description |
|-------------|---|
| msgConsumer | Get the destination from this consumer. |
| destination | The function stores the destination in this location. |

Remarks The consumer consumes messages from this destination.
Programs set this destination when creating the consumer, and cannot subsequently change it.

tibemsMsgConsumer_GetMsgListener

Function

Purpose Get the message callback and closure data from a consumer.

C Declaration `tibems_status tibemsMsgConsumer_GetMsgListener(
tibemsMsgConsumer msgConsumer,
tibemsMsgCallback* callbackPtr,
void** closure);`

| Parameters | Parameter | Description |
|------------|-------------|--|
| | msgConsumer | Get the listener from this consumer. |
| | callbackPtr | The function stores a pointer to the callback in this location. |
| | closure | The function stores a pointer to the closure data in this location. This pointer is passed into the message listener callback. |

Remarks EMS C programs can implement a message listener as a callback function paired with closure data. This call extracts these items from a consumer object.

Your program implements the callback, and registers it by calling [tibemsMsgConsumer_SetMsgListener](#). When a message arrives, the consumer calls the callback.

This call is not supported in COBOL.

See Also [tibemsMsgConsumer_SetMsgListener](#) on page 173
[tibemsMsgCallback](#) on page 174

tibemsMsgConsumer_GetMsgSelector

Function

Purpose Get the message selector from a consumer.

C Declaration `tibems_status tibemsMsgConsumer_GetMsgSelector(
tibemsMsgConsumer msgConsumer,
const char** selectorPtr);`

COBOL Call `CALL "tibemsMsgConsumer_GetMsgSelector"
USING BY VALUE msgConsumer,
BY REFERENCE selectorPtr,
RETURNING tibems-status
END-CALL.`



msgConsumer and selectorPtr have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgConsumer | Get the listener from this consumer. |
| selectorPtr | The function stores a pointer to the selector string in this location. |

Remarks A message selector restricts the set of messages that the consumer receives to those that match the selector; see [Message Selectors on page 17](#).

Programs can set this property only when creating the consumer object; see [tibemsSession_CreateConsumer on page 301](#).

See Also [tibemsMsgCallback on page 174](#)

tibemsMsgConsumer_GetNoLocal

Function

Purpose Get the no local property of a message consumer.

C Declaration `tibems_status tibemsMsgConsumer_GetNoLocal(
tibemsMsgConsumer msgConsumer,
tibems_bool* noLocal);`

COBOL Call `CALL "tibemsMsgConsumer_GetNoLocal"
USING BY VALUE msgConsumer,
BY REFERENCE noLocal,
RETURNING tibems-status
END-CALL.`



msgConsumer has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgConsumer | Get the property from this consumer. |
| noLocal | The function stores the property value in this location. |

Remarks

When true, the consumer does not receive messages sent through the same server connection (that is, the connection associated with the consumer).

Programs set this property when creating the consumer, and cannot subsequently change it.

This property is only associated with topics, and does not apply to queues.

tibemsMsgConsumer_Receive

Function

Purpose Receive a message (synchronous).

C Declaration `tibems_status tibemsMsgConsumer_Receive(
tibemsMsgConsumer msgConsumer,
tibemsMsg* message);`

COBOL Call `CALL "tibemsMsgConsumer_Receive"
USING BY VALUE msgConsumer,
BY REFERENCE message,
RETURNING tibems-status
END-CALL.`



msgConsumer and message have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgConsumer | Receive a message through this consumer. |
| message | The function stores a pointer to the inbound message in this location. |

Remarks This function consumes the next message from the consumer’s destination. When the destination does not have any messages ready, this function blocks:

- If a message arrives at the destination, this call immediately consumes that message and returns.
- If another thread closes the consumer, this call returns `TIBEMS_INTR`.

When calling `tibemsMsgConsumer_Receive` from a transaction, the consumer retains the message until transaction commits.

See Also [tibemsMsgConsumer_ReceiveNoWait on page 171](#)
[tibemsMsgConsumer_ReceiveTimeout on page 172](#)

tibemsMsgConsumer_ReceiveNoWait

Function

Purpose Receive a message (synchronous, non-blocking).

C Declaration `tibems_status tibemsMsgConsumer_ReceiveNoWait(
tibemsMsgConsumer msgConsumer,
tibemsMsg* message);`

COBOL Call `CALL "tibemsMsgConsumer_ReceiveNoWait"
USING BY VALUE msgConsumer,
BY REFERENCE message,
RETURNING tibems-status
END-CALL.`



msgConsumer and message have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgConsumer | Receive a message through this consumer. |
| msg | The function stores a pointer to the inbound message in this location. |

Remarks When the destination has at least one message ready, this function immediately returns the next message.

When the destination does *not* have any messages ready, this function immediately returns `TIBEMS_NOT_FOUND`.

When calling receive within a transaction, the consumer retains the message until transaction commits.

Note that this function should not be used if the destination property `prefetch=none`.

See Also [tibemsMsgConsumer_Receive on page 170](#)
[tibemsMsgConsumer_ReceiveTimeout on page 172](#)

tibemsMsgConsumer_ReceiveTimeout

Function

Purpose Receive a message (synchronous, blocks up to a time limit).

C Declaration `tibems_status tibemsMsgConsumer_ReceiveTimeout(
tibemsMsgConsumer msgConsumer,
tibemsMsg* message,
tibems_long timeout);`

COBOL Call `CALL "tibemsMsgConsumer_ReceiveTimeout"
USING BY VALUE msgConsumer,
BY REFERENCE message,
BY VALUE timeout,
RETURNING tibems-status
END-CALL.`



msgConsumer and message have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgConsumer | Receive a message through this consumer. |
| msg | The function stores a pointer to the inbound message in this location. |
| timeout | When present, wait no longer than this interval (in milliseconds) for a message to arrive. Zero is a special value, which specifies no timeout (block indefinitely). |

Remarks This function consumes the next message from the consumer’s destination. When the destination does not have any messages ready, this function blocks:

- If a message arrives at the destination, this call immediately consumes that message and returns.
- If the (non-zero) timeout elapses before a message arrives, this call returns `TIBEMS_TIMEOUT`.
- If another thread closes the consumer, this call returns `TIBEMS_INTR`.

When calling receive within a transaction, the consumer retains the message until transaction commits.

See Also [tibemsMsgConsumer_Receive on page 170](#)
[tibemsMsgConsumer_ReceiveNoWait on page 171](#)

tibemsMsgConsumer_SetMsgListener

Function

Purpose Set the message callback and closure data of a consumer.

C Declaration `tibems_status tibemsMsgConsumer_SetMsgListener(
 tibemsMsgConsumer msgConsumer,
 tibemsMsgCallback callback,
 void* closure);`

Parameters

| Parameter | Description |
|-------------|------------------------------------|
| msgConsumer | Set the listener of this consumer. |
| callback | Use this callback function. |
| closure | Use this closure data. |

Remarks EMS C programs can implement a message listener as a callback function paired with closure data. This call sets these items in a consumer object.

Your program implements the callback, and registers it by calling this function. When a message arrives, the consumer calls the callback.

This call is not supported in COBOL.

See Also [tibemsMsgCallback on page 174](#)

tibemsMsgCallback

Type

Purpose Asynchronously process an arriving message.

C Declaration

```
typedef void (*tibemsMsgCallback) (  
    tibemsMsgConsumer msgConsumer,  
    tibemsMsg msg,  
    void* closure );
```

| Parameters | Parameter | Description |
|------------|-------------|--|
| | msgConsumer | This parameter receives the consumer object. |
| | msg | This parameter receives the message object. |
| | closure | This parameter receives the closure argument, which your program registered on the consumer. |

Remarks To asynchronous receive messages, your program can define callback functions of this type, and register them with a consumer (using [tibemsMsgConsumer_SetMsgListener](#) or a related function). When a message arrives, the consumer calls its callback.

Serialization In compliance with the JMS specification, sessions distribute messages to consumers in serial (non-concurrent) fashion.

See Also [tibemsMsgConsumer](#) on page 164

Chapter 5 **Producer**

Message producers send messages to destinations on the server.

Topics

- [tibemsMsgProducer](#), page 176

tibemsMsgProducer

Type

- Purpose** Send message to destinations on the server.
- Remarks** Clients use message producers to send messages. A message producer object can store several parameters that affect the messages it sends.

Clients create message producers using functions of a `tibemsSession` object.

| Function | Description | Page |
|--|--|------|
| <code>tibemsMsgProducer_AsyncSend</code> <code>tibemsMsgProducer_AsyncSendEx</code> <code>tibemsMsgProducer_AsyncSendToDestination</code> <code>tibemsMsgProducer_AsyncSendToDestinationEx</code> | Asynchronously send a message. | 178 |
| <code>tibemsMsgProducer_Close</code> | Destroy the producer object; reclaim resources. | 182 |
| <code>tibemsMsgProducer_GetDeliveryDelay</code> | Get the delivery delay property of a producer object. | 183 |
| <code>tibemsMsgProducer_GetDeliveryMode</code> | Get the delivery mode property of a producer object. | 184 |
| <code>tibemsMsgProducer_GetDestination</code> | Get the destination of a message producer object. | 185 |
| <code>tibemsMsgProducer_GetDisableMessageID</code> | Get the disable message ID property of a producer object. | 186 |
| <code>tibemsMsgProducer_GetDisableMessageTimestamp</code> | Get the disable message timestamp property of a producer object. | 187 |
| <code>tibemsMsgProducer_GetNPSSendCheckMode</code> | Get the mode that defines when a producer checks the result of sending a NON_PERSISTENT message. | 188 |
| <code>tibemsMsgProducer_GetPriority</code> | Get the priority property of a producer object. | 189 |

| Function | Description | Page |
|--|--|------|
| tibemsMsgProducer_GetTimeToLive | Get the time-to-live property of a producer object. | 190 |
| tibemsMsgProducer_Send | Send a message. | 191 |
| tibemsMsgProducer_SendEx | | |
| tibemsMsgProducer_SendToDestination | | |
| tibemsMsgProducer_SendToDestinationEx | | |
| tibemsMsgProducer_SetDeliveryDelay | Set the delivery delay property of a producer object. | 194 |
| tibemsMsgProducer_SetDeliveryMode | Set the delivery mode property of a producer object. | 195 |
| tibemsMsgProducer_SetDisableMessageID | Set the disable message ID property of a producer object. | 196 |
| tibemsMsgProducer_SetDisableMessageTimestamp | Set the disable message timestamp property of a producer object. | 197 |
| tibemsMsgProducer_SetNPSSendCheckMode | Set when a producer should check the result of sending a NON_PERSISTENT message. | 198 |
| tibemsMsgProducer_SetPriority | Set the priority property of a producer object. | 200 |
| tibemsMsgProducer_SetTimeToLive | Set the time-to-live property of a producer object. | 201 |

See Also [tibemsSession_CreateProducer](#) on page 308

tibemsMsgProducer_AsyncSend

Function

Purpose Asynchronously send a message.

C Declaration

```
tibems_status tibemsMsgProducer_AsyncSend(  
    tibemsMsgProducer msgProducer,  
    tibemsMsg message  
    tibemsMsgCompletionCallback asyncSendCallback,  
    void* asyncSendClosure );  
  
tibems_status tibemsMsgProducer_AsyncSendEx(  
    tibemsMsgProducer msgProducer,  
    tibemsMsg message,  
    tibems_int deliveryMode,  
    tibems_int priority,  
    tibems_long timeToLive  
    tibemsMsgCompletionCallback asyncSendCallback,  
    void* asyncSendClosure );  
  
tibems_status tibemsMsgProducer_AsyncSendToDestination(  
    tibemsMsgProducer msgProducer,  
    tibemsDestination destination,  
    tibemsMsg message  
    tibemsMsgCompletionCallback asyncSendCallback,  
    void* asyncSendClosure );  
  
tibems_status tibemsMsgProducer_AsyncSendToDestinationEx(  
    tibemsMsgProducer msgProducer,  
    tibemsDestination destination,  
    tibemsMsg message,  
    tibemsDeliveryMode deliveryMode,  
    tibems_int priority,  
    tibems_long timeToLive  
    tibemsMsgCompletionCallback asyncSendCallback,  
    void* asyncSendClosure );
```

Parameters

| Parameter | Description |
|-------------|---|
| msgProducer | Send a message through this producer object. |
| destination | <p>When present, the call sends the message to this destination (queue or topic).</p> <p>Other send calls send the message to the producer’s default destination. When the producer does not specify a default, the send call must supply this parameter.</p> |
| message | Send this message object. |

| Parameter | Description |
|---------------------------|--|
| <code>deliveryMode</code> | <p>When present, the call sends the message with this delivery mode.</p> <p>This argument is an enumerated value (see tibemsDeliveryMode on page 129).</p> <p>Other send calls send the message with the producer's default delivery mode.</p> |
| <code>priority</code> | <p>When present, the call sends the message with this priority.</p> <p>Priority affects the order in which the server delivers messages to consumers (higher values first). The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.</p> <p>Other send calls send the message with the producer's default priority.</p> |
| <code>timeToLive</code> | <p>When present, the call uses this value (in milliseconds) to compute the message expiration.</p> <ul style="list-style-type: none"> • If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client's current time (GMT). This rule applies even within sessions with transaction semantics—the timer begins with the send call, not the commit call. • If the time-to-live is zero, then expiration is also zero—indicating that the message never expires. <p>Other send calls use the producer's default value to compute expiration.</p> <p>Whenever your application uses non-zero values for message expiration or time-to-live, you must ensure that clocks are synchronized among all the host computers that send and receive messages. Synchronize clocks to a tolerance that is a very small fraction of the smallest or time-to-live.</p> |

| Parameter | Description |
|--------------|---|
| deliveryMode | <p>When present, the call sends the message with this delivery mode.</p> <p>This argument is an enumerated value (see tibemsDeliveryMode on page 129).</p> <p>Other send calls send the message with the producer's default delivery mode.</p> |
| priority | <p>When present, the call sends the message with this priority.</p> <p>Priority affects the order in which the server delivers messages to consumers (higher values first). The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.</p> <p>Other send calls send the message with the producer's default priority.</p> |
| timeToLive | <p>When present, the call uses this value (in milliseconds) to compute the message expiration.</p> <ul style="list-style-type: none">• If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client's current time (GMT). This rule applies even within sessions with transaction semantics—the timer begins with the send call, not the commit call.• If the time-to-live is zero, then expiration is also zero—indicating that the message never expires. <p>Other send calls use the producer's default value to compute expiration.</p> <p>Whenever your application uses non-zero values for message expiration or time-to-live, you must ensure that clocks are synchronized among all the host computers that send and receive messages. Synchronize clocks to a tolerance that is a very small fraction of the smallest or time-to-live.</p> |

| Parameter | Description |
|------------------------------|---|
| asyncSendCallback | A callback to be invoked when a message has successfully been sent. |
| asyncSendCallback Closure | Data to be passed into the asyncSendCallback. |

tibemsMsgProducer_Close

Function

Purpose Destroy the producer object; reclaim resources.

C Declaration `tibems_status tibemsMsgProducer_Close(
tibemsMsgProducer msgProducer);`

COBOL Call `CALL "tibemsMsgProducer_Close"
USING BY VALUE msgProducer,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|----------------------|
| msgProducer | Close this producer. |

Remarks This call also notifies the server that the client program is closing the producer. In response, the server reclaims storage associated with the producer.
Your program must explicitly close all producers that it creates.

See Also [tibemsSession_CreateProducer on page 308](#)

tibemsMsgProducer_GetDeliveryDelay

Function

Purpose Get the delivery delay property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_GetDeliveryDelay(
tibemsMsgProducer msgProducer,
tibems_long* deliveryDelay);`

COBOL Call `CALL "tibemsMsgProducer_GetDeliveryDelay"
USING BY VALUE msgProducer,
BY REFERENCE deliveryDelay,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|---------------|--|
| msgProducer | Get the property from this producer. |
| deliveryDelay | The function stores the property in this location. |

Remarks Gets the minimum length of time, in milliseconds, that must elapse after a message is sent before the JMS provider may deliver the message to a consumer.

See Also [tibemsMsg_GetDeliveryTime on page 41](#)
[tibemsMsgProducer_SetDeliveryDelay on page 194](#)

tibemsMsgProducer_GetDeliveryMode

Function

Purpose Get the delivery mode property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_GetDeliveryMode(
tibemsMsgProducer msgProducer,
tibems_int* deliveryMode);`

COBOL Call `CALL "tibemsMsgProducer_GetDeliveryMode"
USING BY VALUE msgProducer,
BY REFERENCE deliveryMode,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| msgProducer | Get the property from this producer. |
| deliveryMode | The function stores the property in this location. |

Remarks Delivery mode instructs the server concerning persistent storage. Programs can use this property to define a default delivery mode for messages that this producer sends. Individual sending calls can override this default value. For values, see the type [tibemsDeliveryMode](#) on page 129.

tibemsMsgProducer_GetDestination

Function

Purpose Get the destination of a message producer object.

C Declaration `tibems_status tibemsMsgProducer_GetDestination(
tibemsMsgProducer msgProducer,
tibemsDestination* destination);`

COBOL Call `CALL "tibemsMsgProducer_GetDestination"
USING BY VALUE msgProducer,
BY REFERENCE destination,
RETURNING tibems-status
END-CALL.`



msgProducer and destination have usage pointer.

Parameters

| Parameter | Description |
|-------------|---|
| msgProducer | Get the destination from this producer. |
| destination | The function stores the destination in this location. |

Remarks Each send call directs a message to a destination.

Programs can use this property to define a default destination for messages that this producer sends. Individual sending calls can override this default value.

Programs set this destination when creating the sender, and cannot subsequently change it.

tibemsMsgProducer_GetDisableMessageID

Function

Purpose Get the disable message ID property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_GetDisableMessageID(
tibemsMsgProducer msgProducer,
tibems_bool* disable);`

COBOL Call `CALL "tibemsMsgProducer_GetDisableMessageID"
USING BY VALUE msgProducer,
BY REFERENCE disable,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgProducer | Get the property from this producer. |
| disable | The function stores the property in this location. |

Remarks Applications that do not require message IDs can reduce overhead costs by disabling IDs (set this property to true).

tibemsMsgProducer_GetDisableMessageTimestamp

Function

Purpose Get the disable message timestamp property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_GetDisableMessageTimestamp(
tibemsMsgProducer msgProducer,
tibems_bool* disable);`

COBOL Call `CALL "tibemsMsgProducer_GetDisableMessageTimestamp"
USING BY VALUE msgProducer,
BY REFERENCE disable,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------------------|--|
| msgProducer | Get the property from this producer. |
| disableMessageTimeStamp | The function stores the property in this location. |

Remarks Applications that do not require timestamps can reduce overhead costs by disabling timestamps (set this property to true).

tibemsMsgProducer_GetNPSTransmitCheckMode

Function

Purpose Get the mode that defines when a producer checks the result of sending a NON_PERSISTENT message.

C Declaration `extern tibems_status tibemsMsgProducer_GetNPSTransmitCheckMode(
 tibemsMsgProducer msgProducer,
 tibemsNpCheckMode* mode);`

COBOL Call `CALL "tibemsMsgProducer_GetNPSTransmitCheckMode"
 USING BY VALUE msgProducer,
 BY REFERENCE mode,
 RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgProducer | Get the property from this producer. |
| mode | The function stores the mode in this location. Must not be null. See tibemsNpCheckMode on page 130 for details. |

Remarks This function returns the send check mode set by the [tibemsMsgProducer_SetNPSTransmitCheckMode](#) function. If the returned value is NPSEND_CHECK_DEFAULT, then the effective mode can be set by the server parameter applied to all producers.

See Also [tibemsMsgProducer_SetNPSTransmitCheckMode on page 198](#)

tibemsMsgProducer_GetPriority

Function

Purpose Get the priority property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_GetPriority(
tibemsMsgProducer msgProducer,
tibems_int* priority);`

COBOL Call `CALL "tibemsMsgProducer_GetPriority"
USING BY VALUE msgProducer,
BY REFERENCE priority,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgProducer | Get the property from this producer. |
| priority | The function stores the property in this location. |

Remarks Priority affects the order in which the server delivers messages to consumers (higher values first).

The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.

Programs can use this property to define a default priority for messages that this producer sends. Individual sending calls can override this default value.

tibemsMsgProducer_GetTimeToLive

Function

Purpose Get the time-to-live property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_GetTimeToLive(
tibemsMsgProducer msgProducer,
tibems_long* timeToLive);`

COBOL Call `CALL "tibemsMsgProducer_GetTimeToLive"
USING BY VALUE msgProducer,
BY REFERENCE timeToLive,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| msgProducer | Get the property from this producer. |
| timeToLive | The function stores the property in this location. |

- Remarks** Time-to-live (in milliseconds) determines the expiration time of a message.
- If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client’s current time (GMT). This rule applies even within sessions with transaction semantics—the timer begins with the send call, not the commit call.
 - If the time-to-live is zero, then expiration is also zero—indicating that the message never expires.

Programs can use this property to define a default time-to-live for messages that this producer sends. Individual sending calls can override this default value.

Whenever your application uses non-zero values for message expiration or time-to-live, you must ensure that clocks are synchronized among all the host computers that send and receive messages. Synchronize clocks to a tolerance that is a very small fraction of the smallest or time-to-live.

tibemsMsgProducer_Send

Function

Purpose Send a message.

C Declaration

```

tibems_status tibemsMsgProducer_Send(
    tibemsMsgProducer msgProducer,
    tibemsMsg message );

tibems_status tibemsMsgProducer_SendEx(
    tibemsMsgProducer msgProducer,
    tibemsMsg message,
    tibems_int deliveryMode,
    tibems_int priority,
    tibems_long timeToLive );

tibems_status tibemsMsgProducer_SendToDestination(
    tibemsMsgProducer msgProducer,
    tibemsDestination destination,
    tibemsMsg message );

tibems_status tibemsMsgProducer_SendToDestinationEx(
    tibemsMsgProducer msgProducer,
    tibemsDestination destination,
    tibemsMsg message,
    tibemsDeliveryMode deliveryMode,
    tibems_int priority,
    tibems_long timeToLive );

```

COBOL Call

```

CALL "tibemsMsgProducer_Send"
    USING BY VALUE msgProducer,
          BY VALUE message,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMsgProducer_SendEx"
    USING BY VALUE msgProducer,
          BY VALUE message,
          BY VALUE deliveryMode,
          BY VALUE priority,
          BY VALUE timeToLive,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMsgProducer_SendToDestination"
    USING BY VALUE msgProducer,
          BY VALUE destination,
          BY VALUE message,
          RETURNING tibems-status
END-CALL.

CALL "tibemsMsgProducer_SendToDestinationEx"
    USING BY VALUE msgProducer,
          BY VALUE destination,
          BY VALUE message,

```

```
        BY VALUE deliveryMode,  
        BY VALUE priority,  
        BY VALUE timeToLive,  
        RETURNING tibems-status  
END-CALL.
```



msgProducer, message and destination have usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| msgProducer | Send a message through this producer object. |
| destination | <p>When present, the call sends the message to this destination (queue or topic).</p> <p>Other send calls send the message to the producer’s default destination. When the producer does not specify a default, the send call must supply this parameter.</p> |
| message | Send this message object. |
| deliveryMode | <p>When present, the call sends the message with this delivery mode.</p> <p>This argument is an enumerated value (see tibemsDeliveryMode on page 129).</p> <p>Other send calls send the message with the producer’s default delivery mode.</p> |
| priority | <p>When present, the call sends the message with this priority.</p> <p>Priority affects the order in which the server delivers messages to consumers (higher values first). The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.</p> <p>Other send calls send the message with the producer’s default priority.</p> |

| Parameter | Description |
|------------|---|
| timeToLive | <p>When present, the call uses this value (in milliseconds) to compute the message expiration.</p> <ul style="list-style-type: none">• If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client's current time (GMT). This rule applies even within sessions with transaction semantics—the timer begins with the send call, not the commit call.• If the time-to-live is zero, then expiration is also zero—indicating that the message never expires. <p>Other send calls use the producer's default value to compute expiration.</p> <p>Whenever your application uses non-zero values for message expiration or time-to-live, you must ensure that clocks are synchronized among all the host computers that send and receive messages. Synchronize clocks to a tolerance that is a very small fraction of the smallest or time-to-live.</p> |

tibemsMsgProducer_SetDeliveryDelay

Function

Purpose Set the delivery delay property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_SetDeliveryDelay(
tibemsMsgProducer msgProducer,
tibems_long deliveryDelay);`

COBOL Call `CALL "tibemsMsgProducer_SetDeliveryDelay"
USING BY VALUE msgProducer,
BY VALUE deliveryDelay,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|---------------|------------------------------------|
| msgProducer | Set the property of this producer. |
| deliveryDelay | Set the property to this value. |

Remarks Sets the minimum length of time, in milliseconds, that must elapse after a message is sent before the JMS provider may deliver the message to a consumer.

For transacted sends, this time starts when the client sends the message, not when the transaction is committed.

The default value is zero, indicating no delay in delivery.

See Also [tibemsMsg_GetDeliveryTime on page 41](#)
[tibemsMsgProducer_GetDeliveryDelay on page 183](#)

tibemsMsgProducer_SetDeliveryMode

Function

Purpose Set the delivery mode property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_SetDeliveryMode(
tibemsMsgProducer msgProducer,
tibems_int deliveryMode);`

COBOL Call `CALL "tibemsMsgProducer_SetDeliveryMode"
USING BY VALUE msgProducer,
BY VALUE deliveryMode,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|--------------|------------------------------------|
| msgProducer | Set the property of this producer. |
| deliveryMode | Set the property to this value. |

Remarks Delivery mode instructs the server concerning persistent storage.
Programs can use this property to define a default delivery mode for messages that this producer sends. Individual sending calls can override this default value.
For values, see the type [tibemsDeliveryMode on page 129](#).

tibemsMsgProducer_SetDisableMessageID

Function

Purpose Set the disable message ID property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_SetDisableMessageID(
tibemsMsgProducer msgProducer,
tibems_bool disable);`

COBOL Call `CALL "tibemsMsgProducer_SetDisableMessageID"
USING BY VALUE msgProducer,
BY VALUE disable,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|------------------------------------|
| msgProducer | Set the property of this producer. |
| disable | Set the property to this value. |

Remarks Applications that do not require message IDs can reduce overhead costs by disabling IDs (set this property to true).

tibemsMsgProducer_SetDisableMessageTimestamp

Function

Purpose Set the disable message timestamp property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_SetDisableMessageTimestamp(
tibemsMsgProducer msgProducer,
tibems_bool disable);`

COBOL Call `CALL "tibemsMsgProducer_SetDisableMessageTimestamp"
USING BY VALUE msgProducer,
BY VALUE disable,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|------------------------------------|
| msgProducer | Set the property of this producer. |
| disable | Set the property to this value. |

Remarks Applications that do not require timestamps can reduce overhead costs by disabling timestamps (set this property to true).

tibemsMsgProducer_SetNPSendCheckMode

Function

Purpose Set when a producer should check the result of sending a NON_PERSISTENT message.

C Declaration

```
extern tibems_status tibemsMsgProducer_SetNPSendCheckMode(
    tibemsMsgProducer msgProducer,
    tibemsNpCheckMode mode);
```

COBOL Call

```
CALL "tibemsMsgProducer_SetNPSendCheckMode"
    USING BY VALUE msgProducer,
          BY VALUE mode,
          RETURNING tibems-status
END-CALL.
```



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|---|
| msgProducer | Set the property of this producer. |
| mode | The send check mode. See tibemsNpCheckMode on page 130 for details. |

Remarks [tibemsNpCheckMode](#) only applies to messages sent using the NON_PERSISTENT delivery mode, using non-transactional Session. It does not apply to cases when message was sent using PERSISTENT or RELIABLE_DELIVERY delivery modes, or if the corresponding Session is transactional.

If the producer's send check mode is not set, it may execute the mode applied globally to all producers via EMS server parameter. Setting any mode other than NPSEND_CHECK_DEFAULT unconditionally overrides global setting defined by the server.

Normally applications use the server's setting or configure producers with a specific send mode only once. However, if required, applications may choose to change this mode before sending every message.

If a producer does not check the result of sending a message, it will not know if a problem has occurred and the message was not processed by the server. If the producer checks the result of the send, the send method will receive the server's response to the send and throw the appropriate exception if any problem has occurred. However, checking the result of sending a message will reduce the performance of the producer.

See Also [tibemsMsgProducer_GetNPSendCheckMode on page 188](#)

tibemsMsgProducer_SetPriority

Function

Purpose Set the priority property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_SetPriority(
tibemsMsgProducer msgProducer,
tibems_int priority);`

COBOL Call `CALL "tibemsMsgProducer_SetPriority"
USING BY VALUE msgProducer,
BY VALUE priority,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|------------------------------------|
| msgProducer | Set the property of this producer. |
| priority | Set the property to this value. |

Remarks Priority affects the order in which the server delivers messages to consumers (higher values first).

The JMS specification defines ten levels of priority value, from zero (lowest priority) to 9 (highest priority). The specification suggests that clients consider 0–4 as gradations of normal priority, and priorities 5–9 as gradations of expedited priority.

Programs can use this property to define a default priority for messages that this producer sends. Individual sending calls can override this default value.

tibemsMsgProducer_SetTimeToLive

Function

Purpose Set the time-to-live property of a producer object.

C Declaration `tibems_status tibemsMsgProducer_SetTimeToLive(
tibemsMsgProducer msgProducer,
tibems_long timeToLive);`

COBOL Call `CALL "tibemsMsgProducer_SetTimeToLive"
USING BY VALUE msgProducer,
BY VALUE timeToLive,
RETURNING tibems-status
END-CALL.`



msgProducer has usage pointer.

Parameters

| Parameter | Description |
|-------------|------------------------------------|
| msgProducer | Set the property of this producer. |
| timeToLive | Set the property to this value. |

- Remarks** Time-to-live (in milliseconds) determines the expiration time of a message.
- If the time-to-live is non-zero, the expiration is the sum of that time-to-live and the sending client’s current time (GMT). This rule applies even within sessions with transaction semantics—the timer begins with the send call, not the commit call.
 - If the time-to-live is zero, then expiration is also zero—indicating that the message never expires.

Programs can use this property to define a default time-to-live for messages that this producer sends. Individual sending calls can override this default value.

Whenever your application uses non-zero values for message expiration or time-to-live, you must ensure that clocks are synchronized among all the host computers that send and receive messages. Synchronize clocks to a tolerance that is a very small fraction of the smallest or time-to-live.

Chapter 6 Requestor

Requestors implement convenience functions for request-reply semantics. They send messages (called *requests*) and wait for *reply* messages in response.

Topics

- [tibemsMsgRequestor](#), page 204

tibemsMsgRequestor

Type

- Purpose**Encapsulate request-reply semantics.
- Remarks**

We recommend that programs follow these steps:
 1. Create a [tibemsSession](#), and use it to create either a [tibemsQueue](#) or [tibemsTopic](#) (respectively) for requests and replies.
 2. Supply that session and destination to [tibemsMsgRequestor_Create](#) to create a `tibemsMsgRequestor`.
 3. Call [tibemsMsgRequestor_Request](#) to send a request and receive a reply. You may repeat this step for several request and reply pairs.
 4. Close the requestor object. [tibemsMsgRequestor_Close](#) also closes the requestor’s session as a side effect.

| Function | Description | Page |
|--|---|------|
| tibemsMsgRequestor_Close | Close a message requestor. | 205 |
| tibemsMsgRequestor_Create | Create a message requestor. | 206 |
| tibemsMsgRequestor_Request | Send a request message; wait for a reply. | 208 |

See Also

[tibemsSession](#)
[tibemsQueue](#) on page 152
[tibemsTopic](#) on page 158

tibemsMsgRequestor_Close

Function

Purpose Close a message requestor.

C Declaration `tibems_status tibemsMsgRequestor_Close(
tibemsMsgRequestor msgRequestor);`

COBOL Call `CALL "tibemsMsgRequestor_Close"
USING BY VALUE msgRequestor,
RETURNING tibems-status
END-CALL.`



msgRequestor has usage pointer.

Parameters

| Parameter | Description |
|--------------|-----------------------|
| msgRequestor | Close this requestor. |

Remarks This call also closes the requestor’s session as a side effect.

tibemsMsgRequestor_Create

Function

Purpose Create a message requestor.

C Declaration `tibems_status tibemsMsgRequestor_Create(
tibemsSession session,
tibemsMsgRequestor* msgRequestor,
tibemsDestination destination);`

COBOL Call `CALL "tibemsMsgRequestor_Create"
USING BY VALUE session,
BY REFERENCE msgRequestor,
BY VALUE destination,
RETURNING tibems-status
END-CALL.`



session, msgRequestor and destination have usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| session | The requestor operates within this session. This session must not use transaction semantics. Its delivery mode must be either TIBEMS_AUTO_ACKNOWLEDGE or TIBEMS_DUPS_OK_ACKNOWLEDGE . |
| msgRequestor | The function stores the new requestor in this location. |
| destination | The requestor sends request messages to this destination, and waits for replies on an internally created temporary destination. If the destination that request messages are sent to is a queue, then an internal temporary queue is created and used. If the destination that request messages are sent to is a topic, then an internal temporary topic is created and used. You <i>must</i> create this destination using the session you supply as the first argument. |

- Remarks** We recommend that programs follow these steps:
1. Create a [tibemsSession](#), and use it to create a [tibemsQueue](#) or [tibemsTopic](#) for requests and replies.
 2. Create a [tibemsMsgRequestor](#), using the session and destination as arguments.
 3. Send a request and receive a reply with [tibemsMsgRequestor_Request](#). You may repeat this step for several request and reply pairs.
 4. Close the requestor object. [tibemsMsgRequestor_Close](#) also closes the requestor's session as a side effect.
- See Also** [tibemsDestination](#) on page 146
[tibemsMsgRequestor_Close](#) on page 205
[tibemsMsgRequestor_Request](#) on page 208
[tibemsSession](#) on page 294

tibemsMsgRequestor_Request

Function

Purpose Send a request message; wait for a reply.

C Declaration `tibems_status tibemsMsgRequestor_Request(
tibemsMsgRequestor msgRequestor,
tibemsMsg message,
tibemsMsg* reply);`

COBOL Call `CALL "tibemsMsgRequestor_Request"
USING BY VALUE msgRequestor,
BY VALUE message,
BY REFERENCE reply,
RETURNING tibems-status
END-CALL.`



msgRequestor, message and reply have usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| msgRequestor | Send and receive through this requestor. |
| message | Send this request message. |
| reply | When a reply message arrives, the function stores it in this location. |

Remarks This call blocks indefinitely, until a reply arrives.
The requestor receives only the first reply. It discards other replies that arrive subsequently.

Chapter 7 **Connection**

Connection objects represent a client program's network connection to the server.

Topics

- [tibemsConnection](#), page 210
- [tibemsConnectionMetaData](#), page 227
- [tibemsExceptionCallback](#), page 233
- [tibemsMulticastExceptionCallback](#), page 234
- [tibemsSSL](#), page 235
- [tibemsSSLParams](#), page 239
- [tibemsSSLHostNameVerifier](#), page 254

tibemsConnection

Type

- Purpose

Represent a server connection.
- Remarks

When a program first opens a connection, the connection is *stopped*—that is, it does not deliver inbound messages. To begin the flow of inbound messages, the program must explicitly call `tibemsConnection_Start`. (Outbound messages flow even before calling `tibemsConnection_Start`.)

The EMS C and COBOL APIs do *not* support the JMS methods `createConnectionConsumer` and `createDurableConnectionConsumer` (which are optional in the JMS specification).
- Asynchronous Errors

When a program uses a connection to send messages, the send calls can detect problems with the connection, and notify the client program (synchronously) by returning error codes.

However, when a program uses a connection only to receive messages, the client lacks that opportunity to detect problems. Instead, programs can handle such errors asynchronously by defining an exception listener callback (see [tibemsExceptionCallback on page 233](#)).

| Function | Description | Page |
|---|--|------|
| tibemsConnection_Close | Close the connection; reclaim resources. | 212 |
| tibemsConnection_Create tibemsConnection_CreateSSL | Create a new connection to an EMS server. | 214 |
| tibemsConnection_CreateSession | Create a session object. | 216 |
| tibemsConnection_GetActiveURL | Get the active URL of a connection. | 217 |
| tibemsConnection_GetClientId | Get the client ID of a connection. | 218 |
| tibemsConnection_GetExceptionListener | Get the exception listener of a connection. | 219 |
| tibemsConnection_GetMetaData | Get the metadata from a connection. | 220 |
| tibemsConnection_IsDisconnected | Checks whether the connection has been disconnected. | 221 |
| tibemsConnection_SetClientId | Set the client ID of a connection. | 222 |

| Function | Description | Page |
|---|--|---------------------|
| tibemsConnection_SetExceptionListener | Set the exception listener for a connection. | 223 |
| tibemsConnection_Start | Start delivering inbound messages. | 224 |
| tibemsConnection_Stop | Stop delivering inbound messages. | 225 |

tibemsConnection_Close

Function

Purpose Close the connection; reclaim resources.

C Declaration `tibems_status tibemsConnection_Close(
tibemsConnection connection);`

COBOL Call CALL "tibemsConnection_Close"
USING BY VALUE connection,
RETURNING tibems-status
END-CALL.



connection has usage pointer.

Parameters

| Parameter | Description |
|------------|------------------------|
| connection | Close this connection. |

Remarks Closing the connection is not sufficient to reclaim all of its resources; your program must explicitly close the sessions, producers, and consumers associated with the connection.

Closing a connection deletes all temporary destinations associated with the connection.

Blocking If any message listener or receive call associated with the connection is processing a message when the program calls this function, all facilities of the connection and its sessions remain available to those listeners until they return. In the meantime, this function blocks until that processing completes—that is, until all message listeners and receive calls have returned.

Acknowledge Closing a connection does *not* force acknowledgment in client-acknowledged sessions. When the program still has a message that it received from a connection that has since closed, `tibemsMsg_Acknowledge` indicates status code `TIBEMS_ILLEGAL_STATE`.

Transactions Closing a connection rolls back all open transactions in all sessions associated with the connection.

| Status Code | Description |
|--------------------------------------|--|
| TIBEMS_ILLEGAL_STATE | The connection is currently processing a message callback. |

See Also [tibemsMsg_Acknowledge on page 25](#)
[tibemsMsgConsumer on page 164](#)
[tibemsMsgProducer on page 176](#)
[tibemsDestination on page 146](#)
[tibemsSession on page 294](#)

tibemsConnection_Create

Function

Purpose Create a new connection to an EMS server.

C Declarations

```

tibems_status tibemsConnection_Create(
    tibemsConnection* connection,
    const char* brokerURL,
    const char* clientId,
    const char* username,
    const char* password );

tibems_status tibemsConnection_CreateSSL(
    tibemsConnection* connection,
    const char* brokerURL,
    const char* clientId,
    const char* username,
    const char* password,
    tibemsSSLParams sslParams,
    const char* pk_password );

```

COBOL Call

```

CALL "tibemsConnection_Create"
  USING BY REFERENCE connection,
        BY REFERENCE brokerURL,
        BY REFERENCE clientId,
        BY REFERENCE username,
        BY REFERENCE password
  RETURNING tibems-status
END-CALL.

CALL "tibemsConnection_CreateSSL"
  USING BY REFERENCE connection,
        BY REFERENCE brokerURL,
        BY REFERENCE clientId,
        BY REFERENCE username,
        BY REFERENCE password,
        BY VALUE tibemsSSLParams,
        BY REFERENCE pk-password,
  RETURNING tibems-status
END-CALL.

```



connection and sslParams have usage pointer.

On IBM z/OS systems, the pk-password must always be a null value.

Parameters

| Parameter | Description |
|-------------|---|
| connection | The function stores the new connection in this location. |
| brokerURL | Find the EMS server at this URL. If configuring a fault-tolerant client, enter two or more URLs, as described in Configuring C and COBOL Clients for Fault-Tolerant Connections on page 5 . |
| clientId | Identify the client program to the server with this unique ID. |
| username | Authenticate the client program to the server with this user name. |
| password | Authenticate the client program to the server with this password. |
| sslParams | Establish SSL communication using these parameters. |
| pk_password | Private key password for SSL. |

Remarks

When the authentication parameters are null, the connection object presents a default user identity. If the server configuration permits that anonymous user, then the call succeeds.

| Status Code | Description |
|---|---|
| TIBEMS_SERVER_NOT_CONNECTED | <ul style="list-style-type: none">No server is running at the specified URL.The call could not communicate with a server because of mismatched SSL and TCP protocols.Other error situations are possible. |
| TIBEMS_SECURITY_EXCEPTION | <ul style="list-style-type: none">The server rejected the connection because the username or password was invalid.SSL setup is incorrect. |
| TIBEMS_INVALID_CLIENT_ID | The client ID is not unique; that is, another client already uses the ID. |

See Also

[tibemsConnectionFactory_Create on page 261](#)
[SSL Implementation on IBM EBCDIC Systems on page 576](#)

tibemsConnection_CreateSession

Function

Purpose Create a session object.

C Declaration `tibems_status tibemsConnection_CreateSession(
tibemsConnection connection,
tibemsSession* session,
tibems_bool transacted,
tibemsAcknowledgeMode acknowledgeMode);`

COBOL Call `CALL "tibemsConnection_CreateSession"
USING BY VALUE connection,
BY REFERENCE session,
BY VALUE transacted,
BY VALUE acknowledgeMode,
RETURNING tibems-status
END-CALL.`



connection and session have usage pointer.

Parameters

| Parameter | Description |
|-----------------|---|
| connection | Create a session on this connection. |
| session | The function stores the new session in this location. |
| transacted | When true, the new session has transaction semantics. When false, it has non-transaction semantics. |
| acknowledgeMode | This parameter determines the acknowledge mode of the session. Supply a value enumerated by <code>tibemsAcknowledgeMode</code> . |

Remarks The new session uses the connection for all server communications.

See Also [tibemsMsg_Acknowledge on page 25](#)
[tibemsSession on page 294](#)
[tibemsAcknowledgeMode on page 324](#)

tibemsConnection_GetActiveURL

Function

Purpose Get the active URL of a connection.

C Declaration `tibems_status tibemsConnection_GetActiveURL(
tibemsConnection connection,
char** serverURL);`

COBOL Call `CALL "tibemsConnection_GetActiveURL"
USING BY VALUE connection,
BY REFERENCE serverURL,
RETURNING tibems-status
END-CALL.`



connection and serverURL have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| connection | Get the active URL of this connection. |
| serverURL | The function stores a pointer to the URL in this location. |

Remarks This property is the URL of the server at the other endpoint of the connection. When the connection interacts with several servers in a fault-tolerant arrangement, this property indicates the current active server.

tibemsConnection_GetClientId

Function

Purpose Get the client ID of a connection.

C Declaration `tibems_status tibemsConnection_GetClientId(
tibemsConnection connection,
const char** clientId);`

COBOL Call `CALL "tibemsConnection_GetClientId"
USING BY VALUE connection,
BY REFERENCE clientId,
RETURNING tibems-status
END-CALL.`



connection and clientId have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| connection | Get the client ID of this connection. |
| clientId | The function stores a pointer to the ID string in this location. |

Remarks Each connection uses a unique client ID.
Client IDs partition the namespace of durable subscribers; see [tibemsSession_CreateDurableSubscriber on page 303](#).

See Also [tibemsConnection_SetClientId on page 222](#)

tibemsConnection_GetExceptionListener

Function

Purpose Get the exception listener of a connection.

C Declaration

```
tibems_status tibemsConnection_GetExceptionListener(  
    tibemsConnection connection,  
    tibemsExceptionCallback* listener,  
    void** closure );
```

Parameters

| Parameter | Description |
|------------|--|
| connection | Get the exception listener of this connection. |
| listener | The function stores a pointer to the exception listener callback in this location. |
| closure | The function stores a pointer to the exception listener closure argument in this location. |

Remarks This is an alternate pathway for alerting a client program of connection problems. The program defines an exception listener callback function, and registers the callback using [tibemsConnection_SetExceptionListener](#). When the client library detects a connection problem, it calls the callback with an exception argument that details the problem.

This call is not available in COBOL.

See Also [tibemsConnection_SetExceptionListener on page 223](#)
[Asynchronous Errors on page 210](#).
[tibemsExceptionCallback on page 233](#)

tibemsConnection_GetMetaData

Function

Purpose Get the metadata from a connection.

C Declaration `tibems_status tibemsConnection_GetMetaData(
tibemsConnection connection,
tibemsConnectionMetaData* metaData);`

COBOL Call `CALL "tibemsConnection_GetMetaData"
USING BY VALUE connection,
BY REFERENCE metaData,
RETURNING tibems-status
END-CALL.`



connection and metaData have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| connection | Get the metadata of this connection. |
| metaData | The function stores a metadata object in this location. |

See Also [tibemsConnectionMetaData on page 227](#)

tibemsConnection_IsDisconnected

Function

Purpose Checks whether the connection has been disconnected.

C Declaration `tibems_status tibemsConnection_IsDisconnected(
tibemsConnection* connection,
tibems_bool* disconnected);`

COBOL Call `CALL "tibemsConnection_IsDisconnected"
USING BY REFERENCE connection,
BY REFERENCE disconnected,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| connection | Get the status of this connection. |
| disconnected | The function stores the connection status in this location. |

Remarks This function gets a value indicating whether the connection is disconnected from the server. If the connection is disconnected from the server, `tibemsConnection_IsDisconnected` sets the the connection status to TRUE. Otherwise, the connection status is FALSE.

That is, if the client has called `tibemsConnection_Close`, or if the connection has been terminated due to a network failure, `tibemsConnection_IsDisconnected` returns TRUE.

tibemsConnection_SetClientId

Function

Purpose Set the client ID of a connection.

C Declaration `tibems_status tibemsConnection_SetClientId(
tibemsConnection connection,
const char* clientId);`

COBOL Call `CALL "tibemsConnection_SetClientId"
USING BY VALUE connection,
BY REFERENCE clientId,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.

Parameters

| Parameter | Description |
|------------|---------------------------------------|
| connection | Set the client ID of this connection. |
| clientId | Set the client ID to this string. |

Remarks Each connection uses a unique client ID.

Client IDs partition the namespace of durable subscribers; see [tibemsSession_CreateDurableSubscriber on page 303](#).

Administrators can configure connection factories to assign client IDs to new connections. Alternatively, administrators can allow client programs to assign their own IDs. If the factory does not assign an ID, the program may set this property. However, it is illegal to overwrite an existing client ID value, and or to set this property after using the connection in any way (for example, after creating a session, or starting the connection); attempting to set this property in these situations results in [TIBEMS_ILLEGAL_STATE](#).

See Also [tibemsConnection_GetClientId on page 218](#)

tibemsConnection_SetExceptionListener

Function

Purpose Set the exception listener for a connection.

C Declaration `tibems_status tibemsConnection_SetExceptionListener(
tibemsConnection connection,
tibemsExceptionCallback listener,
const void* closure);`

COBOL Call `CALL "tibemsConnection_SetExceptionListener_STL"
USING BY VALUE tibemsConnection,
BY REFERENCE tibems-Exception-Status,
BY VALUE TIBEMS-NULLPTR,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.
tibems-Exception-Status has usage binary.

Parameters

| Parameter | Description |
|------------|---|
| connection | Set the exception listener for this connection. |
| listener | Register this exception listener callback. |
| closure | Register this closure argument. |

Remarks This is an alternate pathway for alerting a client program of connection problems. The program defines an exception listener callback function, and calls this function to register the callback and a closure argument. When the client library detects a connection problem, it calls the callback with a status code that identifies the problem.

See Also [tibemsConnection_GetExceptionListener on page 219](#)
[Asynchronous Errors on page 210.](#)
[tibemsExceptionCallback on page 233](#)

tibemsConnection_Start

Function

Purpose Start delivering inbound messages.

C Declaration `tibems_status tibemsConnection_Start(
tibemsConnection connection);`

COBOL Call `CALL "tibemsConnection_Start"
USING BY VALUE connection,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| connection | Start delivering inbound messages on this connection. |

Remarks When a connection is created, it is stopped. It does not deliver inbound messages until the program calls this function to explicitly start it.
If the connection is not stopped, this call has no effect.
Outbound messages flow even before calling start.

See Also [tibemsConnection_Stop on page 225](#)

tibemsConnection_Stop

Function

Purpose Stop delivering inbound messages.

C Declaration `tibems_status tibemsConnection_Stop(
tibemsConnection connection);`

COBOL Call `CALL "tibemsConnection_Stop"
USING BY VALUE connection,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| connection | Stop delivering inbound messages on this connection. |

Remarks

This call temporarily stops the connection from delivering inbound messages. A program can restart delivery by calling `tibemsConnection_Start`.

When a connection is created, it is stopped. It does not deliver inbound messages until the program calls this function to explicitly start it.

If the connection is already stopped, this call has no effect.

Effect

When this call returns, the connection has stopped delivery to all consumers associated with the connection:

- Messages do not arrive to trigger asynchronous message handler events, nor message listeners.
- Synchronous receive functions block. If their timeout intervals expire, they return null.

Blocking

If any message listener or receive call associated with the connection is processing a message when the program calls this function, all facilities of the connection and its sessions remain available to those listeners until they return. In the meantime, this function blocks until that processing completes—that is, until all message listeners and receive calls have returned.

However, the stopped connection prevents the client program from processing any new messages.

Sending

A stopped connection can still send outbound messages.

See Also [tibemsConnection_Start](#) on page 224

tibemsConnectionMetaData

Type

- Purpose**Get information about EMS and the EMS provider.
- Remarks**Functions of type `tibemsConnectionMetaData` retrieve information about the EMS application.

| Function | Description | Page |
|--|---|------|
| tibemsConnectionMetaData_GetEMSMajorVersion | Get information about the JMS specification supported by EMS. | 228 |
| tibemsConnectionMetaData_GetEMSMinorVersion | | |
| tibemsConnectionMetaData_GetEMSVersion | | |
| tibemsConnectionMetaData_GetProviderMajorVersion | Get the version number of the EMS installation. | 230 |
| tibemsConnectionMetaData_GetProviderMinorVersion | | |
| tibemsConnectionMetaData_GetProviderVersion | | |
| tibemsConnectionMetaData_GetEMSProviderName | Get the name of the EMS provider. | 232 |

See Also [tibemsConnection_GetMetaData](#) on page 220

tibemsConnectionMetaData_GetEMS

Function

Purpose Get information about the JMS specification supported by EMS.

C Declaration

```
tibems_status tibemsConnectionMetaData_GetEMSMajorVersion(  
    tibemsConnectionMetaData metaData,  
    tibems_int* majorVersion);  
  
tibems_status tibemsConnectionMetaData_GetEMSMinorVersion(  
    tibemsConnectionMetaData metaData,  
    tibems_int* minorVersion);  
  
tibems_status tibemsConnectionMetaData_GetEMSVersion(  
    tibemsConnectionMetaData metaData,  
    const char** version);
```

COBOL Call

```
CALL "tibemsConnectionMetaData_GetEMSMajorVersion"  
    USING BY VALUE metaData  
          BY REFERENCE majorVersion  
          RETURNING tibems_status  
END-CALL.  
  
CALL "tibemsConnectionMetaData_GetEMSMinorVersion"  
    USING BY VALUE metaData  
          BY REFERENCE minorVersion  
          RETURNING tibems_status  
END-CALL.  
  
CALL "tibemsConnectionMetaData_GetEMSVersion"  
    USING BY VALUE metaData  
          BY REFERENCE version  
          RETURNING tibems_status  
END-CALL.
```



metadata has usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| metaData | The tibemsConnectionMetaData object from which the version number will be extracted. |
| majorVersion | tibemsConnectionMetaData_GetEMSMajorVersion uses this location to store the major version number of the JMS specification supported by the EMS application. |

| Parameter | Description |
|--------------|---|
| minorVersion | tibemsConnectionMetaData_GetEMSMajorVersion uses this location to store the minor version number of the JMS specification supported by the EMS application. |
| version | tibemsConnectionMetaData_GetEMSVersion uses this location to store the version number of the JMS specification supported by the EMS application. |

Remarks EMS applications can retrieve the metaData object from any connection; see [tibemsConnection_GetMetaData](#) on page 220.

tibemsConnectionMetaData_GetProvider

Function

Purpose Get the version number of the EMS installation.

C Declaration

```
tibems_status tibemsConnectionMetaData_GetProviderMajorVersion(  
    tibemsConnectionMetaData metaData,  
    tibems_int* providerMajorVersion);  
  
tibems_status tibemsConnectionMetaData_GetProviderMinorVersion(  
    tibemsConnectionMetaData metaData,  
    tibems_int* providerMinorVersion);  
  
tibems_status tibemsConnectionMetaData_GetProviderVersion(  
    tibemsConnectionMetaData metaData,  
    const char** providerVersion);
```

COBOL Call

```
CALL "tibemsConnectionMetaData_GetProviderMajorVersion"  
    USING BY VALUE metaData  
          BY REFERENCE majorVersion  
          RETURNING tibems_status  
END-CALL.  
  
CALL "tibemsConnectionMetaData_GetProviderMinorVersion"  
    USING BY VALUE metaData  
          BY REFERENCE minorVersion  
          RETURNING tibems_status  
END-CALL.  
  
CALL "tibemsConnectionMetaData_GetProviderVersion"  
    USING BY VALUE metaData  
          BY REFERENCE version  
          RETURNING tibems_status  
END-CALL.
```



metaData and version have usage pointers.

Parameters

| Parameter | Description |
|----------------------|---|
| metaData | The tibemsConnectionMetaData object from which the version number will be extracted. |
| providerMajorVersion | tibemsConnectionMetaData_GetProviderMajorVersion uses this location to store the major version number of the EMS application. |

| Parameter | Description |
|----------------------|---|
| providerMinorVersion | tibemsConnectionMetaData_GetProviderMinorVersion uses this location to store the minor version number of the EMS application. |
| providerVersion | tibemsConnectionMetaData_GetProviderVersion uses this location to store the version number of the EMS application. |

Remarks EMS applications can retrieve the metaData object from any connection; see [tibemsConnection_GetMetaData on page 220](#).

tibemsConnectionMetaData_GetEMSProviderName

Function

Purpose Get the name of the EMS provider.

C Declaration `tibems_status tibemsConnectionMetaData_GetEMSProviderName(
tibemsConnectionMetaData metaData,
const char** providerName);`

COBOL Call `CALL "tibemsConnectionMetaData_GetEMSProviderName"
USING BY VALUE metaData
BY REFERENCE providerName
RETURNING tibems_status
END-CALL.`



metaData has usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| metaData | The object from which the provider name will be extracted. |
| providerName | The location where the provider’s vendor name will be stored. |

Remarks tibemsConnectionMetaData_GetEMSProviderName provides the name of the EMS provider, TIBCO Software Inc.

EMS applications can retrieve the metaData object from any connection; see [tibemsConnection_GetMetaData on page 220](#).

tibemsExceptionCallback

Function Type

Purpose Programs define functions of this type to asynchronously detect problems with connections.

C Declaration

```
typedef void (*tibemsExceptionCallback) (  
    tibemsConnection connection,  
    tibems_status status,  
    void* closure);
```

| Parameters | Parameter | Description |
|------------|------------|--|
| | connection | This parameter receives the connection object. |
| | status | This parameter receives a status code, which identifies the connection problem. |
| | closure | This parameter receives the closure data, which the program supplied in the call that registered the callback. |

Remarks When a program uses a connection to send messages, the send calls can detect problems with the connection, and notify the client program by returning an error status code. However, when a program uses a connection only to receive messages, the client cannot detect errors in this way.

This callback provides an alternate pathway for alerting a client program of connection problems. The program implements this callback, and registers it with the connection object. When the client library detects a connection problem, it calls this callback with a status code that identifies the problem.

See Also [tibemsConnection on page 210](#)
[tibemsConnection_SetExceptionListener on page 223](#)

tibemsMulticastExceptionCallback

Function Type

Purpose Programs define functions of this type to asynchronously detect conditions with EMS multicast that may affect message consumers.

C Declaration

```
typedef void (*tibemsMulticastExceptionCallback) (  
    tibemsConnection connection,  
    tibemsSession session,  
    tibemsMsgConsumer consumer,  
    tibems_status status,  
    const char* description,  
    void* closure);
```

| Parameters | Parameter | Description |
|------------|-------------|--|
| | connection | This parameter receives the connection object. |
| | session | This parameter receives the session object. |
| | consumer | This parameter receives the consumer object. |
| | status | This parameter receives a status code, which identifies the multicast problem. |
| | description | This parameter receives a text description describing the multicast problem. |
| | closure | This parameter receives the closure data, which the program supplied in the call that registered the callback. |

Remarks When a program uses a multicast consumer to receive messages, EMS can detect conditions that may indicate a problem, and notify the client program by returning an error status code. The client application can then take the appropriate action.

This callback provides a pathway for alerting a client program of multicast problems. The program implements this callback and registers it. When the client library detects a multicast problem, it calls this callback and passes it the appropriate EMS objects, a status code that identifies the problem, and a detailed description of the problem. This callback is invoked for each consumer that is affected by the multicast warning or error. Some applications may just simply log the problem; others may take further measures.

See Also [tibems_SetMulticastExceptionListener on page 415](#)
[Chapter 14, Using Multicast](#), in the *TIBCO Enterprise Message Service User’s Guide*

tibemsSSL

Type

Table 12 Functions

| Function | Description | Page |
|--|---|------|
| tibemsSSL_GetTrace | Determine whether SSL tracing is enabled. | 236 |
| tibemsSSL_OpenSSLVersion | Get a string representing the OpenSSL version number. | 237 |
| tibemsSSL_SetTrace | Enable or disable SSL tracing. | 238 |

Table 13 Certificate Encodings

| Constant | Value |
|------------------------------|----------|
| TIBEMS_SSL_ENCODING_AUTO | (0x0000) |
| TIBEMS_SSL_ENCODING_PEM | (0x0001) |
| TIBEMS_SSL_ENCODING_DER | (0x0002) |
| TIBEMS_SSL_ENCODING_BER | (0x0004) |
| TIBEMS_SSL_ENCODING_PKCS7 | (0x0010) |
| TIBEMS_SSL_ENCODING_PKCS8 | (0x0020) |
| TIBEMS_SSL_ENCODING_PKCS12 | (0x0040) |
| TIBEMS_SSL_ENCODING_ENTRUST | (0x0100) |
| TIBEMS_SSL_ENCODING_KEYSTORE | (0x0200) |

tibemsSSL_GetTrace

Function

| | |
|---------------|---|
| Purpose | Determine whether SSL tracing is enabled. |
| C Declaration | <code>tibems_bool tibemsSSL_GetTrace(void);</code> <code>tibems_bool tibemsSSL_GetDebugTrace(void);</code> |
| IBM Systems | This function is not supported on z/OS and IBM i systems. For more information, see SSL Implementation on IBM EBCDIC Systems on page 576 . |
| Remarks | Two levels of SSL tracing are available—regular tracing and debug tracing (more detailed). If tracing is enabled, these calls return TIBEMS_TRUE. If tracing is disabled, they return TIBEMS_FALSE. |

tibemsSSL_OpenSSLVersion

Function

Purpose Get a string representing the OpenSSL version number.

C Declaration

```
const char* tibemsSSL_OpenSSLVersion(  
    char* buffer,  
    tibems_int buf_size );
```

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|--|
| buffer | The function copies the version string in this buffer. |
| buf_size | Length (in bytes) of the buffer. |

Remarks The versions string has the format *major.minor.update*.
A null character terminates the version string.

tibemsSSL_SetTrace

Function

Purpose Enable or disable SSL tracing.

C Declaration

```
void tibemsSSL_SetTrace(  
    tibems_bool trace );  
  
void tibemsSSL_SetDebugTrace(  
    tibems_bool trace );
```

IBM Systems These functions are not supported on IBM z/OS systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-----------|--------------------------------|
| | trace | TIBEMS_TRUE enables tracing. |
| | | TIBEMS_FALSE disables tracing. |

Remarks Two levels of SSL tracing are available—regular tracing and debug tracing (more detailed).

tibemsSSLParams

Type

Purpose Group parameters representing a client identity.

Remarks These parameters apply when creating SSL connections to the EMS server. On most systems, secure connections are created using OpenSSL. Users on IBM z/OS systems must create SSL connections using IBM System SSL. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Function | Description | Page |
|--|--|------|
| tibemsSSLParams_AddIssuerCert | Add one or more issuer certificates to the SSL parameter object. | 240 |
| tibemsSSLParams_AddTrustedCert | Add one or more trusted certificates to the SSL parameter object. | 241 |
| tibemsSSLParams_Create | Create a new SSL parameter object. | 242 |
| tibemsSSLParams_Destroy | Destroy an SSL parameter object. | 243 |
| tibemsSSLParams_GetIdentity | Get the client identity that an SSL parameter object represents. | 244 |
| tibemsSSLParams_GetPrivateKey | Get the private key from an SSL parameter object. | 245 |
| tibemsSSLParams_SetAuthOnly | Limit the use of SSL to improve performance. | 246 |
| tibemsSSLParams_SetCiphers | Set the cipher suites for SSL connections. | 247 |
| tibemsSSLParams_SetExpectedHostName | Set the expected host name. | 248 |
| tibemsSSLParams_SetHostNameVerifier | Set the host name verifier function. | 249 |
| tibemsSSLParams_SetIdentity | Set the identity of the client program. | 250 |
| tibemsSSLParams_SetPrivateKey | Set the client's private key. | 251 |
| tibemsSSLParams_SetRandData tibemsSSLParams_SetRandEGD tibemsSSLParams_SetRandFile | Settings for generating random data. | 252 |
| tibemsSSLParams_SetVerifyHost | Sets flags that enable client verification of the host certificate or host name. | 253 |

tibemsSSLParams_AddIssuerCert

Function

Purpose Add one or more issuer certificates to the SSL parameter object.

C Declaration

```
tibems_status tibemsSSLParams_AddIssuerCert(  
    tibemsSSLParams SSLParams,  
    const void* data,  
    tibems_int size,  
    tibems_int encoding );  
  
tibems_status tibemsSSLParams_AddIssuerCertFile(  
    tibemsSSLParams SSLParams,  
    const char* filename,  
    tibems_int encoding );
```

IBM Systems These functions are not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-----------|--|
| | SSLParams | Add the certificates to this SSL parameter object. |
| | data | Use the certificate data at this location. |
| | size | Length of the certificate data (in bytes). |
| | encoding | Interpret the certificate data using this encoding; for values, see Table 13, Certificate Encodings, on page 235 . |
| | filename | Read the certificate data from this file. |

Remarks Issuer certificates are certificates that authenticate the client’s certificate; the certificate authority (CA) that issued the client’s certificate supplies these. SSL clients must supply them during the SSL handshake, so your program must set them.

If the parameter object already has issuer certificates, this call adds to that set; it does not overwrite them.

tibemsSSLParams_AddTrustedCert

Function

Purpose Add one or more trusted certificates to the SSL parameter object.

C Declaration

```
tibems_status tibemsSSLParams_AddTrustedCert(  
    tibemsSSLParams SSLParams,  
    const void* data,  
    tibems_int size,  
    tibems_int encoding );  
  
tibems_status tibemsSSLParams_AddTrustedCertFile(  
    tibemsSSLParams SSLParams,  
    const char* filename,  
    tibems_int encoding );
```

IBM Systems These functions are not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-----------|--|
| | SSLParams | Add the certificates to this SSL parameter object. |
| | data | Use the certificate data at this location. |
| | size | Length of the certificate data (in bytes). |
| | encoding | Interpret the certificate data using this encoding; for values, see Table 13, Certificate Encodings, on page 235 . |
| | filename | Read the certificate data from this file. |

Remarks Trusted certificates are certificates that authenticate the server’s certificate; the certificate authority (CA) that issued the server’s certificate supplies these. SSL clients may verify them during the SSL handshake; if your program verifies host certificates (see [tibemsSSLParams_SetVerifyHost on page 253](#)), then you must register trusted certificates as well.

If the parameter object already has trusted certificates, this call adds to that set; it does not overwrite them.

tibemsSSLParams_Create

Function

- Purpose** Create a new SSL parameter object.
- C Declaration** `tibemsSSLParams tibemsSSLParams_Create(void);`
- IBM Systems** This function is not supported on z/OS and IBM i systems. See [SSL Implementation on IBM EBCDIC Systems on page 576](#).

tibemsSSLParams_Destroy

Function

Purpose Destroy an SSL parameter object.

C Declaration `void tibemsSSLParams_Destroy(
tibemsSSLParams SSLParams);`

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|------------------------------------|
| SSLParams | Destroy this SSL parameter object. |

tibemsSSLParams_GetIdentity

Function

Purpose Get the client identity that an SSL parameter object represents.

C Declaration `tibems_status tibemsSSLParams_GetIdentity(
tibemsSSLParams SSLParams,
const void** data,
tibems_int* size,
tibems_int* encoding);`

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|--|
| SSLParams | Get the identity from this SSL parameter object. |
| data | The function stores in this location a pointer to the identity data within the <code>tibemsSSLParams</code> object. |
| size | The function stores the length (in bytes) of the identity data in this location. |
| encoding | The function stores the encoding of the identity data in this location; for values, see Table 13, Certificate Encodings, on page 235 . |

Remarks A client identity includes a certificate and private key; it may also include issuer certificates (optional).

tibemsSSLParams_GetPrivateKey

Function

- Purpose

Get the private key from an SSL parameter object.
- C Declaration

```
tibems_status tibemsSSLParams_GetPrivateKey(  
    tibemsSSLParams SSLParams,  
    const void** data,  
    tibems_int* size,  
    tibems_int* encoding );
```
- IBM Systems

This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|---|
| SSLParams | Get the private key from this SSL parameter object. |
| data | The function stores in this location a pointer to the key data within the tibemsSSLParams object. |
| size | The function stores the length (in bytes) of the key data in this location. |
| encoding | The function stores the encoding of the key data in this location; for values, see Table 13, Certificate Encodings, on page 235 . |

tibemsSSLParams_SetAuthOnly

Function

Purpose Limit the use of SSL to improve performance.

C Declaration `tibems_status tibemsSSLParams_SetAuthOnly(
tibemsSSLParams SSLParams,
tibems_bool auth_only);`

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-----------|--|
| | SSLParams | Set the value in this SSL parameter object. |
| | auth_only | TIBEMS_TRUE instructs the SSL parameter object to request a connection that uses SSL only for authentication. TIBEMS_FALSE instructs the SSL parameter object to request a connection that uses SSL to secure all data. |

Remarks For background information, see [SSL Authentication Only on page 518](#) in *TIBCO Enterprise Message Service User's Guide*.

tibemsSSLParams_SetCiphers

Function

Purpose Set the cipher suites for SSL connections.

C Declaration `tibems_status tibemsSSLParams_SetCiphers(
tibemsSSLParams SSLParams,
const char* ciphers);`

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|--|
| SSLParams | Set the value in this SSL parameter object. |
| ciphers | <p>Specify the cipher suites that the client can use.</p> <p>Supply a colon-separated list of cipher names. Names may be either OpenSSL names, or longer descriptive names.</p> <p>For a list of supported cipher suites, see Supported Cipher Suites on page 514 in <i>TIBCO Enterprise Message Service User's Guide</i>.</p> |

tibemsSSLParams_SetExpectedHostName

Function

Purpose Set the expected host name.

C Declaration `tibems_status tibemsSSLParams_SetExpectedHostName(
tibemsSSLParams SSLParams,
const char* expected_hostname);`

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-------------------|---|
| | SSLParams | Set the value in this SSL parameter object. |
| | expected_hostname | Use this value. |

Remarks This parameter applies when establishing an SSL connection to the EMS server. If host name verification is enabled, an application-specific verifier function checks that the actual host name where the server is running is the same as this expected host name.

See Also [tibemsSSLParams_SetHostNameVerifier on page 249](#)
[tibemsSSLParams_SetVerifyHost on page 253](#)
[tibemsSSLHostNameVerifier on page 254](#)

tibemsSSLParams_SetHostNameVerifier

Function

Purpose Set the host name verifier function.

C Declaration

```
tibems_status tibemsSSLParams_SetHostNameVerifier(  
    tibemsSSLParams SSLParams,  
    tibemsSSLHostNameVerifier verifier,  
    const void* closure );
```

IBM Systems This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|---|
| SSLParams | Set the value in this SSL parameter object. |
| verifier | Use this verifier function. |
| closure | Supply application-specific data. Each call to the verifier function passes this data as an argument. |

Remarks When creating a connection to the EMS server, an application-specific verifier function checks that the actual host name where the server is running is the same as this expected host name.

See Also [tibemsSSLParams_SetExpectedHostName on page 248](#)
[tibemsSSLParams_SetVerifyHost on page 253](#)
[tibemsSSLHostNameVerifier on page 254](#)

tibemsSSLParams_SetIdentity

Function

Purpose Set the identity of the client program.

C Declaration

```
tibems_status tibemsSSLParams_SetIdentity(  
    tibemsSSLParams SSLParams,  
    const void* data,  
    tibems_int size,  
    tibems_int encoding );  
  
tibems_status tibemsSSLParams_SetIdentityFile(  
    tibemsSSLParams SSLParams,  
    const char* filename,  
    tibems_int encoding );
```

IBM Systems Thess functions are not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-----------|--|
| | SSLParams | Set the value in this SSL parameter object. |
| | data | Data must include the client’s certificate and private key. It may optionally include issuer certificates. |
| | size | Supply the size (in bytes) of the data. |
| | filename | Read identity data from this file. |
| | encoding | Interpret the certificate data using this encoding; for values, see Table 13, Certificate Encodings, on page 235 . |

tibemsSSLParams_SetPrivateKey

Function

Purpose Set the client's private key.

C Declaration

```
tibems_status tibemsSSLParams_SetPrivateKey(
    tibemsSSLParams SSLParams,
    const void* data,
    tibems_int size,
    tibems_int encoding );

tibems_status tibemsSSLParams_SetPrivateKeyFile(
    tibemsSSLParams SSLParams,
    const char* filename,
    tibems_int encoding );
```

IBM Systems These functions are not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|-----------|--|
| SSLParams | Set the value in this SSL parameter object. |
| data | Private key data. |
| size | Supply the size (in bytes) of the data. |
| filename | Read private key data from this file. |
| encoding | Interpret the data using this encoding; for values, see Table 13, Certificate Encodings, on page 235 . |

tibemsSSLParams_SetRandData

Function

Purpose Settings for generating random data.

C Declaration

```
tibems_status tibemsSSLParams_SetRandData(  
    tibemsSSLParams SSLParams,  
    const char* rand_data,  
    tibems_int size );  
  
tibems_status tibemsSSLParams_SetRandFile(  
    tibemsSSLParams SSLParams,  
    const char* rand_file );  
  
tibems_status tibemsSSLParams_SetRandEGD(  
    tibemsSSLParams SSLParams,  
    const char* rand_egd_path );
```

IBM Systems These functions are not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

Parameters

| Parameter | Description |
|---------------|---|
| SSLParams | Set the value in this SSL parameter object. |
| rand_data | Supply random data as a character string. |
| size | Supply the length (in bytes) of the random data string. |
| rand_file | Read random data from this file. |
| rand_egd_path | Supply the file pathname of an entropy gathering daemon, which generates random data. |

Remarks These three functions represent three ways to inject crucial random data into SSL computations. Every program must select one of these ways. If an entropy gathering daemon is available on the host computer, we recommend using it.

tibemsSSLParams_SetVerifyHost

Function

Purpose Sets flags that enable client verification of the host certificate or host name.

C Declaration

```
tibems_status tibemsSSLParams_SetVerifyHost(  
    tibemsSSLParams SSLParams,  
    tibems_bool verify );  
  
tibems_status tibemsSSLParams_SetVerifyHostName(  
    tibemsSSLParams SSLParams,  
    tibems_bool verify );
```

IBM Systems These functions are not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|-----------|--|
| | SSLParams | Set the value in this SSL parameter object. |
| | verify | TIBEMS_TRUE enables verification. TIBEMS_FALSE disables verification. |

Remarks Both of verification actions are enabled by default (unless a program explicitly disables them).

tibemsSSLParams_SetVerifyHost enables checking that the server host’s certificate was signed by a trusted CA; see [tibemsSSLParams_AddTrustedCert on page 241](#)).

tibemsSSLParams_SetVerifyHostName enables checking the server’s actual host name against an expected server host name; see [tibemsSSLParams_SetExpectedHostName on page 248](#).

See Also [tibemsSSLParams_SetHostNameVerifier on page 249](#)
[tibemsSSLHostNameVerifier on page 254](#)

tibemsSSLHostNameVerifier

Function Type

- Purpose

Programs define functions of this type to check server identity based on the server’s host name.
- C Declaration

```
typedef tibems_status (*tibemsSSLHostNameVerifier) (  
    const char* connected_hostname,  
    const char* expected_hostname,  
    const char* certificate_name,  
    void* closure );
```
- IBM Systems

This function is not supported on z/OS and IBM i systems. For more information, see [SSL Implementation on IBM EBCDIC Systems on page 576](#).

| Parameters | Parameter | Description |
|------------|--------------------|--|
| | connected_hostname | This parameter receives the actual host name of the server to which the client program is attempting to connect. |
| | expected_hostname | This parameter receives the host name that the client expects the server to be running on. |
| | certificate_name | This parameter receives the host name in the server’s public certificate. |
| | closure | This parameter receives application-specific data. |

- Remarks

SSL attempts to verify that the EMS server hostname (taken from the server’s certificate identity) matches the hostname in the server URL. Your program can use the default matching behavior, or customize it in different ways.

 - The default behavior is a straightforward string comparison, matching the hostname from the server certificate against the hostname of the connected URL.
 - If you set an expected hostname, then the match compares the hostname from the server certificate against the expected hostname (instead of the URL hostname).
 - You may also define and set a hostname verifier function, which can override a string mismatch. If the string comparison fails, then SSL calls your verifier function to determine whether to accept the hostname anyway. Your function receives three hostnames—the connected name, the expected name, and the

certificate hostname—and must return a status code indicating the final match result:

- [TIBEMS_OK](#) indicates a successful check.
- [TIBEMS_SECURITY_EXCEPTION](#) indicates a failed check.

See Also [tibemsSSLParams_SetExpectedHostName on page 248](#)
[tibemsSSLParams_SetHostNameVerifier on page 249](#)
[tibemsSSLParams_SetVerifyHost on page 253](#)

Chapter 8 **Connection Factory**

Connection factories let administrators preconfigure client connections to the EMS server.

Topics

- [tibemsConnectionFactory](#), page 258
- [tibemsFactoryLoadBalanceMetric](#), page 291

tibemsConnectionFactory

Type

- Purpose

Administered object for creating server connections.
- Remarks

Connection factories are administered objects. They support concurrent use.
Administrators define connection factories in a repository. Each connection factory has administrative parameters that guide the creation of server connections. Usage follows either of two models:
- EMS Server

You can use the EMS server as a name service provider—one `tibemspd` process provides both the name repository and the message service. Administrators define factories in the name repository. Client programs create connection factory objects with the URL of the repository, and call `tibemsConnectionFactory_CreateConnection`. This function automatically accesses the corresponding factory in the repository, and uses it to create a connection to the message service.

| Function | Description | Page |
|---|---|------|
| tibemsConnectionFactory_Create | Create a connection factory. | 261 |
| tibemsConnectionFactory_CreateConnection | Create a connection object. | 262 |
| tibemsConnectionFactory_CreateXAConnection | Create an XA connection object. | 263 |
| tibemsConnectionFactory_Destroy | Destroy a connection factory object. | 264 |
| tibemsConnectionFactory_GetSSLProxyHost | Get the SSL proxy host from a connection factory. | 265 |
| tibemsConnectionFactory_GetSSLProxyPort | Get the SSL proxy port from a connection factory. | 266 |
| tibemsConnectionFactory_GetSSLProxyUser | Get the SSL proxy username from a connection factory. | 267 |
| tibemsConnectionFactory_GetSSLProxyPassword | Get the SSL proxy password from a connection factory. | 268 |

| Function | Description | Page |
|--|--|------|
| tibemsConnectionFactory_Print | Print the parameters set in a connection factory object. | 269 |
| tibemsConnectionFactory_PrintToBuffer | Print the parameters set in a connection factory object to a buffer. | 270 |
| tibemsConnectionFactory_SetClientID | Set the client ID of a connection factory object. | 271 |
| tibemsConnectionFactory_SetConnectAttemptCount | Modify the connection attempts setting. | 272 |
| tibemsConnectionFactory_SetConnectAttemptDelay | Modify the connection delay setting. | 273 |
| tibemsConnectionFactory_SetConnectAttemptTimeout | Modify the connection timeout setting. | 274 |
| tibemsConnectionFactory_SetMetric | Modify the load balancing metric. | 275 |
| tibemsConnectionFactory_SetMulticastDaemon | Sets the port on which the client will connect to the multicast daemon. | 276 |
| tibemsConnectionFactory_SetMulticastEnabled | Set whether message consumers subscribed to multicast-enabled topics will receive messages over multicast. | 277 |
| tibemsConnectionFactory_SetPkPassword | Set the SSL private key password for the connection factory. | 278 |
| tibemsConnectionFactory_SetReconnectAttemptCount | Modify the reconnection attempts setting. | 279 |
| tibemsConnectionFactory_SetReconnectAttemptDelay | Modify the reconnection delay setting. | 280 |

| Function | Description | Page |
|--|---|------|
| tibemsConnectionFactory_SetReconnectAttemptTimeout | Modify the reconnection timeout setting. | 281 |
| tibemsConnectionFactory_SetServerURL | Set the server URL. | 282 |
| tibemsConnectionFactory_SetSSLParams | Set a connection factory's default SSL parameters. | 283 |
| tibemsConnectionFactory_SetSSLProxy | Set a connection factory's parameters for connecting through an SSL proxy. | 284 |
| tibemsConnectionFactory_SetSSLProxyAuth | Set a connection factory's username and password for connecting through an SSL proxy. | 285 |
| tibemsConnectionFactory_SetUserName | Set a connection factory's username. | 286 |
| tibemsConnectionFactory_SetUserPassword | Set the password used by the connection factory to authenticate itself with the EMS Server. | 287 |
| tibemsUFOConnectionFactory_Create | Create an unshared state connection factory. | 288 |
| tibemsUFOConnectionFactory_CreateFromConnectionFactory | Create an unshared state connection factory from a normal connection factory. | 289 |
| tibemsUFOConnectionFactory_RecoverConnection | Recover an unshared state connection. | 290 |

Administered Objects Administered objects let administrators configure EMS behavior at the enterprise level. Administrators define these objects, and client programs use them. This arrangement relieves program developers and end users of the responsibility for correct configuration.

See Also [tibemsLookupContext](#) on page 334

tibemsConnectionFactory_Create

Function

Purpose Create a connection factory.

C Declaration `tibemsConnectionFactory tibemsConnectionFactory_Create(void);`

COBOL Call CALL "tibemsConnectionFactory_Create"
RETURNING factory
END-CALL.



factory has usage pointer.

Remarks The resulting connection factory object is empty. This call does not attempt to access the repository (see also [tibemsLookupContext on page 334](#)).

See Also [tibemsLookupContext on page 334](#)

tibemsConnectionFactory_CreateConnection

Function

Purpose Create a connection object.

C Declaration `tibems_status tibemsConnectionFactory_CreateConnection(
tibemsConnectionFactory factory,
tibemsConnection* connection,
const char * username,
const char * password);`

COBOL Call `CALL "tibemsConnectionFactory_CreateConnection"
USING BY VALUE factory,
BY REFERENCE connection,
BY REFERENCE username,
BY REFERENCE password,
RETURNING tibems-status
END-CALL.`



factory and connection have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| factory | Use this connection factory to create a connection. |
| connection | The function stores the new connection object in this location. |
| userName | The connection object presents this user identity to the server. Set to NULL if the server isn't authenticating or authorizing users. |
| password | The connection object authenticates the user identity with this password. Set to NULL if the server isn't authenticating or authorizing users. |

Remarks When the identity parameters are null, the connection object presents a default user identity. If the server configuration permits that anonymous user, then the call succeeds.

See Also [tibemsConnection on page 210](#)

tibemsConnectionFactory_CreateXAConnection

Function

Purpose Create an XA connection object.

C Declaration

```
extern tibems_status
tibemsConnectionFactory_CreateXAConnection(
    tibemsConnectionFactory factory,
    tibemsConnection* connection,
    const char* username,
    const char* password);
```

COBOL Call

```
CALL "tibemsConnectionFactory_CreateXAConnection"
    USING BY VALUE factory,
          BY REFERENCE connection,
          BY REFERENCE username,
          BY REFERENCE password,
          RETURNING tibems-status
END-CALL.
```



factory and connection have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| factory | Use this connection factory to create a connection. |
| connection | The function stores the new connection object in this location. |
| userName | The connection object presents this user identity to the server. Set to NULL if the server isn't authenticating or authorizing users. |
| password | The connection object authenticates the user identity with this password. Set to NULL if the server isn't authenticating or authorizing users. |

Remarks When the identity parameters are null, the connection object presents a default user identity. If the server configuration permits that anonymous user, then the call succeeds.

See Also [tibemsConnection on page 210](#)

tibemsConnectionFactory_Destroy

Function

Purpose Destroy a connection factory object.

C Declaration `tibems_status tibemsConnectionFactory_Destroy(
tibemsConnectionFactory factory)`

COBOL Call `CALL "tibemsConnectionFactory_Destroy"
USING BY VALUE factory,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|----------------------------------|
| factory | Destroy this connection factory. |

Remarks This call destroys an object within the program. It does not affect objects in the repository.

tibemsConnectionFactory_GetSSLProxyHost

Function

Purpose Get the SSL proxy host from a connection factory.

C Declaration `tibems_status tibemsConnectionFactory_GetSSLProxyHost(
tibemsConnectionFactory factory,
const char** proxy_host);`

COBOL Call `CALL "tibemsConnectionFactory_GetSSLProxyHost"
USING BY VALUE factory,
BY REFERENCE proxy-host,
RETURNING tibems-status
END-CALL.`



factory and proxy-host have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| factory | Get the SSL proxy host from this connection factory. |
| proxy_host | The function stores the proxy host in this location. |

See Also [tibemsConnectionFactory_SetSSLProxy on page 284](#)

tibemsConnectionFactory_GetSSLProxyPort

Function

Purpose Get the SSL proxy port from a connection factory.

C Declaration `tibems_status tibemsConnectionFactory_GetSSLProxyPort(
tibemsConnectionFactory factory,
tibems_int* proxy_port);`

COBOL Call `CALL "tibemsConnectionFactory_GetSSLProxyPort"
USING BY VALUE factory,
BY REFERENCE proxy-port,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| factory | Get the SSL proxy port number from this connection factory. |
| proxy_port | The function stores the proxy port in this location. |

See Also [tibemsConnectionFactory_SetSSLProxy](#) on page 284

tibemsConnectionFactory_GetSSLProxyUser

Function

Purpose Get the SSL proxy username from a connection factory.

C Declaration `tibems_status tibemsConnectionFactory_GetSSLProxyUser(
tibemsConnectionFactory factory,
const char** proxy_user);`

COBOL Call `CALL "tibemsConnectionFactory_GetSSLProxyUser"
USING BY VALUE factory,
BY REFERENCE proxy-user,
RETURNING tibems-status
END-CALL.`



factory and proxy-user have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| factory | Get the SSL proxy username from this connection factory. |
| proxy_user | The function stores the proxy user name in this location. |

See Also [tibemsConnectionFactory_SetSSLProxyAuth on page 285](#)

tibemsConnectionFactory_GetSSLProxyPassword

Function

Purpose Get the SSL proxy password from a connection factory.

C Declaration `tibems_status tibemsConnectionFactory_GetSSLProxyPassword(
tibemsConnectionFactory factory,
const char** proxy_password);`

COBOL Call `CALL "tibemsConnectionFactory_GetSSLProxyPassword"
USING BY VALUE factory,
BY REFERENCE proxy-password,
RETURNING tibems-status
END-CALL.`



factory and proxy-password have usage pointer.

Parameters

| Parameter | Description |
|----------------|--|
| factory | Get the SSL proxy password from this connection factory. |
| proxy_password | The function stores the proxy password in this location. |

See Also [tibemsConnectionFactory_SetSSLProxyAuth on page 285](#)

tibemsConnectionFactory_Print

Function

Purpose Print the parameters set in a connection factory object.

C Declaration `tibems_status tibemsConnectionFactory_Print(
tibemsConnectionFactory factory);`

COBOL Call `CALL "tibemsConnectionFactory_Print"
USING BY VALUE factory,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| factory | Print the parameters set in this connection factory. |

See Also [tibemsConnectionFactory_PrintToBuffer on page 270](#)

tibemsConnectionFactory_PrintToBuffer

Function

Purpose Print the parameters set in a connection factory object to a buffer.

C Declaration

```
extern tibems_status tibemsConnectionFactory_PrintToBuffer(  
    tibemsConnectionFactory factory,  
    char* buffer,  
    tibems_int maxlen);
```

COBOL Call

```
CALL "tibemsConnectionFactory_PrintToBuffer"  
    USING BY VALUE factory,  
          BY REFERENCE buffer,  
          BY VALUE maxlen  
    RETURNING tibems-status  
END-CALL.
```



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| factory | Print the parameters set in this connection factory. |
| buffer | Location to store the string representation of the connection factory. |
| maxlen | The size of the buffer. |

See Also [tibemsConnectionFactory_Print on page 269](#)

tibemsConnectionFactory_SetClientID

Function

Purpose Set the client ID of a connection factory object.

C Declaration `tibems_status tibemsConnectionFactory_SetClientID(
tibemsConnectionFactory factory,
const char* cid);`

COBOL Call `CALL "tibemsConnectionFactory_SetClientID"
USING BY VALUE factory,
BY REFERENCE cid,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the client ID of this connection factory. |
| type | Set the ID to this string. |

Remarks A client ID string lets the server associate a client-specific factory with each client program. When such a factory already exists, the server supplies that factory to the client. If a factory does not yet exist for the client, the server creates one, and stores it for future use by that specific client.

tibemsConnectionFactory_SetConnectAttemptCount

Function

Purpose Modify the connection attempts setting.

C Declaration `tibems_status tibemsConnectionFactory_SetConnectAttemptCount(
tibemsConnectionFactory factory,
tibems_int connAttempts);`

COBOL Call `CALL "tibemsConnectionFactory_SetConnectAttemptCount"
USING BY VALUE factory,
BY VALUE connAttempts,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| factory | Set the connection attempts parameter of this connection factory. |
| connAttempts | This value limits the number of times that a connection object attempts to establish a connection to the server. The minimum value is 1. When this property is not set, the default value is 2. |

See Also [tibemsConnectionFactory_SetConnectAttemptDelay on page 273](#)
[tibemsConnectionFactory_SetConnectAttemptTimeout on page 274](#)
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibemsConnectionFactory_SetConnectAttemptDelay

Function

Purpose Modify the connection delay setting.

C Declaration `tibems_status tibemsConnectionFactory_SetConnectAttemptDelay(
tibemsConnectionFactory factory,
tibems_int delay);`

COBOL Call `CALL "tibemsConnectionFactory_SetConnectAttemptDelay"
USING BY VALUE factory,
BY VALUE delay,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the connection delay parameter of this connection factory. |
| delay | This value determines the time (in milliseconds) between connection attempts. The minimum value is 250. When this property is not set, the default value is 500. |

See Also [tibemsConnectionFactory_SetConnectAttemptCount on page 272](#)
[tibemsConnectionFactory_SetConnectAttemptTimeout on page 274](#)
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibemsConnectionFactory_SetConnectAttemptTimeout

Function

- Purpose

Modify the connection timeout setting.
- C Declaration

`tibems_status tibemsConnectionFactory_SetConnectAttemptTimeout(
tibemsConnectionFactory factory,
tibems_int timeout);`
- COBOL Call

`CALL "tibemsConnectionFactory_SetConnectAttemptTimeout"
USING BY VALUE factory,
BY VALUE timeout,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the connection timeout parameter of this connection factory. |
| timeout | <p>This value determines the maximum time (in milliseconds) the client will wait for a connection to the server to be established.</p> <p>The minimum permitted timeout is 100 milliseconds. However, under stress conditions, this minimum may be too low to enable reliable connection creation. In such cases, a value of greater than 1000 is suggested. Zero is a special value, which specifies no timeout.</p> <p>When this property is not set, the default value is 0.</p> |

See Also

[tibemsConnectionFactory_SetConnectAttemptCount](#) on page 272
[tibemsConnectionFactory_SetConnectAttemptDelay](#) on page 273
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibemsConnectionFactory_SetMetric

Function

Purpose Modify the load balancing metric.

C Declaration `tibems_status tibemsConnectionFactory_SetMetric(
tibemsConnectionFactory factory,
tibemsFactoryLoadBalanceMetric metric);`

COBOL Call `CALL "tibemsConnectionFactory_SetMetric"
USING BY VALUE factory,
BY VALUE metric,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the load balancing metric of this connection factory. |
| metric | Use this metric. |

Remarks When the connection factory balances the client load among several servers, it uses this metric to determine the least loaded server, so the connection factory can create a connection to it. For values, see [tibemsFactoryLoadBalanceMetric on page 291](#).

tibemsConnectionFactory_SetMulticastDaemon

Function

Purpose Sets the port on which the client will connect to the multicast daemon.

C Declaration `tibems_status tibemsConnectionFactory_SetMulticastDaemon(
tibemsConnectionFactory factory,
const char* multicastDaemon);`

Parameters

| Parameter | Description |
|-----------------|---|
| factory | Set the multicast daemon for this connection factory. |
| multicastDaemon | The port number for the multicast daemon that connections created using this factory will connect to. |

Remarks A connection to the multicast daemon is required when multicast is enabled and a consumer is subscribed to a multicast-enabled topic. Setting the port with this method will override the default port supplied by the server.

See Also [tibemsConnectionFactory_SetMulticastEnabled on page 277](#)
[tibems_SetMulticastDaemon on page 413](#)

tibemsConnectionFactory_SetMulticastEnabled

Function

Purpose Set whether message consumers subscribed to multicast-enabled topics will receive messages over multicast.

C Declaration `tibems_status tibemsConnectionFactory_SetMulticastEnabled(
tibemsConnectionFactory factory,
tibems_bool multicastEnabled);`

| Parameters | Parameter | Description |
|------------|------------------|--|
| | factory | Enable or disable multicast capabilities for connections created by this factory |
| | multicastEnabled | When true, multicast is enabled. When false, multicast is disabled. |

Remarks When enabled, message consumers using a connection created by this factory, and which are subscribed to a multicast-enabled topic will receive messages over multicast. The default is enabled.

See Also [tibemsConnectionFactory_SetMulticastDaemon on page 276](#)
[tibems_SetMulticastEnabled on page 414](#)
[multicast](#) and [multicast_daemon_default](#) server parameters in the *TIBCO Enterprise Message Service User's Guide*

tibemsConnectionFactory_SetPkPassword

Function

Purpose Set the SSL private key password for the connection factory.

C Declaration extern [tibems_status](#) tibemsConnectionFactory_SetPkPassword(
 [tibemsConnectionFactory](#) factory,
 const char* pk_password);

COBOL Call CALL "tibemsConnectionFactory_SetPkPassword"
 USING BY VALUE factory,
 BY REFERENCE pk-password,
 RETURNING tibems-status
 END-CALL.



factory has usage pointer.
On IBM z/OS systems, the pk-password must always be a null value.

Parameters

| Parameter | Description |
|-------------|---|
| factory | Set the SSL password for this connection factory. |
| pk_password | Connections created by the connection factory decode their SSL private key using this password when establishing SSL communication. |

Remarks It is an error to call this function on a connection factory for which an [tibemsSSLParams](#) struct is not yet set.

Notice that this SSL private key encryption password is distinct from the server authentication password, and from the proxy authentication password.

See Also [tibemsSSLParams](#) on page 239
[tibemsConnectionFactory_SetSSLParams](#) on page 283

tibemsConnectionFactory_SetReconnectAttemptCount

Function

Purpose Modify the reconnection attempts setting.

C Declaration `tibems_status tibemsConnectionFactory_SetReconnectAttemptCount(
tibemsConnectionFactory factory,
tibems_int connAttempts);`

COBOL Call `CALL "tibemsConnectionFactory_SetReconnectAttemptCount"
USING BY VALUE factory,
BY VALUE connAttempts,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| factory | Set the reconnection attempts parameter of this connection factory. |
| connAttempts | This value limits the number of times that a connection object attempts to reestablish a connection to the server. The minimum value is 1. When this property is not set, the default value is 4. |

See Also [tibemsConnectionFactory_SetReconnectAttemptDelay on page 280](#)
[tibemsConnectionFactory_SetReconnectAttemptTimeout on page 281](#)

[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibemsConnectionFactory_SetReconnectAttemptDelay

Function

Purpose Modify the reconnection delay setting.

C Declaration `tibems_status tibemsConnectionFactory_SetReconnectAttemptDelay(
tibemsConnectionFactory factory,
tibems_int delay);`

COBOL Call `CALL "tibemsConnectionFactory_SetReconnectAttemptDelay"
USING BY VALUE factory,
BY VALUE delay,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the reconnection delay parameter of this connection factory. |
| delay | This value determines the time (in milliseconds) between reconnection attempts. The minimum value is 250. When this property is not set, the default value is 500. |

See Also [tibemsConnectionFactory_SetReconnectAttemptCount on page 279](#)
[tibemsConnectionFactory_SetReconnectAttemptTimeout on page 281](#)

[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibemsConnectionFactory_SetReconnectAttemptTimeout

Function

Purpose Modify the reconnection timeout setting.

C Declaration `tibems_status tibemsConnectionFactory_SetReconnectAttemptTimeout(
tibemsConnectionFactory factory,
tibems_int timeout);`

COBOL Call `CALL "tibemsConnectionFactory_SetReconnectAttemptTimeout"
USING BY VALUE factory,
BY VALUE timeout,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| factory | Set the reconnection timeout parameter of this connection factory. |
| timeout | This value determines the maximum time (in milliseconds) a client will wait for the reconnection to be established. Zero is a special value, which specifies no timeout. When this property is not set, the default value is 0. |

See Also [tibemsConnectionFactory_SetReconnectAttemptCount on page 279](#)
[tibemsConnectionFactory_SetReconnectAttemptDelay on page 280](#)

[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibemsConnectionFactory_SetServerURL

Function

Purpose Set the server URL.

C Declaration `tibems_status tibemsConnectionFactory_SetServerURL(
tibemsConnectionFactory factory,
const char* url);`

COBOL Call `CALL "tibemsConnectionFactory_SetServerURL"
USING BY VALUE factory,
BY REFERENCE url,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the server URL of this connection factory. |
| url | The factory object contacts the EMS server at this URL, to access a corresponding factory defined by the administrator. |

Reconnect and Fault Tolerance

To enable reconnection behavior and fault tolerance, the connection factory’s server URL parameter must be a comma-separated list of two or more URLs. To enable client reconnection in a situation with only one server, you may supply two copies of that server’s URL (for example, `tcp://localhost:7222,tcp://localhost:7222`).

Note that `tibemsConnectionFactory_SetServerURL` can be used to set the server URL for a connection factory only once. If the URL has previously been set for the connection factory, `tibemsConnectionFactory_SetServerURL` returns the status code `TIBEMS_EXCEPTION`.

When specifying an IPv6 address, use square brackets around the address specification. For example, `tcp://[2001:cafe::107]:7222`.

tibemsConnectionFactory_SetSSLParams

Function

Purpose Set a connection factory’s default SSL parameters.

C Declaration `tibems_status tibemsConnectionFactory_SetSSLParams(
tibemsConnectionFactory factory,
tibemsSSLParams sslparams);`

COBOL Call `CALL "tibemsConnectionFactory_SetSSLParams"
USING BY VALUE factory,
BY VALUE sslparams,
RETURNING tibems-status
END-CALL.`



factory and sslparams have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| factory | Set the default SSL parameters of this connection factory. |
| sslParams | The connection establishes SSL communication using these parameters. |

See Also [tibemsSSLParams on page 239](#)
[tibemsConnectionFactory_CreateConnection on page 262](#)

tibemsConnectionFactory_SetSSLProxy

Function

Purpose Set a connection factory’s parameters for connecting through an SSL proxy.

C Declaration `tibems_status tibemsConnectionFactory_SetSSLProxy(
tibemsConnectionFactory factory,
const char* proxy_host,
tibems_int proxy_port);`

COBOL Call `CALL "tibemsConnectionFactory_SetSSLProxy"
USING BY VALUE factory,
BY REFERENCE proxy-host,
BY VALUE proxy-port,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| factory | Set the SSL proxy host and port on this connection factory. |
| proxy_host | The connection factory establishes SSL communication through a web proxy at this host. Supply a simple hostname, a fully qualified hostname with domain name, or an IP address (dot notation). |
| proxy_port | The connection factory establishes SSL communication through a web proxy on this port. |

Remarks An SSL proxy lets an EMS application create an SSL connection to an EMS server, even though a firewall separates the application from the server. The proxy usually runs within the firewall’s DMZ.

A connection factory contacts the SSL proxy, requesting an SSL connection to the server. The proxy authenticates the application program, and mediates the initial SSL negotiation between application and server. After the SSL connection is established, the application and server use it to communicate directly with one another.

See Also [tibemsConnectionFactory_GetSSLProxyHost on page 265](#)
[tibemsConnectionFactory_GetSSLProxyPort on page 266](#)
[tibemsConnectionFactory_SetSSLProxyAuth on page 285](#)

tibemsConnectionFactory_SetSSLProxyAuth

Function

Purpose Set a connection factory’s username and password for connecting through an SSL proxy.

C Declaration

```
tibems_status
tibemsConnectionFactory_SetSSLProxyAuth(
    tibemsConnectionFactory factory,
    const char* proxy_user,
    const char* proxy_password);
```

COBOL Call

```
CALL "tibemsConnectionFactory_SetSSLProxy"
    USING BY VALUE factory,
          BY REFERENCE proxy-user,
          BY REFERENCE proxy-password,
          RETURNING tibems-status
END-CALL.
```



factory has usage pointer.

Parameters

| Parameter | Description |
|----------------|---|
| factory | Set the username and password on this connection factory. |
| proxy_user | The connection factory authenticates itself to the SSL proxy using this username. |
| proxy_password | The connection factory authenticates itself to the SSL proxy using this password. |

Remarks When a connection factory establishes an EMS server connection through an SSL proxy host, the proxy might first require authentication before facilitating a connection. When required, use this call to set that authentication data on the connection factory. Notice that this proxy authentication data is distinct from the server authentication data, and from the SSL private key encryption password.

See Also [tibemsConnectionFactory_GetSSLProxyUser on page 267](#)
[tibemsConnectionFactory_GetSSLProxyPassword on page 268](#)
[tibemsConnectionFactory_SetSSLProxy on page 284](#)

tibemsConnectionFactory_SetUserName

Function

Purpose Set a connection factory’s username.

C Declaration `tibems_status
tibemsConnectionFactory_SetUserName(
tibemsConnectionFactory factory,
const char* username);`

COBOL Call `CALL "tibemsConnectionFactory_SetUserName"
USING BY VALUE factory,
BY REFERENCE username,
RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| factory | Set the username on this connection factory. |
| username | The connection factory identifies itself using this username. |

Remarks When a connection factory establishes an EMS server connection, the EMS server requests identification. Use this call to set the username that the connection factory uses to identify itself to the EMS server. Notice that this server authentication data is different from SSL authentication data.

See Also [tibemsConnectionFactory_SetUserPassword on page 287](#)

tibemsConnectionFactory_SetUserPassword

Function

Purpose Set the password used by the connection factory to authenticate itself with the EMS Server.

C Declaration `tibems_status
tibemsConnectionFactory_SetUserPassword(
 tibemsConnectionFactory factory,
 const char* password);`

COBOL Call `CALL "tibemsConnectionFactory_SetUserPassword"
 USING BY VALUE factory,
 BY REFERENCE password,
 RETURNING tibems-status
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| factory | Set the password on this connection factory. |
| password | The connection factory authenticates itself using this password. |

Remarks When a connection factory establishes an EMS server connection, the EMS server requests authentication. Use this call to set the password that the connection factory uses to authenticate itself with the EMS server. Notice that this server authentication data is different from SSL authentication data.

See Also [tibemsConnectionFactory_SetUserName on page 286](#)

tibemsUFOConnectionFactory_Create

Function

Purpose Create an unshared state connection factory.

C Declaration `tibemsConnectionFactory tibemsUFOConnectionFactory_Create(void);`

COBOL Call `CALL "tibemsUFOConnectionFactory_Create"
RETURNING factory
END-CALL.`



factory has usage pointer.

Remarks The resulting unshared state connection factory object is empty. This call does not attempt to access the repository (see also [tibemsLookupContext on page 334](#)).

See Also [tibemsLookupContext on page 334](#)

tibemsUFOConnectionFactory_CreateFromConnectionFactory

Function

Purpose Create an unshared state connection factory from a normal connection factory.

C Declaration `tibemsConnectionFactory
tibemsUFOConnectionFactory_CreateFromConnectionFactory(
 tibemsConnectionFactory emsFactory);`

COBOL Call `CALL "tibemsUFOConnectionFactory_CreateFromConnectionFactory"
 USING BY VALUE emsFactory
 RETURNING facory
END-CALL.`



factory has usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| emsFactory | Connections created by this unshared state connection factory connect to a server in the URL list of this connection factory. |

See Also [tibemsUFOConnectionFactory_Create on page 288](#)

tibemsUFOConnectionFactory_RecoverConnection

Function

Purpose Recover an unshared state connection.

C Declaration

```
tibems_status
tibemsUFOConnectionFactory_RecoverConnection(
    tibemsConnectionFactory ufoFactory,
    tibemsConnection ufoConnection);
```

COBOL Call

```
CALL "tibemsUFOConnectionFactory_RecoverConnection"
    USING BY VALUE ufoFactory,
          BY VALUE ufoConnection,
          RETURNING tibems-status
END-CALL.
```



ufoConnection has usage pointer.

Parameters

| Parameter | Description |
|---------------|---|
| ufoFactory | The unshared state connection factory used to create the unshared state connection. |
| ufoConnection | The unshared state connection to be recovered. |

Remarks This function is used to recover the broken connection on another available server.

See Also See the section Unshared State Failover Process in the *TIBCO Enterprise Message Service User's Guide* for more information.

tibemsFactoryLoadBalanceMetric

Type

- Purpose** Define enumerated load balancing constants.
- Remarks** When a connection factory balances the client load among several servers, it uses this metric to determine the least loaded server, so the connection factory can create a connection to it.

| Constant | Description |
|--|--|
| TIBEMS_FACTORY_LOAD_BALANCE_METRIC_NONE | Indicates absence of any load balancing metric. |
| TIBEMS_FACTORY_LOAD_BALANCE_METRIC_CONNECTIONS | The connection factory balances the connection load among several servers by creating a connection to the server with the fewest number of connections. |
| TIBEMS_FACTORY_LOAD_BALANCE_METRIC_BYTE_RATE | The connection factory balances the connection load among several servers by creating a connection to the server with the lowest total byte rate (input and output). |

```
COBOL      * NOTE:  LBM is an acronym for LOAD-BALANCE-METRIC
           01  TIBEMS-FACTORY-LBM-TYPES.
               05  tibemsFactoryLoadBalanceMetric      PIC S9(8) BINARY.
                   88  TIBEMS-FACTORY-LBM-NONE              VALUE 0.
                   88  TIBEMS-FACTORY-LBM-CONNECTIONS      VALUE 1.
                   88  TIBEMS-FACTORY-LBM-BYTE-RATE        VALUE 2.
```

See Also [tibemsConnectionFactory on page 258](#)
 [tibemsConnectionFactory_SetMetric on page 275](#)

Chapter 9 **Session**

A session is a single-threaded context for producing and consuming messages.

Topics

- [tibemsSession](#), page 294
- [tibemsAcknowledgeMode](#), page 324

tibemsSession

Type

| | |
|--------------------|--|
| Purpose | Organizing context for message activity. |
| Remarks | <div>Sessions combine several roles:<ul style="list-style-type: none">• Create message producers and consumers• Create message objects• Create temporary destinations• Create dynamic destinations• Create queue browsers• Serialize for inbound and outbound messages• Serialize for asynchronous message events (or message listeners) of its consumer objects• Cache inbound messages (until the program acknowledges them).• Transaction support (when enabled).</div> |
| Single Thread | The JMS specification restricts programs to use each session within a single thread. |
| Associated Objects | The same single-thread restriction applies to objects associated with a session—namely, messages, message consumers, durable subscribers, message producers, queue browsers, and temporary destinations (however, static and dynamic destinations are exempt from this restriction). |
| Corollary | One consequence of this rule is that all the consumers of a session must deliver messages in the same mode—either synchronously or asynchronously. |
| Asynchronous | In asynchronous delivery, the program registers message handler events or message listeners with the session’s consumer objects. An internal dispatcher thread delivers messages to those event handlers or listeners (in all the session’s consumer objects). No other thread may use the session (nor objects created by the session). |
| Synchronous | In synchronous delivery, the program explicitly begins a thread for the session. That thread processes inbound messages and produces outbound messages, serializing this activity among the session’s producers and consumers. Functions that request the next message (such as <code>tibemsMsgConsumer_Receive</code>) can organize the thread’s activity. |

Close The only exception to the rule restricting session calls to a single thread is the function `tibemsSession_Close`; programs can call `Close` from any thread at any time.

Transactions A session has either transaction or non-transaction semantics. When a program specifies transaction semantics, the session object cooperates with the server, and all messages that flow through the session become part of a transaction.

- When the program calls `tibemsSession_Commit`, the session acknowledges all inbound messages in the current transaction, and the server delivers all outbound messages in the current transaction to their destinations.
- If the program calls `tibemsSession_Rollback`, the session recovers all inbound messages in the current transaction (so the program can consume them in a new transaction), and the server destroys all outbound messages in the current transaction.


After these actions, both `Commit` and `Rollback` immediately begin a new transaction.

| Function | Description | Page |
|--|------------------------------------|------|
| Messages | | |
| <code>tibemsSession_CreateBytesMessage</code> | Create a byte array message. | 300 |
| <code>tibemsSession_CreateMapMessage</code> | Create a map message. | 306 |
| <code>tibemsSession_CreateStreamMessage</code> | Create a stream message. | 313 |
| <code>tibemsSession_CreateTextMessage</code> | Create a text message. | 316 |
| Destinations | | |
| <code>tibemsSession_CreateBrowser</code> | Create a queue browser. | 299 |
| <code>tibemsSession_CreateTemporaryQueue</code> | Create a temporary queue. | 314 |
| <code>tibemsSession_CreateTemporaryTopic</code> | Create a temporary topic. | 315 |
| Consumers & Producers | | |
| <code>tibemsSession_CreateConsumer</code> | Create a message consumer. | 301 |
| <code>tibemsSession_CreateDurableSubscriber</code> | Create a durable topic subscriber. | 303 |
| <code>tibemsSession_CreateProducer</code> | Create a message producer. | 308 |

| Function | Description | Page |
|--|--|------|
| <code>tibemsSession_CreateSharedConsumer</code> | Create a shared consumer. | 309 |
| <code>tibemsSession_CreateSharedDurableConsumer</code> | Create a shared durable consumer. | 311 |
| <code>tibemsSession_Unsubscribe</code> | Unsubscribe a durable topic subscription. | 323 |
| Transactions | | |
| <code>tibemsSession_Commit</code> | Commit the open transaction. | 298 |
| <code>tibemsSession_Rollback</code> | Roll back messages in the current transaction. | 322 |
| Other | | |
| <code>tibemsSession_Close</code> | Close a session; reclaim resources. | 297 |
| <code>tibemsSession_Recover</code> | Recover from undetermined state during message processing. | 321 |

tibemsSession_Close

Function

| | |
|---|--|
| Purpose | Close a session; reclaim resources. |
| C Declaration | <code>tibems_status tibemsSession_Close(tibemsSession session);</code> |
| COBOL Call | <code>CALL "tibemsSession_Close" USING BY VALUE session, RETURNING tibems-status END-CALL.</code> |
|  | session has usage pointer. |
| Remarks | Closing a session automatically closes its consumers (except for durable subscribers), producers and browsers. |
| Blocking | If any message listener or receive call associated with the session is processing a message when the program calls this function, all facilities of the connection and its sessions remain available to those listeners until they return. In the meantime, this function blocks until that processing completes—that is, until all message listeners and receive calls have returned. |
| Transactions | Closing a session rolls back the open transaction in the session. |

tibemsSession_Commit

Function

Purpose


Commit the open transaction.

C Declaration

`tibems_status tibemsSession_Commit(
 tibemsSession session);`

COBOL Call

`CALL "tibemsSession_Commit"
 USING BY VALUE session,
 RETURNING tibems-status
END-CALL.`



session has usage pointer.

Remarks

A session (with transaction semantics) always has exactly one open transaction. Message operations associated with the session become part of that transaction. This call commits all the messages within the transaction, and releases any locks. Then it opens a new transaction.

| Status Code | Description |
|-----------------------------|---|
| TIBEMS_OK | Successful commit. |
| TIBEMS_ILLEGAL_STATE | The session does not have transaction semantics. |
| TIBEMS_SECURITY_EXCEPTION | The client lacks permission to send one of messages in the transaction. |
| TIBEMS_TRANSACTION_FAILED | Commit failed and the server automatically rolled back the transaction. |
| TIBEMS_TRANSACTION_ROLLBACK | |

tibemsSession_CreateBrowser

Function

Purpose Create a queue browser.

C Declaration

```
tibems_status tibemsSession_CreateBrowser(
    tibemsSession session,
    tibemsQueueBrowser* browser,
    tibemsQueue queue,
    const char* messageSelector );
```

COBOL Call

```
CALL "tibemsSession_CreateBrowser"
    USING BY VALUE session,
          BY REFERENCE browser,
          BY VALUE queue,
          BY REFERENCE messageSelector,
          RETURNING tibems-status
END-CALL.
```



session, browser and queue have usage pointer.

Parameters

| Parameter | Description |
|-----------------|--|
| session | Create a browser in this session. |
| browser | The function stores the new browser object in this location. |
| queue | Browse this queue. |
| messageSelector | When non-null, the browser presents only messages that match this selector; see Message Selectors on page 17 . When null, or the empty string, the browser views all messages in the queue. |

See Also [tibemsQueue on page 152](#)
[tibemsQueueBrowser on page 328](#)

tibemsSession_CreateBytesMessage

Function

Purpose Create a byte array message.

C Declaration `tibems_status tibemsSession_CreateBytesMessage(
tibemsSession session,
tibemsBytesMsg* bytesMsg);`

COBOL Call `CALL "tibemsSession_CreateBytesMessage"
USING BY VALUE session,
BY REFERENCE bytesMsg,
RETURNING tibems-status
END-CALL.`



session and bytesMsg have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Create the message in this session. |
| bytesMsg | The function stores the new message object in this location. |

See Also [tibemsBytesMsg on page 75](#)

tibemsSession_CreateConsumer

Function

Purpose Create a message consumer.

C Declaration `tibems_status tibemsSession_CreateConsumer(
tibemsSession session,
tibemsMsgConsumer* consumer,
tibemsDestination destination,
const char* messageSelector,
tibems_bool noLocal);`

COBOL Call `CALL "tibemsSession_CreateConsumer"
USING BY VALUE session,
BY REFERENCE consumer,
BY VALUE destination,
BY REFERENCE messageSelector,
BY VALUE noLocal,
RETURNING tibems-status
END-CALL.`



session, consumer and destination have usage pointer.

Parameters

| Parameter | Description |
|-----------------|--|
| session | Create the consumer in this session. |
| consumer | The function stores the new consumer object in this location. |
| destination | Create a consumer for this destination. The argument may be any destination (queue or topic). |
| messageSelector | When non-null, the server filters messages using this selector, so the consumer receives only matching messages; see Message Selectors on page 17 . When null, or the empty string, the consumer receives messages without filtering. |
| noLocal | When true, the server filters messages so the consumer does not receive messages that originate locally—that is, messages sent through the same connection. When false, the consumer receives messages with local origin. |

See Also [tibemsDestination on page 146](#)
 [tibemsMsgConsumer on page 164](#)

tibemsSession_CreateDurableSubscriber

Function

Purpose Create a durable topic subscriber.

C Declaration

```
tibems_status tibemsSession_CreateDurableSubscriber(  
    tibemsSession session,  
    tibemsMsgConsumer* msgConsumer,  
    tibemsTopic topic,  
    const char* name,  
    const char* messageSelector,  
    tibems_bool noLocal );
```

COBOL Call

```
CALL "tibemsSession_CreateDurableSubscriber"  
    USING BY VALUE session,  
          BY REFERENCE msgConsumer,  
          BY VALUE topic,  
          BY REFERENCE name,  
          BY REFERENCE messageSelector,  
          BY VALUE noLocal,  
          RETURNING tibems-status  
END-CALL.
```



session, msgConsumer, and topic have usage pointer.

Parameters

| Parameter | Description |
|-----------------|--|
| session | Create the topic subscriber in this session. |
| msgConsumer | The function stores the new message consumer object in this location. Note that the message consumer must be a topic subscriber. |
| topic | Create a durable subscriber for this topic (which <i>cannot</i> be a tibemsTemporaryTopic). |
| name | This unique name lets the server associate the subscriber with a subscription. |
| messageSelector | When non-null, the server filters messages using this selector, so the subscriber receives only matching messages; see Message Selectors on page 17 . When null, or the empty string, the subscriber receives messages without filtering. |

| Parameter | Description |
|----------------------|--|
| <code>noLocal</code> | When <code>true</code> , the server filters messages so the subscriber does not receive messages that originate locally—that is, messages sent through the same connection. When <code>false</code> , the consumer receives messages with local origin. |

Remarks The server associates a durable subscription with at most one subscriber object at a time. When a subscriber object exists, the subscription is *active*, and the server delivers messages to it; when no subscriber object exists, the subscription is *inactive*.

Durable subscriptions guarantee message delivery across periods during which the subscriber is inactive. The server retains unacknowledged messages until the subscriber acknowledges them, or until the messages expire.

Subscription Continuity Continuity across inactive periods uses two data items from the client:

- **Subscription Name** a parameter of this call
- **Client ID** an optional property of the `tibemsConnection` (used only when supplied)

The server uses one or both of these two items to match a subscriber object with its subscription. If a matching subscription exists, and it is inactive, then the server associates it with the subscriber (and the subscription becomes active). The server delivers unacknowledged messages to the subscriber.

If a matching subscription exists, but it is already active, this function fails with `TIBEMS_INVALID_CONSUMER`.

If a matching subscription to the topic does not yet exist, the server creates one.

- Matching Client ID**
- If the `tibemsConnection`'s client ID is non-null when a session creates a durable subscription, then only sessions of a connection with the same client ID can attach to that subscription.
 - If the `tibemsConnection`'s client ID is null when a session creates a durable subscription, then any session can attach to that subscription (to receive its messages).

**Changing Topic
or Selector**

Notice that the server does *not* use the topic and message selector arguments to match a subscriber to an existing subscription. As a result, client programs can *change* a subscription by altering either or both of these arguments. The effect is equivalent to deleting the existing subscription (from the server) and creating a new one (albeit with the same client ID and subscription name).

See Also

[tibemsTopic on page 158](#)
[tibemsMsgConsumer on page 164](#)
[tibemsConnection on page 210](#)

tibemsSession_CreateMapMessage

Function

- Purpose

Create a map message.
- C Declaration

`tibems_status tibemsSession_CreateMapMessage(
tibemsSession session,
tibemsMapMsg* mapMsg);`
- COBOL Call

`CALL "tibemsSession_CreateMapMessage"
USING BY VALUE session,
BY REFERENCE mapMsg,
RETURNING tibems-status
END-CALL.`



session and mapMsg have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Create the message in this session. |
| mapMsg | The function stores the new message object in this location. |

- Remarks

The JMS specification requires this call. It is equivalent to [tibemsMapMsg_Create on page 91](#).
- See Also

[tibemsMapMsg on page 90](#)

tibemsSession_CreateMessage

Function

Purpose Create a message.

C Declaration `tibems_status tibemsSession_CreateMessage(
tibemsSession session,
tibemsMsg* message);`

COBOL Call `CALL "tibemsSession_CreateMessage"
USING BY VALUE session,
BY REFERENCE message,
RETURNING tibems-status
END-CALL.`



session and message have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Create the message in this session. |
| message | The function stores the new message object in this location. |

Remarks The JMS specification requires this call. It is equivalent to [tibemsMsg_Create on page 29](#).

See Also [tibemsMsg on page 21](#)

tibemsSession_CreateProducer

Function

Purpose Create a message producer.

C Declaration `tibems_status tibemsSession_CreateProducer(
tibemsSession session,
tibemsMsgProducer* producer,
tibemsDestination destination);`

COBOL Call `CALL "tibemsSession_CreateProducer"
USING BY VALUE session,
BY REFERENCE producer,
BY VALUE destination,
RETURNING tibems-status
END-CALL.`



session, producer and destination have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| session | Create the producer in this session. |
| producer | The function stores the new producer object in this location. |
| destination | When non-null, the producer sends messages to this destination. When null, the client program must specify the destination for each message individually. |

See Also [tibemsDestination on page 146](#)
[tibemsMsgProducer on page 176](#)

tibemsSession_CreateSharedConsumer

Function

Purpose Create a shared consumer.

C Declaration `tibems_status tibemsSession_CreateSharedConsumer(
tibemsSession session,
tibemsMsgConsumer* consumer,
tibemsTopic topic,
const char* sharedSubscriptionName,
const char* messageSelector);`

COBOL Call `CALL "tibemsSession_CreateSharedConsumer"
USING BY VALUE session,
BY REFERENCE consumer,
BY VALUE topic,
BY REFERENCE sharedSubscriptionName,
BY REFERENCE messageSelector,
RETURNING tibems-status
END-CALL.`



session, consumer and topic have usage pointer.

Parameters

| Parameter | Description |
|-------------------------|--|
| session | Create the shared non-durable consumer in this session. |
| consumer | The function stores the new message consumer object in this location. |
| topic | Create the shared consumer for this topic. |
| sharedSubscription Name | The name used to identify the shared non-durable subscription. |
| messageSelector | When non-null, the server filters messages using this selector, so the consumer receives only matching messages; see Message Selectors on page 17 . When null, or the empty string, the consumer receives messages without filtering. |

Remarks Creates a shared non-durable subscription with the specified name on the specified topic (if one does not already exist), optionally specifying a message selector, and creates a consumer on that subscription.

If a shared non-durable subscription already exists with the same name and client identifier (if set), and the same topic and message selector has been specified, then this method creates a `tibemsMsgConsumer` on the existing subscription.

A non-durable shared subscription is used by a client that needs to be able to share the work of receiving messages from a topic subscription amongst multiple consumers. A non-durable shared subscription may therefore have more than one consumer. Each message from the subscription will be delivered to only one of the consumers on that subscription. Such a subscription is not persisted and is deleted (together with any undelivered messages associated with it) when there are no consumers on it. The term *consumer* here means a `tibemsMsgConsumer` object in any client.

A shared non-durable subscription is identified by a name specified by the client and by the client identifier (which may be unset). An application which subsequently wishes to create a consumer on that shared non-durable subscription must use the same client identifier.

If a shared non-durable subscription already exists with the same name and client identifier (if set) but a different topic or message selector has been specified, and there is a consumer already active (i.e. not closed) on the subscription, then an error will be returned.

There is no restriction on durable subscriptions and shared non-durable subscriptions having the same name and `clientId` (which may be unset). Such subscriptions would be completely separate.

See Also [tibemsSession_CreateSharedDurableConsumer on page 311](#)

tibemsSession_CreateSharedDurableConsumer

Function

Purpose Create a shared durable consumer.

C Declaration

```
tibems_status tibemsSession_CreateSharedDurableConsumer(
    tibemsSession session,
    tibemsMsgConsumer* consumer,
    tibemsTopic topic,
    const char* durableName,
    const char* messageSelector );
```

COBOL Call

```
CALL "tibemsSession_CreateSharedDurableConsumer"
    USING BY VALUE session,
         BY REFERENCE consumer,
         BY VALUE topic,
         BY REFERENCE durableName,
         BY REFERENCE messageSelector,
         RETURNING tibems-status
END-CALL.
```



session, consumer and topic have usage pointer.

Parameters

| Parameter | Description |
|-----------------|--|
| session | Create the shared durable consumer in this session. |
| consumer | The function stores the new message consumer object in this location. |
| topic | Create the shared durable consumer for this topic. |
| durableName | The name used to identify the shared durable subscription. |
| messageSelector | When non-null, the server filters messages using this selector, so the consumer receives only matching messages; see Message Selectors on page 17 . When null, or the empty string, the consumer receives messages without filtering. |

Remarks Creates a shared durable subscription on the specified topic (if one does not already exist), optionally specifying a message selector, and creates a consumer on that durable subscription.

A durable subscription is used by an application that needs to receive all the messages published on a topic, including the ones published when there is no active consumer associated with it. The server retains a record of this durable subscription and ensures that all messages from the topic's publishers are retained until they are delivered to, and acknowledged by, a consumer on this durable subscription, or until they have expired.

A durable subscription will continue to accumulate messages until it is deleted using the `tibemsSession_Unsubscribe` function.

This method may only be used with shared durable subscriptions. Any durable subscription created using this method is shared. This means that multiple active (that is, not closed) consumers on the subscription may exist at the same time. The term *consumer* here means a `tibemsMsgConsumer` object in any client.

A shared durable subscription is identified by a name specified by the client and by the client identifier (which may be unset). An application which subsequently wishes to create a consumer on that shared durable subscription must use the same client identifier.

If a shared durable subscription already exists with the same name and client identifier (if set), and the same topic and message selector have been specified, then this method creates a `tibemsMsgConsumer` on the existing shared durable subscription.

If a shared durable subscription already exists with the same name and client identifier (if set), but a different topic or message selector has been specified, and there is no consumer already active (that is, not closed) on the durable subscription, then this is equivalent to unsubscribing (deleting) the old one and creating a new one.

If a shared durable subscription already exists with the same name and client identifier (if set) but a different topic or message selector has been specified, and there is a consumer already active (that is, not closed) on the durable subscription, then an error is returned.

A shared durable subscription and an unshared durable subscription may not have the same name and client identifier (if set). If an unshared durable subscription already exists with the same name and client identifier (if set) then an error is returned.

There is no restriction on durable subscriptions and shared non-durable subscriptions having the same name and `clientId` (which may be unset). Such subscriptions would be completely separate.

See Also [tibemsSession_CreateSharedConsumer on page 309](#)
 [tibemsSession_Unsubscribe on page 323](#)

tibemsSession_CreateStreamMessage

Function

Purpose Create a stream message.

C Declaration `tibems_status tibemsSession_CreateStreamMessage(
tibemsSession session,
tibemsStreamMsg* streamMsg);`

COBOL Call `CALL "tibemsSession_CreateStreamMessage"
USING BY VALUE session,
BY REFERENCE streamMsg,
RETURNING tibems-status
END-CALL.`



session and streamMsg have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Create the message in this session. |
| streamMsg | The function stores the new message object in this location. |

Remarks The JMS specification requires this call. It is equivalent to [tibemsStreamMsg_Create on page 111](#).

See Also [tibemsStreamMsg on page 109](#)

tibemsSession_CreateTemporaryQueue

Function

Purpose Create a temporary queue.

C Declaration `tibems_status tibemsSession_CreateTemporaryQueue(
tibemsSession session,
tibemsTemporaryQueue* tmpQueue);`

COBOL Call `CALL "tibemsSession_CreateTemporaryQueue"
USING BY VALUE session,
BY REFERENCE tmpQueue,
RETURNING tibems-status
END-CALL.`



session and tmpQueue have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Create the queue in this session. |
| tmpQueue | The function stores the new temporary queue object in this location. |

Remarks A temporary queue lasts no longer than the connection. That is, when the connection is closed or broken, the server deletes temporary queues associated with the connection.

If the named queue already exists at the server, then this function returns that queue. (That queue can be either static or dynamic.)

If the named queue does not yet exist at the server, and the server allows dynamic queue, then this function creates a dynamic queue.

Dynamic destinations are provider-specific, so programs that use them might not be portable to other providers.

See Also [tibemsTemporaryQueue on page 156](#)

tibemsSession_CreateTemporaryTopic

Function

Purpose Create a temporary topic.

C Declaration `tibems_status tibemsSession_CreateTemporaryTopic(
tibemsSession session,
tibemsTemporaryTopic* tmpTopic);`

COBOL Call `CALL "tibemsSession_CreateTemporaryTopic"
USING BY VALUE session,
BY REFERENCE tmpTopic,
RETURNING tibems-status
END-CALL.`



session and tmpTopic have usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Create the topic in this session. |
| tmpTopic | The function stores the new temporary topic object in this location. |

Remarks A temporary topic lasts no longer than the connection. That is, when the connection is closed or broken, the server deletes temporary topic associated with the connection.

If the named topic already exists at the server, then this function returns that topic. (That topic can be either static or dynamic.)

If the named topic does not yet exist at the server, and the server allows dynamic topics, then this function creates a dynamic topic.

Dynamic destinations are provider-specific, so programs that use them might not be portable to other providers.

See Also [tibemsTemporaryTopic on page 157](#)

tibemsSession_CreateTextMessage

Function

Purpose Create a text message.

C Declaration

```
tibems_status tibemsSession_CreateTextMessage(  
    tibemsSession session,  
    tibemsTextMsg* textMsg );  
  
tibems_status tibemsSession_CreateTextMessageEx(  
    tibemsSession session,  
    tibemsTextMsg* textMsg  
    const char* text );
```

COBOL Call

```
CALL "tibemsSession_CreateTextMessage"  
    USING BY VALUE session,  
          BY REFERENCE textMsg,  
          RETURNING tibems-status  
END-CALL.  
  
CALL "tibemsSession_CreateTextMessageEx"  
    USING BY VALUE session,  
          BY REFERENCE textMsg,  
          BY REFERENCE text,  
          RETURNING tibems-status  
END-CALL.
```



session and textMsg have usage pointer.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | session | Create the message in this session. |
| | textMsg | The function stores the new message object in this location. |
| | text | Create a text message with this text as its body. |

Remarks The JMS specification requires these calls. It is equivalent to [tibemsTextMsg_Create on page 125](#).

See Also [tibemsTextMsg on page 124](#)

tibemsSession_DeleteTemporaryQueue

Function

Purpose Delete a temporary queue.

C Declaration `tibems_status tibemsSession_DeleteTemporaryQueue(
tibemsSession session,
tibemsTemporaryQueue tmpQueue);`

COBOL Call `CALL "tibemsSession_DeleteTemporaryQueue"
USING BY VALUE session,
BY VALUE tmpQueue,
RETURNING tibems-status
END-CALL.`



session and tmpQueue have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| session | Delete a temporary queue from this session. |
| tmpQueue | Delete this temporary queue. |

Remarks When a client deletes a temporary queue, the server deletes any unconsumed messages in the queue.

If the client still has listeners or receivers for the queue, then this delete call returns TIBEMS_ILLEGAL_STATE.

See Also [tibemsTemporaryQueue on page 156](#)

tibemsSession_DeleteTemporaryTopic

Function

Purpose Delete a temporary topic.

C Declaration `tibems_status tibemsSession_DeleteTemporaryTopic(
tibemsSession session,
tibemsTemporaryTopic tmpTopic);`

COBOL Call `CALL "tibemsSession_DeleteTemporaryTopic"
USING BY VALUE session,
BY VALUE tmpTopic,
RETURNING tibems-status
END-CALL.`



session and tmpTopic have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| session | Delete a temporary topic from this session. |
| tmpTopic | Delete this temporary topic. |

Remarks When a client deletes a temporary topic, the server deletes any unconsumed messages in the topic.

If the client still has listeners or receivers for the topic, then this delete call returns TIBEMS_ILLEGAL_STATE.

See Also [tibemsTemporaryTopic on page 157](#)

tibemsSession_GetAcknowledgeMode

Function

Purpose Get the acknowledge mode of a session.

C Declaration `tibems_status tibemsSession_GetAcknowledgeMode(
tibemsSession session,
tibemsAcknowledgeMode* acknowledgeMode);`

COBOL Call `CALL "tibemsSession_GetAcknowledgeMode"
USING BY VALUE session,
BY REFERENCE acknowledgeMode,
RETURNING tibems-status
END-CALL.`



session has usage pointer.

Parameters

| Parameter | Description |
|-----------------|--|
| session | Get the property from this session. |
| acknowledgeMode | The function stores the property value in this location. |

Remarks This mode governs message acknowledgement and redelivery for consumers associated with the session. For values, see [tibemsAcknowledgeMode on page 324](#).

This property is irrelevant when the session has transactional semantics.

tibemsSession_GetTransacted

Function

Purpose Get the transactional semantics property of a session.

C Declaration `tibems_status tibemsSession_GetTransacted(
tibemsSession session,
tibems_bool* isTransacted);`

COBOL Call `CALL "tibemsSession_GetTransacted"
USING BY VALUE session,
BY REFERENCE isTransacted,
RETURNING tibems-status
END-CALL.`



session has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| session | Get the property from this session. |
| isTransacted | The function stores the property value in this location. |

Remarks When true, then the session has transaction semantics, and the session’s acknowledge mode is irrelevant.
When false, it has non-transaction semantics.

tibemsSession_Recover

Function

Purpose Recover from undetermined state during message processing.

C Declaration `tibems_status tibemsSession_Recover(
tibemsSession session);`

COBOL Call `CALL "tibemsSession_Recover"
USING BY VALUE session,
RETURNING tibems-status
END-CALL.`



session has usage pointer.

Parameters

| Parameter | Description |
|-----------|-----------------------|
| session | Recover this session. |

Remarks Exceptions during message processing can sometimes leave a program in an ambiguous state. For example, some messages might be partially processed. This function lets a program return to an unambiguous state—the point within the message stream when the program last acknowledged the receipt of inbound messages. Programs can then review the messages delivered since that point (they are marked as *redelivered*), and resolve ambiguities about message processing. Programs can also use this function to resolve similar ambiguities after a [tibemsConnection](#) stops delivering messages, and then starts again.

Operation This function requests that the server do this sequence of actions:

1. Stop message delivery within the session.
2. Mark as *redelivered*, any messages that the server has attempted to deliver to the session, but for which it has not received acknowledgement (that is, messages for which processing state is ambiguous).

According to the JMS specification, the server need not redeliver messages in the same order as it first delivered them.
3. Restart message delivery (including messages marked as *redelivered* in step 2).

Transactions Commit and rollback are more appropriate with transactions. When a session has transactional semantics, this call is illegal, and returns [TIBEMS_INVALID_SESSION](#).

See Also [tibemsMsg_Recover](#) on page 59

tibemsSession_Rollback

Function

Purpose Roll back messages in the current transaction.

C Declaration `tibems_status tibemsSession_Rollback(
tibemsSession session);`

COBOL Call `CALL "tibemsSession_Rollback"
USING BY VALUE session,
RETURNING tibems-status
END-CALL.`



session has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Rollback the messages in this session. |

Remarks When a session does not have transactional semantics, this function returns `TIBEMS_ILLEGAL_STATE`.

Messages sent to a queue with `prefetch=none` and `maxRedelivery=number` properties are not received *number* times by an EMS application that receives in a loop and does an XA rollback after the XA prepare phase.

tibemsSession_Unsubscribe

Function

Purpose Unsubscribe a durable topic subscription.

C Declaration `tibems_status tibemsSession_Unsubscribe(
tibemsSession session
const char* name);`

COBOL Call `CALL "tibemsSession_Unsubscribe"
USING BY VALUE session,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`



session has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| session | Delete a subscription in this session. |
| name | This name lets the server locate the subscription. |

Remarks This function deletes the subscription from the server.



You must unsubscribe *before* closing the session.

It is illegal to delete an active subscription—that is, while a `tibemsMsgConsumer` exists.

It is illegal to delete a subscription while one of its messages is either unacknowledged, or uncommitted (in the current transaction). Attempting to do so results in a status of `TIBEMS_EXCEPTION`.

See Also [tibemsMsgConsumer on page 164](#)
[tibemsTopic on page 158](#)
[tibemsSession_CreateDurableSubscriber on page 303](#)

tibemsAcknowledgeMode

Type

Purpose Define acknowledgement mode constants.

| Constant | Description |
|----------------------------|--|
| TIBEMS_AUTO_ACKNOWLEDGE | <p>In this mode, the session automatically acknowledges a message when message processing is finished—that is, when either of these calls returns successfully:</p> <ul style="list-style-type: none">• synchronous receive calls (such as tibemsMsgConsumer_Receive on page 170)• asynchronous listener callback (namely, tibemsMsgCallback on page 174) |
| TIBEMS_CLIENT_ACKNOWLEDGE | <p>In this mode, the client program acknowledges receipt by calling tibemsMsg_Acknowledge on page 25. Each call acknowledges all messages received so far.</p> |
| TIBEMS_DUPS_OK_ACKNOWLEDGE | <p>As with TIBEMS_AUTO_ACKNOWLEDGE, the session automatically acknowledges messages. However, it may do so lazily.</p> <p><i>Lazy</i> means that the provider client library can delay transferring the acknowledgement to the server until a convenient time; meanwhile the server might redeliver the message. Lazy acknowledgement can reduce session overhead.</p> |

| Constant | Description |
|--|---|
| TIBEMS_EXPLICIT_CLIENT_ACKNOWLEDGE | <p>As with TIBEMS_CLIENT_ACKNOWLEDGE, the client program acknowledges receipt by calling tibemsMsg_Acknowledge on page 25. However, each call acknowledges <i>only</i> the individual message. The client may acknowledge messages in any order.</p> <p>This mode and behavior are proprietary extensions, specific to TIBCO EMS.</p> |
| TIBEMS_EXPLICIT_CLIENT_DUPS_OK_ACKNOWLEDGE | <p>In this mode, the client program lazily acknowledges <i>only</i> the individual message, by calling tibemsMsg_Acknowledge on page 25. The client may acknowledge messages in any order.</p> <p><i>Lazy</i> means that the provider client library can delay transferring the acknowledgement to the server until a convenient time; meanwhile the server might redeliver the message.</p> <p>This mode and behavior are proprietary extensions, specific to TIBCO EMS.</p> |
| TIBEMS_NO_ACKNOWLEDGE | <p>In TIBEMS_NO_ACKNOWLEDGE mode, messages do not require acknowledgement (which reduces message overhead). The server never redelivers messages.</p> <p>This mode and behavior are proprietary extensions, specific to TIBCO EMS.</p> |

```
COBOL      01  TIBEMS-ACKNOWLEDGE-MODES.
              05  TIBEMS-AUTO-ACKNOWLEDGE          PIC S9(8) COMP VALUE 1.
              05  TIBEMS-CLIENT-ACKNOWLEDGE        PIC S9(8) COMP VALUE 2.
              05  TIBEMS-DUPS-OK-ACKNOWLEDGE        PIC S9(8) COMP VALUE 3.
              05  TIBEMS-NO-ACKNOWLEDGE             PIC S9(8) COMP VALUE 22.
              05  TIBEMS-EXPLICIT-CL-ACK            PIC S9(8) COMP VALUE 23.
              05  TIBEMS-EXPLICIT-CL-DUPS-OK-ACK    PIC S9(8) COMP VALUE 24.
```


Chapter 10 **Queue Browser**

Queue browsers let client programs examine the messages on a queue without removing them from the queue.

Topics

- [tibemsQueueBrowser](#), page 328

tibemsQueueBrowser

Type

- Purpose**View the messages in a queue without consuming them.
- Remarks**

A browser is a dynamic enumerator of the queue (not a static snapshot). The queue is at the server, and its contents change as message arrive and consumers remove them. Meanwhile, while the browser is at the client. The function `tibemsQueueBrowser_GetNext` gets the next message from the server.

The browser can enumerate messages in a queue, or a subset filtered by a message selector.



Sessions serve as factories for queue browsers; see `tibemsSession_CreateBrowser` on page 299.

| Function | Description | Page |
|--|--|------|
| <code>tibemsQueueBrowser_Close</code> | Close the browser; reclaim resources. | 329 |
| <code>tibemsQueueBrowser_GetNext</code> | Get the next message from the browser. | 331 |
| <code>tibemsQueueBrowser_GetMsgSelector</code> | Get the selector string for the browser. | 330 |
| <code>tibemsQueueBrowser_GetQueue</code> | Get the queue that the browser examines. | 332 |

See Also `tibemsSession_CreateBrowser` on page 299

tibemsQueueBrowser_Close

Function

Purpose Close the browser; reclaim resources.

C Declaration `tibems_status tibemsQueueBrowser_Close(
tibemsQueueBrowser queueBrowser);`

COBOL Call `CALL "tibemsQueueBrowser_Close"
USING BY VALUE queueBrowser,
RETURNING tibems-status
END-CALL.`



queueBrowser has usage pointer.

Parameters

| Parameter | Description |
|--------------|---------------------------|
| queueBrowser | Close this queue browser. |

tibemsQueueBrowser_GetMsgSelector

Function

Purpose Get the selector string for the browser.

C Declaration `tibems_status tibemsQueueBrowser_GetMsgSelector(
tibemsQueueBrowser queueBrowser,
const char** selector);`

COBOL Call `CALL "tibemsQueueBrowser_GetMsgSelector"
USING BY VALUE queueBrowser,
BY REFERENCE selector,
RETURNING tibems-status
END-CALL.`



queueBrowser and selector have usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| queueBrowser | Get the selector from the queue of this browser. |
| selector | The function stores the selector string in this location. |

Remarks When non-null, the browser presents only messages that match this selector; see [Message Selectors on page 17](#).
When null, or the empty string, the browser views all messages in the queue.

tibemsQueueBrowser_GetNext

Function

Purpose Get the next message from the browser.

C Declaration `tibems_status tibemsQueueBrowser_GetNext(
tibemsQueueBrowser queueBrowser,
tibemsMsg* msg);`

COBOL Call `CALL "tibemsQueueBrowser_GetNext"
USING BY VALUE queueBrowser,
BY REFERENCE msg,
RETURNING tibems-status
END-CALL.`



queueBrowser and msg have usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| queueBrowser | Get the next message from the queue of this browser. |
| msg | The function stores the next message in this location. |

Remarks

A browser is a dynamic enumerator of the queue (not a static snapshot). The queue is at the server, and its contents change as message arrive and consumers remove them. Meanwhile, while the browser is at the client. This function gets the next message from the server.

If prior calls to this function have exhausted the messages in the queue, the function returns `TIBEMS_NOT_FOUND`.

tibemsQueueBrowser_GetQueue

Function

Purpose Get the queue that the browser examines.

C Declaration `tibems_status tibemsQueueBrowser_GetQueue(
tibemsQueueBrowser queueBrowser,
tibemsQueue* queue);`

COBOL Call `CALL "tibemsQueueBrowser_GetQueue"
USING BY VALUE queueBrowser,
BY REFERENCE queue,
RETURNING tibems-status
END-CALL.`



queueBrowser and queue have usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| queueBrowser | Get the queue of this browser. |
| queue | The function stores the queue in this location. |

Chapter 11 **Name Server Lookup**

Lookup context objects find named objects (such as connection factories and destinations) in the name repository. (The EMS server, `tibemsd`, provides the name repository service).

Topics

- [tibemsLookupContext](#), page 334
- [tibemsLookupParams](#), page 341

tibemsLookupContext

Type

- Purpose** Retrieve objects from the server’s naming directory.
- Remarks** The context object establishes communication with an EMS server or an LDAP server, authenticates the user, and submits name queries.

Name queries can retrieve connection factories and destinations.

| Function | Description | Page |
|--|---|------|
| tibemsLookupContext_Create tibemsLookupContext_CreateSSL | Create a new EMS lookup context object. | 335 |
| tibemsLookupContext_CreateExternal | Create a new LDAP lookup context object. | 337 |
| tibemsLookupContext_Destroy | Destroy a lookup context and reclaim resources. | 338 |
| tibemsLookupContext_Lookup tibemsLookupContext_LookupDestination tibemsLookupContext_LookupConnectionFactory | Lookup an object in the naming server. | 339 |

tibemsLookupContext_Create

Function

Purpose Create a new EMS lookup context object.

C Declaration

```
tibems_status tibemsLookupContext_Create(
    tibemsLookupContext* context,
    const char* brokerURL,
    const char* username,
    const char* password );

tibems_status tibemsLookupContext_CreateSSL(
    tibemsLookupContext* context,
    const char* brokerURL,
    const char* username,
    const char* password,
    tibemsSSLParams sslParams,
    const char* pk_password );
```

COBOL Call

```
CALL "tibemsLookupContext_Create"
    USING BY REFERENCE context,
          BY REFERENCE brokerURL,
          BY REFERENCE username,
          BY REFERENCE password,
          RETURNING tibems-status
END-CALL.

CALL "tibemsLookupContext_CreateSSL"
    USING BY REFERENCE context,
          BY REFERENCE brokerURL,
          BY REFERENCE username,
          BY REFERENCE password,
          BY VALUE sslParams,
          BY REFERENCE pk-password,
          RETURNING tibems-status
END-CALL.
```



context and sslParams have usage pointer.

On IBM z/OS systems, the pk-password must always be a null value.

Parameters

| Parameter | Description |
|-----------|---|
| context | The function stores the new lookup context object in this location. |
| brokerURL | The context object connects to the EMS server at this URL. If configuring a fault-tolerant client, enter two or more URLs, as described in Configuring C and COBOL Clients for Fault-Tolerant Connections on page 5 . |

| Parameter | Description |
|-------------|--|
| username | The context object identifies itself to the server with this user name. |
| password | The context object identifies itself to the server with this password. |
| sslParams | The context object uses this data to create an SSL connection to the EMS server. |
| pk_password | The context object uses this password to decrypt its SSL private key. |

Remarks The first call produces a lookup context that communicates with server without encryption. The second call produces a lookup context that communicates using an SSL connection.

 If the server permits anonymous lookup, you may supply null values for the username and password parameters.

See Also [tibemsLookupContext_CreateExternal on page 337](#)

tibemsLookupContext_CreateExternal

Function

Purpose Create a new LDAP lookup context object.

C Declaration `tibems_status tibemsLookupContext_CreateExternal(
tibemsLookupContext* context,
tibemsLookupParams lookupParams);`

COBOL Call `CALL "tibemsLookupContext_CreateExternal"
USING BY REFERENCE context,
BY VALUE lookupParams,
RETURNING tibems-status
END-CALL.`



context and lookupParams have usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| context | The function stores the new lookup context object in this location. |
| lookupParams | The context object uses these parameters to connect to an LDAP server. After the function returns successfully, the calling program may delete this struct. |

See Also [tibemsLookupContext_Create on page 335](#)
[tibemsLookupParams on page 341](#)
[tibemsLookupParams_Create on page 342](#)
[tibemsLookupParams_Destroy on page 343](#)

tibemsLookupContext_Destroy

Function

Purpose Destroy a lookup context and reclaim resources.

C Declaration `tibems_status tibemsLookupContext_Destroy(
tibemsLookupContext context);`

COBOL Call CALL "tibemsLookupContext_Destroy"
USING BY VALUE context,
RETURNING tibems-status
END-CALL.



context has usage pointer.

Parameters

| Parameter | Description |
|-----------|-------------------------------------|
| context | Destroy this lookup context object. |

tibemsLookupContext_Lookup

Function

Purpose Lookup an object in the naming server.

C Declaration

```
tibems_status tibemsLookupContext_Lookup(
    tibemsLookupContext context,
    const char* name,
    void** object);

tibems_status tibemsLookupContext_LookupDestination(
    tibemsLookupContext context,
    const char* name,
    tibemsDestination* destination);

tibems_status tibemsLookupContext_LookupConnectionFactory(
    tibemsLookupContext context,
    const char* name,
    tibemsConnectionFactory* factory);
```

COBOL Call

```
CALL "tibemsLookupContext_Lookup"
    USING BY VALUE context,
          BY REFERENCE name,
          BY REFERENCE object,
          RETURNING tibems-status
END-CALL.

CALL "tibemsLookupContext_LookupDestination"
    USING BY VALUE context,
          BY REFERENCE name,
          BY REFERENCE destination,
          RETURNING tibems-status
END-CALL.

CALL "tibemsLookupContext_LookupConnectionFactory"
    USING BY VALUE context,
          BY REFERENCE name,
          BY REFERENCE factory,
          RETURNING tibems-status
END-CALL.
```



context, object, destination and factory have usage pointer.

Parameters

| Parameter | Description |
|-----------|-------------------------------------|
| context | Destroy this lookup context object. |
| name | Lookup this name. |

| Parameter | Description |
|-------------|---|
| object | The function stores the results of the lookup operation in this location. |
| destination | |
| factory | |

Remarks These calls look up names in either the name server portion of an EMS server, or in an LDAP server.

The first call looks up a generic object; the calling program must cast the result to the expect type. The other calls restrict lookup to either destinations or connection factories.

If the server does not find the name, this call returns `TIBEMS_NOT_FOUND`.

If the server finds both a topic and a queue with the same name, this call returns `TIBEMS_ILLEGAL_STATE`.

The calling program must destroy the resulting object when it is no longer needed.

tibemsLookupParams

Type

Purpose Encapsulate parameters for LDAP lookup.

| Function | Description | Page |
|---|---|------|
| tibemsLookupParams_Create | Create a new LDAP lookup context object. | 342 |
| tibemsLookupParams_Destroy | Destroy a lookup parameters object. | 343 |
| tibemsLookupParams_GetLdapServerUrl | Get the LDAP server URL. | 344 |
| tibemsLookupParams_SetLdapBaseDN | Set the LDAP base distinguished name. | 345 |
| tibemsLookupParams_SetLdapCAFile | Set the LDAP CA certificate file. | 346 |
| tibemsLookupParams_SetLdapCAPath | Set the LDAP CA certificate directory pathname. | 347 |
| tibemsLookupParams_SetLdapCertFile | Set the LDAP client certificate file. | 348 |
| tibemsLookupParams_SetLdapCiphers | Set SSL ciphers. | 349 |
| tibemsLookupParams_SetLdapConnType | Set the LDAP connection type. | 350 |
| tibemsLookupParams_SetLdapCredential | Set the LDAP credential (password). | 351 |
| tibemsLookupParams_SetLdapKeyFile | Set the LDAP client key file. | 352 |
| tibemsLookupParams_SetLdapPrincipal | Set the LDAP principal (user name). | 353 |
| tibemsLookupParams_SetLdapRandFile | Set a randomization data file. | 354 |
| tibemsLookupParams_SetLdapSearchScope | Set the LDAP search scope. | 355 |
| tibemsLookupParams_SetLdapServerUrl | Set the LDAP server URL. | 356 |

tibemsLookupParams_Create

Function

- Purpose** Create a new lookup parameters object.
- C Declaration** [tibemsLookupParams](#)
tibemsLookupParams_Create(void);
- IBM Systems** This function is not supported on z/OS and IBM i systems.
- See Also** [tibemsLookupContext_CreateExternal](#) on page 337

tibemsLookupParams_Destroy

Function

Purpose Destroy a lookup parameters object.

C Declaration

```
void tibemsLookupParams_Destroy(  
    tibemsLookupParams lparams );
```

IBM Systems This function is not supported on z/OS and IBM i systems.

Parameters

| Parameter | Description |
|-----------|---|
| lparams | The function stores the new lookup context object in this location. |

tibemsLookupParams_GetLdapServerUrl

Function

- Purpose**Get the LDAP server URL.
- C Declaration**

```
char* tibemsLookupParams_GetLdapServerUrl(  
    tibemsLookupParams lparams);
```
- IBM Systems**This function is not supported on z/OS and IBM i systems.

Parameters

| Parameter | Description |
|-----------|---|
| lparams | Get the LDAP server URL from this external lookup context object. |

tibemsLookupParams_SetLdapBaseDN

Function

Purpose Set the LDAP base distinguished name.

C Declaration `tibems_status tibemsLookupParams_SetLdapBaseDN(
tibemsLookupParams lparams,
const char* basedn);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | basedn | Set the property to this distinguished name. |

Remarks This parameter is required for all LDAP lookup operations.

tibemsLookupParams_SetLdapCAFile

Function

Purpose Set the LDAP CA certificate file.

C Declaration `tibems_status tibemsLookupParams_SetLdapCAFile(
tibemsLookupParams lparams,
const char* file);`

IBM Systems This function is not supported on z/OS and IBM i systems.

Parameters

| Parameter | Description |
|-----------|--|
| lparams | Set the property in this parameter object. |
| path | Set the property to this filename. |

Remarks The client program reads the CA certificate from this file.

tibemsLookupParams_SetLdapCAPath

Function

Purpose Set the LDAP CA certificate directory pathname.

C Declaration `tibems_status tibemsLookupParams_SetLdapCAPath(
tibemsLookupParams lparams,
const char* path);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | path | Set the property to this directory pathname. |

Remarks Set this parameter when several certificate files are grouped in one directory. This parameter specifies that directory. The client program reads certificate files from this directory.

tibemsLookupParams_SetLdapCertFile

Function

Purpose Set the LDAP client certificate file.

C Declaration `tibems_status tibemsLookupParams_SetLdapCertFile(
tibemsLookupParams lparams,
const char* file);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | file | Set the property to this filename. |

Remarks The client program reads the client certificate from this file.
Set this parameter when the LDAP server requires clients to present certificates as identification.

tibemsLookupParams_SetLdapCiphers

Function

Purpose Set SSL ciphers.

C Declaration `tibems_status tibemsLookupParams_SetLdapCiphers(
tibemsLookupParams lparams,
const char* ciphers);`

IBM Systems This function is not supported on z/OS and IBM i systems.

Parameters

| Parameter | Description |
|-----------|---|
| lparams | Set the property in this parameter object. |
| ciphers | <p>Set the property to specify these ciphers (as a colon-separated list).</p> <p>For example:</p> <p>"EDH-RSA-DES-CBC3-SHA:EDH-DSS-DES-CBC3-SHA:DES-CBC3-SHA:DES-CBC3-MD5:DHE-DSS-RC4-SHA:IDEA-CBC-SHA:RC4-SHA:RC4-MD5:IDEA-CBC-MD5:RC2-CBC-MD5:RC4-MD5:RC4-64-MD5:EXP1024-DHE-DSS-RC4-SHA:EXP1024-RC4-SHA:EXP1024-DHE-DSS-DES-CBC-SHA:EXP1024-DES-CBC-SHA:EXP1024-RC2-CBC-MD5:EXP1024-RC4-MD5:EDH-RSA-DES-CBC-SHA:EDH-DSS-DES-CBC-SHA:DES-CBC-SHA:DES-CBC-MD5:EXP-EDH-RSA-DES-CBC-SHA:EXP-EDH-DSS-DES-CBC-SHA:EXP-DES-CBC-SHA:EXP-RC2-CBC-MD5:EXP-RC4-MD5:EXP-RC2-CBC-MD5:EXP-RC4-MD5"</p> |

Remarks Set this parameter when using secure LDAP connections.

The LDAP server configures a similar list of ciphers. SSL communication uses the strongest ciphers in the intersection of the server and client cipher lists.

tibemsLookupParams_SetLdapConnType

Function

Purpose Set the LDAP connection type.

C Declaration `tibems_status tibemsLookupParams_SetLdapConnType(
tibemsLookupParams lparams,
const char* type);`

IBM Systems This function is not supported on z/OS and IBM i systems.

Parameters

| Parameter | Description |
|-----------|--|
| lparams | Set the property in this parameter object. |
| type | Set the property to this type. When this value is not set, it specifies a simple (non-secure) connection. Either "ldaps" or "startTLS" specify secure connections. |

tibemsLookupParams_SetLdapCredential

Function

Purpose Set the LDAP credential (password).

C Declaration `tibems_status tibemsLookupParams_SetLdapCredential(
tibemsLookupParams lparams,
const char* credential);`

IBM Systems This function is not supported on z/OS and IBM i systems.

Parameters

| Parameter | Description |
|------------|---|
| lparams | Set the property in this parameter object. |
| credential | Set the property to this credential (password). |

tibemsLookupParams_SetLdapKeyFile

Function

Purpose Set the LDAP client key file.

C Declaration `tibems_status tibemsLookupParams_SetLdapKeyFile(
tibemsLookupParams lparams,
const char* file);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | file | Set the property to this filename. |

Remarks The client program reads the private key for the client certificate from this (encrypted) file.

Set this parameter when the LDAP server requires clients to present certificates as identification.

tibemsLookupParams_SetLdapPrincipal

Function

Purpose Set the LDAP principal (user name).

C Declaration `tibems_status tibemsLookupParams_SetLdapPrincipal(
tibemsLookupParams lparams,
const char* principal);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | lparams | Set the property in this parameter object. |
| | principal | Set the property to this principal (user name). |

Remarks This parameter is required for all LDAP lookup operations.

tibemsLookupParams_SetLdapRandFile

Function

Purpose Set a randomization data file.

C Declaration `tibems_status tibemsLookupParams_SetLdapRandFile(
tibemsLookupParams lparams,
const char* file);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | file | Set the property to this filename. |

Remarks The client program reads random data for security computations from this file.
Set this parameter when the operating system does not provide a random data service.

tibemsLookupParams_SetLdapSearchScope

Function

Purpose Set the LDAP search scope.

C Declaration `tibems_status tibemsLookupParams_SetLdapSearchScope(
tibemsLookupParams lparams,
const char* scope);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | scope | Set the property to this search scope. |

Remarks This parameter is required for all LDAP lookup operations.

tibemsLookupParams_SetLdapServerUrl

Function

Purpose Set the LDAP server URL.

C Declaration `tibems_status tibemsLookupParams_SetLdapServerUrl(
tibemsLookupParams lparams,
const char* url);`

IBM Systems This function is not supported on z/OS and IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | lparams | Set the property in this parameter object. |
| | url | Set the property to this URL. |

Remarks This parameter is required for all LDAP lookup operations.

Chapter 12 **XA—External Transaction Manager**

This chapter describes the EMS XA API. This API lets you code your own transaction manager (TM) that can interact with the EMS server as a transactional resource.

Topics

- [tibemsXAConnection_Close, page 359](#)
- [tibemsXAConnection_Create, page 361](#)
- [tibemsXAConnection_CreateXASession, page 363](#)
- [tibemsXAConnection_Get, page 364](#)
- [tibemsXAConnection_GetXASession, page 365](#)
- [XID, page 366](#)
- [tibemsXAResource, page 367](#)
- [tibemsXASession, page 381](#)

tibemsXAConnection

This implicit type is not defined; instead it is identical to [tibemsConnection on page 210](#). The functions we present on the following pages apply only to connection objects used with XA.

tibemsXAConnection_Close

Function

Purpose Close the connection; reclaim resources.

C Declaration `tibems_status tibemsXAConnection_Close(
tibemsConnection connection);`

COBOL Call `CALL "tibemsXAConnection_Close"
USING BY VALUE connection,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.

Parameters

| Parameter | Description |
|------------|------------------------|
| connection | Close this connection. |

Remarks

Closing an XA connection reclaims all XA resources associated with the connection or its sessions.

Closing the connection is not sufficient to reclaim all of its resources; your program must explicitly close the sessions, producers, and consumers associated with the connection.

Closing a connection deletes all temporary destinations associated with the connection.

Blocking

If any message listener or receive call associated with the connection is processing a message when the program calls this function, all facilities of the connection and its sessions remain available to those listeners until they return. In the meantime, this function blocks until that processing completes—that is, until all message listeners and receive calls have returned.

Acknowledge

Closing a connection does *not* force acknowledgment in client-acknowledged sessions. When the program still has a message that it received from a connection that has since closed, `tibemsMsg_Acknowledge` returns the status code `TIBEMS_ILLEGAL_STATE`.

Transactions

Closing a connection rolls back all open transactions in all sessions associated with the connection.

See Also [tibemsMsg_Acknowledge on page 25](#)
 [tibemsMsgConsumer on page 164](#)
 [tibemsMsgProducer on page 176](#)
 [tibemsDestination on page 146](#)
 [tibemsSession on page 294](#)

tibemsXAConnection_Create

Function

Purpose Create a new XA connection to an EMS server; use XA for transactions.

C Declarations

```
tibems_status tibemsXAConnection_Create(  
    tibemsConnection* connection,  
    const char* brokerURL,  
    const char* clientId,  
    const char* username,  
    const char* password );  
  
tibems_status tibemsXAConnection_CreateSSL(  
    tibemsConnection* connection,  
    const char* brokerURL,  
    const char* clientId,  
    const char* username,  
    const char* password,  
    tibemsSSLParams sslParams,  
    const char* pk_password );
```

COBOL Call

```
CALL "tibemsXAConnection_Create"  
    USING BY REFERENCE connection,  
          BY REFERENCE brokerURL,  
          BY REFERENCE clientId,  
          BY REFERENCE username,  
          BY REFERENCE password,  
          RETURNING tibems-status  
END-CALL.
```



On IBM z/OS systems, the pk-password must always be a null value.

Parameters

| Parameter | Description |
|------------|---|
| connection | The function stores the new connection in this location. |
| brokerURL | Find the EMS server at this URL. If configuring a fault-tolerant client, enter two or more URLs, as described in Configuring C and COBOL Clients for Fault-Tolerant Connections on page 5 . |
| clientId | Identify the client program to the server with this unique ID. |
| username | Identify the client program to the server with this user name. |
| password | Authenticate the client program to the server with this password. |

| Parameter | Description |
|-------------|---|
| sslParams | Establish SSL communication using these parameters. |
| pk_password | Private key password for SSL. |

| Status Code | Description |
|-----------------------------|---|
| TIBEMS_OK | The call succeeded. |
| TIBEMS_SERVER_NOT_CONNECTED | <ul style="list-style-type: none">No server is running at the specified URL.The call could not communicate with a server because of mismatched SSL and TCP protocols.Other error situations are possible. |
| TIBEMS_SECURITY_EXCEPTION | <ul style="list-style-type: none">The server rejected the connection because the username or password was invalid.SSL setup is incorrect. |
| TIBEMS_INVALID_CLIENT_ID | The client ID is not unique; that is, another client already uses the ID. |

See Also [tibemsConnection_Create on page 214](#)

tibemsXAConnection_CreateXASession

Function

Purpose Create an XA session object.

C Declaration `tibems_status tibemsXAConnection_CreateXASession(
tibemsConnection connection,
tibemsSession* session);`

COBOL Call `CALL "tibemsXAConnection_CreateXASession"
USING BY VALUE connection,
BY REFERENCE session,
RETURNING tibems-status
END-CALL.`



connection and session have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| connection | Create a session on this connection. |
| session | The function stores the new session in this location. |

Remarks The new session has transactional semantics with an external transaction manager, and uses the connection for all server communications.



XA sessions do not support routed queues.

See Also [tibemsSession on page 294](#)

tibemsXAConnection_Get

Function

Purpose Find the XA connection object for a server URL.

C Declaration `tibems_status tibemsXAConnection_Get(
tibemsConnection* connection,
const char* brokerURL);`

COBOL Call `CALL "tibemsXAConnection_Get"
USING BY REFERENCE connection,
BY REFERENCE brokerURL,
RETURNING tibems-status
END-CALL.`



connection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| connection | The function stores the connection object in this location. |
| brokerURL | Find the connection the EMS server at this URL. If configuring a fault-tolerant client, enter two or more URLs, as described in Configuring C and COBOL Clients for Fault-Tolerant Connections on page 5 . |

Remarks If the TM has implicitly created a connection by calling `xa_open`, then the TM can get that connection object with this call.

tibemsXAConnection_GetXASession

Function

Purpose Get the XA session object from an XA connection.

C Declaration `tibems_status tibemsXAConnection_GetXASession(
tibemsConnection* connection,
tibemsSession* xaSession);`

COBOL Call `CALL "tibemsXAConnection_GetXASession"
USING BY VALUE connection,
BY REFERENCE xaSession,
RETURNING tibems-status
END-CALL.`



connection and xaSession have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| connection | Get the XA session object from this XA connection. |
| xaSession | The function stores the XA session object in this location. |

Remarks If the TM has implicitly created a session by calling xa_open, then the TM can get that session object with this call.

XID

Type

Purpose Represent a transaction ID.

tibemsXAResource

Type

Purpose Coordinate XA transactions.

Remarks Each `tibemsXAResource` instance can coordinate a series of transactions, but only one transaction at a time. A program that keeps n transactions open simultaneously must create n instances of this type.

The transaction manager assigns each resource instance a unique RMID, which it uses to bind together a thread, a resource and a transaction.

| Function | Description | Page |
|---|---|------|
| <code>tibemsXAResource_Commit</code> | Commit a transaction. | 368 |
| <code>tibemsXAResource_End</code> | Disassociate a transaction from the resource. | 369 |
| <code>tibemsXAResource_Forget</code> | Unimplemented. | 370 |
| <code>tibemsXAResource_GetRMID</code> | Get the RMID of the resource. | 371 |
| <code>tibemsXAResource_GetTransactionTimeout</code> | Get the timeout limit. | 372 |
| <code>tibemsXAResource_isSameRM</code> | Determine whether two resource objects originate from the same connection to an EMS server. | 373 |
| <code>tibemsXAResource_Prepare</code> | Prepare a transaction for commit. | 374 |
| <code>tibemsXAResource_Recover</code> | Get a list of prepared transactions. | 375 |
| <code>tibemsXAResource_SetRMID</code> | Assign an RMID to a resource. | 378 |
| <code>tibemsXAResource_SetTransactionTimeout</code> | Set the timeout limit. | 379 |
| <code>tibemsXAResource_Start</code> | Associate a transaction with a resource. | 380 |

tibemsXAResource_Commit

Function

Purpose Commit a transaction.

C Declaration `tibems_status tibemsXAResource_Commit(
tibemsXAResource xaResource,
XID* xid,
tibems_bool onePhase);`

COBOL Call `CALL "tibemsXAResource_Commit"
USING BY VALUE xaResource,
BY REFERENCE xid,
BY VALUE onePhase,
RETURNING tibems-status
END-CALL.`



xaResource and xid have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| xaResource | Commit the transaction in this resource. |
| xid | Commit this transaction. |
| onePhase | TIBEMS_TRUE requests a <i>one-phase commit</i> . TIBEMS_FALSE requests a <i>two-phase commit</i> . |

tibemsXAResource_End

Function

Purpose Disassociate a transaction from the resource.

C Declaration `tibems_status tibemsXAResource_End(
tibemsXAResource xaResource,
XID* xid,
int flags);`

COBOL Call `CALL "tibemsXAResource_End"
USING BY VALUE xaResource,
BY REFERENCE xid,
BY VALUE flags,
RETURNING tibems-status
END-CALL.`



xaResource and xid have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| xaResource | Disassociate the transaction from this resource. |
| xid | Disassociate this transaction from the resource. |
| flags | TMSUCCESS—Completely end the transaction. TMSUSPEND—Temporarily disassociate the transaction from this resource. |

tibemsXAResource_Forget

Function

Purpose Unimplemented.

C Declaration `tibems_status tibemsXAResource_Forget(
tibemsXAResource xaResource,
XID* xid);`

COBOL Call `CALL "tibemsXAResource_Forget"
USING BY VALUE xaResource,
BY REFERENCE xid,
RETURNING tibems-status
END-CALL.`



xaResource and xid have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| xaResource | Forget the transaction in this resource. |
| xid | Forget this transaction. |

Remarks In the XA interface, the transaction manager can instruct a resource to forget a transaction.
However, this call is not implemented in EMS; it is present for completeness only.

tibemsXAResource_GetRMID

Function

Purpose Get the RMID of the resource.

C Declaration `tibems_status tibemsXAResource_GetRMID(
tibemsXAResource xaResource,
tibems_int* rmid);`

COBOL Call `CALL "tibemsXAResource_GetRMID"
USING BY VALUE xaResource,
BY REFERENCE rmid,
RETURNING tibems-status
END-CALL.`



xaResource has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| xaResource | Get the RMID of this resource. |
| rmid | The function stores the RMID in this location. |

Remarks The transaction manager assigns a unique RMID to each resource instance, which it uses to bind together a thread, a resource and a transaction.

tibemsXAResource_GetTransactionTimeout

Function

Purpose Get the timeout limit.

C Declaration `tibems_status tibemsXAResource_GetTransactionTimeout(
tibemsXAResource xaResource,
tibems_int* seconds);`

COBOL Call `CALL "tibemsXAResource_GetTransactionTimeout"
USING BY VALUE xaResource,
BY REFERENCE seconds,
RETURNING tibems-status
END-CALL.`



xaResource has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| xaResource | Get the transaction timeout of this resource. |
| seconds | The function stores the transaction timeout (in seconds) in this location. |

Remarks If an open, unprepared transaction does not log any activity on the server for this length of time, then the server automatically rolls back the transaction.

See Also [tibemsXAResource_SetTransactionTimeout on page 379](#)

tibemsXAResource_isSameRM

Function

Purpose Determine whether two resource objects originate from the same connection to an EMS server.

C Declaration `tibems_status tibemsXAResource_isSameRM(
tibemsXAResource xaResource,
tibemsXAResource xaResource2,
tibems_bool* result);`

COBOL Call `CALL "tibemsXAResource_isSameRM"
USING BY VALUE xaResource,
BY VALUE xaResource2,
BY REFERENCE result,
RETURNING tibems-status
END-CALL.`



xaResource and xaResource2 have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| xaResource | First XA resource. |
| xaResource2 | Second XA resource. |
| result | The function stores the result in this location: |

tibemsXAResource_Prepere

Function

Purpose Prepare a transaction for commit.

C Declaration `tibems_status tibemsXAResource_Prepere(
tibemsXAResource xaResource,
XID* xid);`

COBOL Call `CALL "tibemsXAResource_Prepere"
USING BY VALUE xaResource,
BY REFERENCE xid,
RETURNING tibems-status
END-CALL.`



xaResource and xid have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| xaResource | Prepare the transaction in this resource. |
| xid | Prepare this transaction. |

tibemsXAResource_Recover

Function

Purpose Get a list of prepared transactions.

C Declaration

```
tibems_status tibemsXAResource_Recover(  
    tibemsXAResource xaResource,  
    XID* xids,  
    tibems_int desiredCount,  
    tibems_int* returnedCount,  
    tibems_int flag );
```

COBOL Call

```
CALL "tibemsXAResource_Recover"  
  USING BY VALUE xaResource,  
        BY REFERENCE xids,  
        BY VALUE desiredCount,  
        BY REFERENCE returnedCount,  
        BY VALUE flag,  
        RETURNING tibems-status  
END-CALL.
```



xaResource and xids have usage pointer.

Parameters

| Parameter | Description |
|---------------|---|
| xaResource | List the prepared transactions of this resource. |
| xids | The function stores the list of transaction IDs in the array in this location. |
| desiredCount | Size of the array (number of XIDs). |
| returnedCount | The function stores the actual number of transaction IDs in this location. |
| flag | TMSTARTRSCAN—Start a new list of XIDs; the EMS server generates a complete list, and sends the first batch. TMNOFLAGS—Continue the list of XIDs; the EMS server sends the next batch. TMENDRSCAN—The EMS server discards its list of prepared transactions, and reclaims storage. |

Remarks When this call returns, if `returnedCount` \neq `desiredCount`, then more prepared transactions might exist. To get the next batch of XIDs, call this function again with `TMNOFLAGS` flag until `returnedCount` $<$ `desiredCount`.

tibemsXAResource_Rollback

Function

Purpose Roll back a transaction.

C Declaration `tibems_status tibemsXAResource_Rollback(
tibemsXAResource xaResource,
XID* xid);`

COBOL Call `CALL "tibemsXAResource_Rollback"
USING BY VALUE xaResource,
BY REFERENCE xid,
RETURNING tibems-status
END-CALL.`



xaResource and xid have usage pointer.

Parameters

| Parameter | Description |
|------------|-----------------------------|
| xaResource | Roll back in this resource. |
| xid | Roll back this transaction. |

Remarks Messages sent to a queue with prefetch=none and maxRedelivery=*number* properties are not received *number* times by an EMS application that receives in a loop and does an XA rollback after the XA prepare phase.

tibemsXAResource_SetRMID

Function

Purpose Assign an RMID to a resource.

C Declaration `tibems_status tibemsXAResource_SetRMID(
tibemsXAResource xaResource,
tibems_int rmid);`

COBOL Call `CALL "tibemsXAResource_SetRMID"
USING BY VALUE xaResource,
BY VALUE rmid,
RETURNING tibems-status
END-CALL.`



xaResource has usage pointer.

Parameters

| Parameter | Description |
|------------|--------------------------------|
| xaResource | Set the RMID of this resource. |
| rmid | Use this RMID. |

tibemsXAResource_SetTransactionTimeout

Function

Purpose Set the timeout limit.

C Declaration `tibems_status tibemsXAResource_SetTransactionTimeout(
tibemsXAResource xaResource,
tibems_int seconds);`

COBOL Call `CALL "tibemsXAResource_SetTransactionTimeout"
USING BY VALUE xaResource,
BY VALUE seconds,
RETURNING tibems-status
END-CALL.`



xaResource has usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| xaResource | Set the transaction timeout of this resource. |
| seconds | Use this transaction timeout (in seconds). |

Remarks If an unprepared transaction does not log any activity on the server for this length of time, then the server automatically rolls back the transaction.

See Also [tibemsXAResource_GetTransactionTimeout on page 372](#)

tibemsXAResource_Start

Function

Purpose Associate a transaction with a resource.

C Declaration `tibems_status tibemsXAResource_Start(
tibemsXAResource xaResource,
XID* xid,
tibems_int flags);`

COBOL Call `CALL "tibemsXAResource_Start"
USING BY VALUE xaResource,
BY REFERENCE xid,
BY VALUE flags,
RETURNING tibems-status
END-CALL.`



xaResource and xid have usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| xaResource | Associate a transaction with this resource. |
| xid | Associate this transaction with a resource. |
| flags | TMNOFLAGS—This is a new transaction, which was not previously associated with the resource. TMRESUME—This transaction was previously associated with the resource. |

tibemsXASession

Type

Purpose A session with an XA resource.

| Function | Description | Page |
|---|---|------|
| tibemsXASession_Close | Close an XA session. | 382 |
| tibemsXASession_GetSession | Get the EMS session from an XA session. | 383 |
| tibemsXASession_GetXAResource | Get the XA resource of an XA session. | 384 |



XA sessions do not support routed queues.

See Also [tibemsSession](#) on page 294

tibemsXASession_Close

Function

Purpose Close an XA session.

C Declaration `tibems_status tibemsXASession_Close(
tibemsSession session);`

COBOL Call `CALL "tibemsXASession_Close"
USING BY VALUE session,
RETURNING tibems-status
END-CALL.`



session has usage pointer.

Parameters

| Parameter | Description |
|-----------|---------------------|
| session | Close this session. |

tibemsXASession_GetSession

Function

Purpose Get the EMS session from an XA session.

C Declaration `tibems_status tibemsXASession_GetSession(
tibemsSession xaSession,
tibemsSession* session);`

COBOL Call `CALL "tibemsXASession_GetSession"
USING BY VALUE xaSession,
BY REFERENCE session,
RETURNING tibems-status
END-CALL.`



xaSession and session have usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| xaSession | Get the EMS session from this XA session. |
| session | The function stores the EMS session in this location. |

tibemsXASession_GetXAResource

Function

Purpose Get the XA resource of an XA session.

C Declaration `tibems_status tibemsXASession_GetXAResource(
tibemsSession session,
tibemsXAResource* xaResource);`

COBOL Call `CALL "tibemsXASession_GetXAResource"
USING BY VALUE session,
BY REFERENCE xaResource,
RETURNING tibems-status
END-CALL.`



session and xaResource have usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| session | Get the XA resource from this session. |
| xaResource | The function stores the resource in this location. |

Chapter 13 **Types**

This chapter presents types in general use.

Topics

- [Uniform Types, page 386](#)

Uniform Types

Purpose Standard datatypes.

C Declarations

```
typedef char tibems_byte;
typedef short tibems_short;
typedef unsigned short tibems_wchar;
typedef int tibems_int;
typedef TIBX_I64 tibems_long;

typedef float tibems_float;
typedef double tibems_double;

typedef unsigned int tibems_uint;

typedef enum {
    TIBEMS_FALSE = 0,
    TIBEMS_TRUE = 1
} tibems_bool;
```

Table 14 EMS Types

| Type | |
|---------------|---------------------------|
| tibems_byte | |
| tibems_short | |
| tibems_wchar | wide character; 2 bytes |
| tibems_int | |
| tibems_long | |
| tibems_float | |
| tibems_double | |
| tibems_uint | |
| tibems_bool | TIBEMS_FALSE, TIBEMS_TRUE |

Chapter 14 **Utilities**

This chapter presents utility functions.

Topics

- [Utility Functions, page 388](#)

Utility Functions

The following functions are not related to a specific data type.

| Function | Description | Page |
|--|--|------|
| <code>tibems_Close</code> | Deallocate the memory used by the EMS internal global data structures. | 391 |
| <code>tibems_GetAllowCloseInCallback</code> | Gets whether the client application is allowed to call close or stop functions inside message listener callbacks. | 392 |
| <code>tibems_GetConnectAttemptCount</code> | Return the connection attempts limit. | 393 |
| <code>tibems_GetConnectAttemptDelay</code> | Return the connection delay. | 394 |
| <code>tibems_GetConnectAttemptTimeout</code> | Return the connection timeout. | 395 |
| <code>tibems_GetExceptionOnFTEvents</code> | Detects whether exception listener is called on any of the following fault-tolerant events: disconnected, each reconnect attempt, reconnected. | 396 |
| <code>tibems_GetExceptionOnFTSwitch</code> | Detects whether exception listener is called on a fault-tolerant switchover. | 397 |
| <code>tibems_GetMulticastDaemon</code> | Gets the port of the multicast daemon that this application connects to. | 398 |
| <code>tibems_GetMulticastEnabled</code> | Gets whether message consumers subscribed to multicast-enabled topics in EMS client applications can receive messages over multicast. | 399 |
| <code>tibems_GetReconnectAttemptCount</code> | Return the reconnection attempts limit. | 400 |
| <code>tibems_GetReconnectAttemptDelay</code> | Return the reconnection delay. | 401 |
| <code>tibems_GetReconnectAttemptTimeout</code> | Return the reconnection timeout. | 402 |
| <code>tibems_GetSocketReceiveBufferSize</code> | Return the size of socket receive buffers. | 403 |
| <code>tibems_GetSocketSendBufferSize</code> | Return the size of socket send buffers. | 404 |

| Function | Description | Page |
|---|--|------|
| <code>tibems_IsConsumerMulticast</code> | Checks if a consumer can receive messages over multicast. | 405 |
| <code>tibems_Open</code> | Allocate the global memory for the EMS library. | 406 |
| <code>tibems_SetAllowCloseInCallback</code> | Sets whether client applications can close sessions or connections, or stop connections, inside message listener callbacks. | 407 |
| <code>tibems_SetConnectAttemptCount</code> | Modify the connection attempt limit. | 408 |
| <code>tibems_SetConnectAttemptDelay</code> | Modify the connection delay. | 409 |
| <code>tibems_SetConnectAttemptTimeout</code> | Modify the connection timeout. | 410 |
| <code>tibems_SetExceptionOnFTEvents</code> | Sets whether exception listener is called each step of the fault-tolerant switchover process. | 411 |
| <code>tibems_setExceptionOnFTSwitch</code> | Sets whether exception listener is called on fault-tolerant switchover. | 412 |
| <code>tibems_SetMulticastDaemon</code> | Sets the port on which the EMS client will connect to the multicast daemon. | 413 |
| <code>tibems_SetMulticastEnabled</code> | Set whether message consumers subscribed to multicast-enabled topics in the EMS client application will receive messages over multicast. | 414 |
| <code>tibems_SetMulticastExceptionListener</code> | Sets the multicast exception listener for an application. | 415 |
| <code>tibems_SetReconnectAttemptCount</code> | Modify the reconnection attempts limit. | 416 |
| <code>tibems_SetReconnectAttemptDelay</code> | Modify the reconnection delay. | 417 |
| <code>tibems_SetReconnectAttemptTimeout</code> | Modify the reconnection timeout. | 418 |
| <code>tibems_SetSocketReceiveBufferSize</code> | Set the size of socket receive buffers. | 419 |
| <code>tibems_SetSocketSendBufferSize</code> | Set the size of socket send buffers. | 420 |

| Function | Description | Page |
|----------------------------------|---|------|
| <code>tibems_SetTraceFile</code> | Start or stop directing client trace information to a file. | 421 |
| <code>tibems_Sleep</code> | Sleep thread. | 422 |
| <code>tibems_Version</code> | Return the EMS library version number. | 423 |

tibems_Close

Function

| | |
|----------------------|--|
| Purpose | Deallocate the memory used by the EMS internal global data structures. |
| C Declaration | <code>void tibems_close(void);</code> |
| COBOL Call | <pre>CALL "tibems_close" RETURNING tibems-Return-Value END-CALL.</pre> |
| Remarks | <p>Before unloading the EMS library, you must call this function to clean up. Windows platforms allow selective unloading of DLLs.</p> <p>Applications that call tibems_Open and <code>tibems_Close</code> one or more times will allocate and deallocate correctly as long as the close calls match the open calls.</p> |
| See Also | tibems_Open on page 406 |

tibems_GetAllowCloseInCallback

Function

Purpose Gets whether the client application is allowed to call close or stop functions inside message listener callbacks.

C Declaration `tibems_status tibems_GetAllowCloseInCallback(
tibems_bool *isAllowed);`

COBOL Call `CALL "tibems_GetAllowCloseInCallback"
USING BY REFERENCE isAllowed,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | isAllowed | Returns true when the client application does not return with a TIBEMS_ILLEGAL_STATE error status before closing a session or connection or stopping a connection inside a message listener callback. Returns false if the application returns with this error in such a situation. |

See Also [tibems_SetAllowCloseInCallback on page 407](#)

tibems_GetConnectAttemptCount

Function

Purpose Return the connection attempts limit.

C Declaration `tibems_int tibems_GetConnectAttemptCount(void);`

COBOL Call CALL "tibems_GetConnectAttemptCount"
RETURNING tibems-Return-Value
END-CALL.

Remarks This setting governs all client [tibemsConnection](#) objects, limiting the number of times that connection objects attempt to establish a connection to the server. The default value is 2. The minimum value is 1.

See Also [tibems_SetConnectAttemptCount](#) on page 408

[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_GetConnectAttemptDelay

Function

| | |
|---------------|--|
| Purpose | Return the connection delay. |
| C Declaration | <code>tibems_int tibems_GetConnectAttemptDelay(void);</code> |
| COBOL Call | <code>CALL "tibems_GetConnectAttemptDelay" RETURNING tibems-Return-Value END-CALL.</code> |
| Remarks | This setting governs all client <code>tibemsConnection</code> objects. It determines the delay time between successive attempt to establish a connection to the server. Its value is the time (in milliseconds) between connection attempts. The default value is 500. The minimum value is 250. |
| See Also | tibems_SetConnectAttemptDelay on page 409 Setting Connection Attempts, Timeout and Delay Parameters in the <i>TIBCO Enterprise Message Service User's Guide</i> |

tibems_GetConnectAttemptTimeout

Function

Purpose Return the connection timeout.

C Declaration `tibems_int tibems_GetConnectAttemptTimeout(void);`

COBOL Call CALL "tibems_GetConnectAttemptTimeout"
RETURNING tibems-Return-Value
END-CALL.

Remarks This setting governs all client [tibemsConnection](#) objects. It determines the maximum time (in milliseconds) the client allows to establish a connection to the server. The default value is 0, indicating no timeout.

See Also [tibems_SetConnectAttemptTimeout](#) on page 410
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_GetExceptionOnFTEvents

Function

Purpose Detects whether exception listener is called on any of the following fault-tolerant events: disconnected, each reconnect attempt, reconnected.

C Declaration `tibems_status tibems_GetExceptionOnFTEvents(
tibems_bool* isSet);`

COBOL Call `CALL "tibems_GetExceptionOnFTEvents"
USING BY REFERENCE isSet,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter Description | |
|------------|-----------------------|---|
| | Parameter | Description |
| | isSet | Returns true if the exception listener is to be called on any of the following fault-tolerant events: disconnected, each reconnect attempt, reconnected. Returns false if it is not to be called. Default is false. |

See Also [tibems_SetExceptionOnFTEvents on page 411](#)
[Setting an Exception Listener](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_GetExceptionOnFTSwitch

Function

Purpose Detects whether exception listener is called on a fault-tolerant switchover.

C Declaration `tibems_status tibems_GetExceptionOnFTSwitch(
tibems_bool* isSet);`

COBOL Call `CALL "tibems_GetExceptionOnFTSwitch"
USING BY REFERENCE isSet,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| isSet | Returns true if the exception listener is to be called on a fault-tolerant switchover and false if it is not to be called. Default is false. |

See Also [tibems_setExceptionOnFTSwitch on page 412](#)
[Setting an Exception Listener](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_GetMulticastDaemon

Function

Purpose Gets the port of the multicast daemon that this application connects to.

C Declaration `const char* tibems_GetMulticastDaemon(void);`

Remarks Gets the port of the multicast daemon that this application connects to.

See Also [tibems_SetMulticastDaemon on page 413](#)
[Chapter 14, Using Multicast](#), in the *TIBCO Enterprise Message Service User's Guide*

tibems_GetMulticastEnabled

Function

Purpose Gets whether message consumers subscribed to multicast-enabled topics in EMS client applications can receive messages over multicast.

C Declaration `tibems_bool tibems_GetMulticastEnabled(void);`

Remarks Gets whether message consumers subscribed to multicast-enabled topics in EMS client applications can receive messages over multicast.

See [Chapter 14, Using Multicast](#), in the *TIBCO Enterprise Message Service User's Guide*, for more information.

See Also [tibems_SetMulticastEnabled on page 414](#)
[tibemsConnectionFactory_SetMulticastEnabled on page 277](#)

tibems_GetReconnectAttemptCount

Function

Purpose Return the reconnection attempts limit.

C Declaration `tibems_int tibems_GetReconnectAttemptCount(void);`

COBOL Call CALL "tibems_GetReconnectAttemptCount"
RETURNING tibems-Return-Value
END-CALL.

Remarks This setting governs all client `tibemsConnection` objects limiting the number of times that they attempt to reconnect to the server after a network disconnect. The default value is 4. The minimum value is 1.

See Also [tibems_GetConnectAttemptCount on page 393](#)
[tibems_SetReconnectAttemptCount on page 416](#)
[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibems_GetReconnectAttemptDelay

Function

Purpose Return the reconnection delay.

C Declaration `tibems_int tibems_GetReconnectAttemptDelay(void);`

COBOL Call CALL "tibems_GetReconnectAttemptDelay"
RETURNING tibems-Return-Value
END-CALL.

Remarks This setting governs all client [tibemsConnection](#) objects. It determines the delay time between successive attempt to establish a connection to the server. Its value is the time (in milliseconds) between connection attempts. The default value is 500. The minimum value is 250.

See Also [tibems_GetConnectAttemptDelay on page 394](#)
[tibems_SetReconnectAttemptDelay on page 417](#)
[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibems_GetReconnectAttemptTimeout

Function

| | |
|---------------|---|
| Purpose | Return the reconnection timeout. |
| C Declaration | <code>tibems_int tibems_GetReconnectAttemptTimeout(void);</code> |
| COBOL Call | <code>CALL "tibems_GetReconnectAttemptTimeout" RETURNING tibems-Return-Value END-CALL.</code> |
| Remarks | This setting governs all client tibemsConnection objects. It determines the maximum time (in milliseconds) to client will allow to reestablish a connection to the server. The default value is 0, indicating no timeout. The minimum value is 250. |
| See Also | tibems_SetReconnectAttemptTimeout on page 418 Setting Reconnection Failure Parameters in the <i>TIBCO Enterprise Message Service User's Guide</i> . |

tibems_GetSocketReceiveBufferSize

Function

Purpose Return the size of socket receive buffers.

C Declaration `tibems_int tibems_GetSocketReceiveBufferSize(void);`

COBOL Call CALL "tibems_GetSocketReceiveBufferSize"
RETURNING tibems-Return-Value
END-CALL.

Remarks When set, this value overrides the operating system's default for the size of receive buffers associated with sockets that the client uses for connections to the server. (Some operating systems do not allow you to override the default size.)

See Also [tibems_SetSocketReceiveBufferSize on page 419](#)

tibems_GetSocketSendBufferSize

Function

| | |
|---------------|--|
| Purpose | Return the size of socket send buffers. |
| C Declaration | <code>tibems_int tibems_GetSocketSendBufferSize(void);</code> |
| COBOL Call | <code>CALL "tibems_GetSocketSendBufferSize" RETURNING tibems-Return-Value END-CALL.</code> |
| Remarks | When set, this value overrides the operating system's default for the size of send buffers associated with sockets that the client uses for connections to the server. (Some operating systems do not allow you to override the default size.) |
| See Also | tibems_SetSocketSendBufferSize on page 420 |

tibems_IsConsumerMulticast

Function

Purpose Checks if a consumer can receive messages over multicast.

C Declaration `tibems_bool tibems_IsConsumerMulticast(
 tibemsMsgConsumer consumer,
 tibems_bool *isMulticast);`

Remarks It is possible for a consumer to be a multicast consumer yet only receive messages over TCP. This may happen when the consumer is created on a wildcard destination that includes both unicast and multicast topics.

See Also [tibems_SetSocketSendBufferSize on page 420](#)

tibems_Open

Function

| | |
|---------------|---|
| Purpose | Allocate the global memory for the EMS library. |
| C Declaration | <code>void tibems_Open(void);</code> |
| COBOL Call | <code>CALL "tibems_Open"</code> RETURNING <code>tibems-Return-Value</code> END-CALL. |
| Remarks | <p>Applications that do not call <code>tibems_Open</code> will work as expected because the EMS internal global data structures are allocated when any public EMS function is called. However, the EMS data structures will not be deallocated until the application calls the tibems_Close function or exits.</p> <p>Existing Windows applications that only call the tibems_Close function will work as expected.</p> <p>Applications that call <code>tibems_Open</code> and tibems_Close one or more times will allocate and deallocate correctly as long as the close calls match the open calls.</p> |
| See Also | tibems_Close on page 391 |

tibems_SetAllowCloseInCallback

Function

Purpose Sets whether client applications can close sessions or connections, or stop connections, inside message listener callbacks.

C Declaration `tibems_status tibems_SetAllowCloseInCallback(
tibems_bool allow);`

COBOL Call `CALL "tibems_SetAllowCloseInCallback",
USING BY VALUE isAllowed,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | allow | When true, the application will proceed without waiting for the message callbacks to return before closing a session or a connection or before stopping a connection. When false, the application will get a TIBEMS_ILLEGAL_STATE error status. By default, the application gets a TIBEMS_ILLEGAL_STATE status. |

Remarks This function can be used to change the default EMS client behavior and set whether the client application can call the `tibemsSession_Close`, `tibemsConnection_Close` or `tibemsConnection_Stop` functions from the `tibemsMsgCallback`.



According to the JMS 2.0 specification, calling any of these functions is not allowed and must return an error. If calling them inside the callback is allowed, then these functions when called inside the callback do not return an error and will proceed without waiting for the same callback to return.

The default behavior is to return with a TIBEMS_ILLEGAL_STATE status and parallel the behavior specified in the JMS 2.0 specification, which the EMS client API adheres to. However, this function allows applications to override the default behavior and close or stop EMS objects inside message callbacks.

See Also [tibemsMsgCallback on page 174](#)
[tibemsMsgConsumer_Close on page 165](#)
[tibemsConnection_Close on page 212](#)
[tibemsSession_Close on page 297](#)
[tibems_GetAllowCloseInCallback on page 392](#)

tibems_SetConnectAttemptCount

Function

Purpose Modify the connection attempt limit.

C Declaration `tibems_status tibems_SetConnectAttemptCount(
tibems_int count);`

COBOL Call `CALL "tibems_SetConnectAttemptCount"
USING BY VALUE count,
RETURNING tibems-status
END-CALL.`

Remarks This setting governs all client `tibemsConnection` objects, limiting the number of times that connection objects attempt to establish a connection to the server.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | count | Set the connect attempt limit to this value. The default value is 2. The minimum value is 1. |

See Also [tibems_GetConnectAttemptCount on page 393](#)
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_SetConnectAttemptDelay

Function

Purpose Modify the connection delay.

C Declaration `tibems_status tibems_SetConnectAttemptDelay(
tibems_int delay);`

COBOL Call `CALL "tibems_SetConnectAttemptDelay"
USING BY VALUE delay,
RETURNING tibems-status
END-CALL.`

Remarks This setting governs all client `tibemsConnection` objects. It determines the delay time between successive attempt to establish a connection to the server. Its value is the time (in milliseconds) between connection attempts.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | delay | Set the connect attempt delay to this time (in milliseconds). |
| | | The default value is 500. The minimum value is 250. |

See Also [tibems_GetConnectAttemptDelay on page 394](#)
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_SetConnectAttemptTimeout

Function

Purpose Modify the connection timeout.

C Declaration `tibems_status tibems_SetConnectAttemptTimeout(
tibems_int timeout);`

COBOL Call `CALL "tibems_SetConnectAttemptTimeout"
USING BY VALUE timeout,
RETURNING tibems-status
END-CALL.`

Remarks This setting governs all client `tibemsConnection` objects. It determines the maximum time (in milliseconds) the client allows to establish a connection to the server.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | timeout | Set the connect attempt timeout to this time (in milliseconds). Zero is a special value, which specifies no timeout. The default value is 0. |

See Also [tibems_GetConnectAttemptTimeout on page 395](#)
[Setting Connection Attempts, Timeout and Delay Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_SetExceptionOnFTEvents

Function

Purpose Sets whether exception listener is called each step of the fault-tolerant switchover process.

C Declaration `tibems_status tibems_SetExceptionOnFTEvents(
tibems_bool* callExceptionListener);`

COBOL Call `CALL "tibems_SetExceptionOnFTEvents"
USING BY VALUE callExceptionListener,
RETURNING tibems-status
END-CALL.`

Remarks This setting determines exception behavior when the fault-tolerant client goes through phases in the failover process. If an exception listener is set on the connection, the callback is invoked when the client detects:

- Disconnection, or TIBEMS_SERVER_DISCONNECTED.
- Each reconnect attempt, or TIBEMS_SERVER_RECONNECTING.
- Reconnection to the server, or TIBEMS_SERVER_RECONNECTED.

This call reports on all events during the failover process. To report only the successful reconnection event, use the [tibems_setExceptionOnFTSwitch](#) method instead.

Parameters

| Parameter | Description |
|------------------------------------|---|
| <code>callExceptionListener</code> | <p>When true, the connection's <code>ExceptionHandler</code> catches an exception, which contains a status code indicating the state of the fault-tolerant failover: TIBEMS_SERVER_DISCONNECTED, TIBEMS_SERVER_RECONNECTING, or TIBEMS_SERVER_RECONNECTED</p> <p>When false, fault-tolerant failover does not trigger an exception in the client.</p> |

See Also [tibems_GetExceptionOnFTEvents](#) on page 396
[tibems_setExceptionOnFTSwitch](#) on page 412

[Setting an Exception Listener](#) in the *TIBCO Enterprise Message Service User's Guide*

tibems_setExceptionOnFTSwitch

Function

Purpose Sets whether exception listener is called on fault-tolerant switchover.

C Declaration `tibems_status tibems_setExceptionOnFTSwitch(
tibems_bool callExceptionListener);`

COBOL Call `CALL "tibems_setExceptionOnFTSwitch"
USING BY VALUE callExceptionListener,
RETURNING tibems-status
END-CALL.`

Remarks This setting determines exception behavior when the client successfully switches to a different server (fault-tolerant failover).

| Parameters | Parameter | Description |
|------------|-----------------------|--|
| | callExceptionListener | When true, the connection's ExceptionListener catches an exception, which contains the name of the new server. When false, fault-tolerant failover does not trigger an exception in the client. |

See Also [tibems_GetExceptionOnFTSwitch on page 397](#)
[tibems_GetExceptionOnFTEvents on page 396](#)
[Setting an Exception Listener in the TIBCO Enterprise Message Service User's Guide](#)

tibems_SetMulticastDaemon

Function

Purpose Sets the port on which the EMS client will connect to the multicast daemon.

C Declaration `tibems_status tibems_SetMulticastDaemon(
const char* port);`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | port | The multicast daemon port that connections created in this application will connect to. |

Remarks A connection to the multicast daemon is required when multicast is enabled and a consumer is subscribed to a multicast-enabled topic. Setting the port with this method will override the default port supplied by the server and any port specified in a connection factory for all connections in the application.

See Also [tibemsConnectionFactory_SetMulticastDaemon on page 276](#)
[tibems_SetMulticastEnabled on page 414](#)
[Chapter 14, Using Multicast](#), in the *TIBCO Enterprise Message Service User's Guide*

tibems_SetMulticastEnabled

Function

Purpose Set whether message consumers subscribed to multicast-enabled topics in the EMS client application will receive messages over multicast.

C Declaration `tibems_status tibems_SetMulticastEnabled(
tibems_bool enabled);`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | enabled | When true, multicast is enabled for the client. When false, multicast is disabled and the client application will receive all messages over TCP. |

Remarks When enabled, message consumers subscribed to a multicast-enabled topic will receive messages over multicast. By default, multicast is enabled.

tibems_SetMulticastEnabled overrides both the EMS server and factory settings that enable multicast.

See Also [tibemsConnectionFactory_SetMulticastDaemon on page 276](#)

[multicast](#) and [multicast_daemon_default](#) server parameters in the *TIBCO Enterprise Message Service User's Guide*

tibems_SetMulticastExceptionListener

Function

Purpose Sets the multicast exception listener for an application.

C Declaration `tibems_status tibems_SetMulticastExceptionListener(
tibemsMulticastExceptionCallback listener,
void* closure);`

Parameters

| Parameter | Description |
|-----------|--|
| listener | Register this multicast exception listener callback. |
| closure | This parameter receives the closure data in this location, which the program supplied in the call that registered the callback. This is a way to pass application related data to the multicast exception listener callback. |

See Also [tibemsMulticastExceptionCallback on page 234](#)
[Chapter 14, Using Multicast](#), in the *TIBCO Enterprise Message Service User's Guide*

tibems_SetReconnectAttemptCount

Function

Purpose Modify the reconnection attempts limit.

C Declaration `tibems_status tibems_SetReconnectAttemptCount(
tibems_int count);`

COBOL Call `CALL "tibems_SetReconnectAttemptCount"
USING BY VALUE count,
RETURNING tibems-status
END-CALL.`

Remarks This setting governs all client `tibemsConnection` objects as they attempt to reconnect to the server after a network disconnect.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | count | Set the reconnect limit to this value. |
| | | The default value is 4. The minimum value is 1. |

See Also [tibems_GetReconnectAttemptCount on page 400](#)
[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibems_SetReconnectAttemptDelay

Function

Purpose Modify the reconnection delay.

C Declaration `tibems_status tibems_SetReconnectAttemptDelay(
tibems_int delay);`

COBOL Call `CALL "tibems_SetReconnectAttemptDelay"
USING BY VALUE delay,
RETURNING tibems-status
END-CALL.`

Remarks This setting governs all client [tibemsConnection](#) objects. It determines the delay time between successive attempt to establish a connection to the server. Its value is the time (in milliseconds) between connection attempts.

Parameters

| Parameter | Description |
|-----------|---|
| delay | Set the reconnect delay to this value. The default value is 500. The minimum value is 250. |

See Also [tibems_GetReconnectAttemptDelay on page 401](#)
[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibems_SetReconnectAttemptTimeout

Function

Purpose Modify the reconnection timeout.

C Declaration `tibems_status tibems_SetReconnectAttemptTimeout(
tibems_int timeout);`

COBOL Call `CALL "tibems_SetReconnectAttemptTimeout"
USING BY VALUE timeout,
RETURNING tibems-status
END-CALL.`

Remarks This setting governs all client `tibemsConnection` objects. It determines the maximum time (in milliseconds) to client will allow to reestablish a connection to the server.

| Parameters | Parameter | Description |
|------------|-----------|--|
| | timeout | Set the reconnect timeout to this value. Zero is a special value, which specifies no timeout. The default value is 0. |

See Also [tibems_GetReconnectAttemptTimeout on page 402](#)
[Setting Reconnection Failure Parameters](#) in the *TIBCO Enterprise Message Service User's Guide*.

tibems_SetSocketReceiveBufferSize

Function

Purpose Set the size of socket receive buffers.

C Declaration `tibems_status tibems_SetSocketReceiveBufferSize(
tibems_int size);`

COBOL Call `CALL "tibems_SetSocketReceiveBufferSize"
USING BY VALUE size,
RETURNING tibems-status
END-CALL.`

Remarks This value overrides the operating system's default for the size of receive buffers associated with sockets that the client uses for connections to the server.

Use this call before creating server connections. This call sets an override buffer size for new socket buffers; it does not change the size of existing socket buffers.

Parameters

| Parameter | Description |
|-----------|--|
| size | Sockets use receive buffers of this size (in kilobytes). |

See Also [tibems_GetSocketReceiveBufferSize on page 403](#)

tibems_SetSocketSendBufferSize

Function

Purpose Set the size of socket send buffers.

C Declaration `tibems_status tibems_SetSocketSendBufferSize(
tibems_int size);`

COBOL Call `CALL "tibems_SetSocketSendBufferSize"
USING BY VALUE size,
RETURNING tibems-status
END-CALL.`

Remarks This value overrides the operating system’s default for the size of send buffers associated with sockets that the client uses for connections to the server.

Use this call before creating server connections. This call sets an override buffer size for new socket buffers; it does not change the size of existing socket buffers.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | size | Sockets use send buffers of this size (in kilobytes). |

See Also [tibems_GetSocketSendBufferSize on page 404](#)

tibems_SetTraceFile

Function

Purpose Start or stop directing client trace information to a file.

C Declaration

```
tibems_status tibems_SetTraceFile(
    const char* fileName);
```

COBOL Call

```
CALL "tibems_SetTraceFile"
    USING BY REFERENCE fileName,
    RETURNING tibems-status
END-CALL.
```

| Parameters | Parameter | Description |
|------------|-----------|--|
| | fileName | The name of the file to which tracing information should be directed, or NULL to stop directing tracing to a file. |

Remarks This call directs client tracing information to the file specified by the `fileName` argument. This function does not generate tracing; tracing must be enabled separately. Tracing can be enabled using the `set server client_trace` command in the administration tool, or, for SSL tracing, using the [tibemsSSL_SetTrace](#) or `tibemsSSL_SetDebugTrace` function. See the *TIBCO Enterprise Message Service User's Guide* for more information about the administration tool.

To stop sending tracing information to the file and resume regular tracing to `stderr` or `stdout`, call `tibems_SetTraceFile`, passing NULL for `fileName` parameter.

| Status Code | Description |
|----------------------|---|
| TIBEMS_ILLEGAL_STATE | Tracing information is already being directed to a file, and the <code>fileName</code> argument was not NULL. |
| TIBEMS_IO_FAILED | The file specified by <code>fileName</code> could not be opened in append mode. |

tibems_Sleep

Function

Purpose Sleep thread.

C Declaration `void tibems_Sleep(
tibems_long milliseconds);`

COBOL Call `CALL "tibems_Sleep"
USING BY VALUE milliseconds
END-CALL.`



COBOL usage of milliseconds is COMP-2.

Parameters

| Parameter | Description |
|--------------|--|
| milliseconds | Sleep for this interval (in milliseconds). |

Remarks This call instructs its calling thread to sleep for a fixed interval (in milliseconds).

tibems_Version

Function

Purpose Return the EMS library version number.

C Declaration `const char* tibems_Version(void);`

COBOL Call `CALL "tibems_Version"
RETURNING tibems-Pointer
END-CALL.`



`tibems-Pointer` has usage pointer.

After this COBOL call, store the `tibems-Pointer` data item to `tibems-Cobol-Char`, using the following SET statement:

`SET ADDRESS OF tibems-Cobol-Char TO tibems-Pointer.`

Remarks This string represents the three-part version number of the release (*major.minor.update*).

Chapter 15 Administration

This chapter documents the C Admin API functions that can be used to query the runtime state of EMS messaging applications.

Topics

- [tibemsAdmin](#), page 427
- [tibemsCollection](#), page 450
- [tibemsConsumerInfo](#), page 455
- [tibemsDetailedDestStat](#), page 479
- [tibemsProducerInfo](#), page 483
- [tibemsQueueInfo](#), page 491
- [tibemsServerInfo](#), page 508
- [tibemsStatData](#), page 514
- [tibemsSubscriptionInfo](#), page 519
- [tibemsTopicInfo](#), page 532

Administration Overview

TIBCO Enterprise Message Service C Admin API provides a C program with the ability to query the `tibemsd` server and obtain information regarding the state of the `tibemsd`, message consumers, producers, topics and queues at runtime. TIBCO Enterprise Message Service C Admin API closely mimics a subset of the Java Admin API query functionality. It does not provide configuration capability.

| | |
|--|--|
| Including the Administration Library | The C Admin API is provided as a separate library. For information about including the C Admin API, see the C Programmer’s Checklist on page 358 of the <i>TIBCO Enterprise Message Service User’s Guide</i> . |
|--|--|

tibemsAdmin

Type

Purpose Represent an administrative connection to the server.

Remarks `tibemsAdmin` provides an administrative connection to the server. To use these functions, first create an administrative connection to the server with `tibemsAdmin_Create`. With that connection you can retrieve information about the server and its components at runtime.

| Function | Description | Page |
|--|--|------|
| <code>tibemsAdmin_Close</code> | Close the administrative connection to the server. | 429 |
| <code>tibemsAdmin_Create</code> | Create an administration connection to a server. | 430 |
| <code>tibemsAdmin_GetCommandTimeout</code> | Get the command timeout. | 432 |
| <code>tibemsAdmin_GetConsumer</code> | Get consumer with specified ID. | 433 |
| <code>tibemsAdmin_GetConsumers</code> | Returns consumers matching specified filters. | 434 |
| <code>tibemsAdmin_GetInfo</code> | Get the current set of server metrics. | 437 |
| <code>tibemsAdmin_GetProducerStatistics</code> | Returns statistical information about producers that match the specified parameters. | 438 |
| <code>tibemsAdmin_GetQueue</code> | Get information about a queue of the given queue name. | 440 |
| <code>tibemsAdmin_GetQueues</code> | Get the queues that match the given pattern and the given permanence type. | 441 |
| <code>tibemsAdmin_GetSubscriptions</code> | Return subscriptions matching the specified filters. | 443 |
| <code>tibemsAdmin_GetTopic</code> | Get the topic for the given topic name. | 445 |
| <code>tibemsAdmin_GetTopics</code> | Get the topics that match the given pattern and the given permanence type. | 446 |
| <code>tibemsAdmin_SetCommandTimeout</code> | Sets the command timeout. | 448 |

| Function | Description | Page |
|--|---|------|
| <code>tibemsAdmin_SetExceptionHandler</code> | Set an exception listener for the connection used by the administration API to communicate with the EMS server. | 448 |

Related Types

- `tibemsCollection` on page 450
- `tibemsConsumerInfo` on page 455
- `tibemsProducerInfo` on page 483
- `tibemsQueueInfo` on page 491
- `tibemsTopicInfo` on page 532

tibemsAdmin_Close

Function

Purpose Close the administrative connection to the server.

C Declaration `tibems_status tibemsAdmin_Close(
tibemsAdmin admin);`

COBOL Call `CALL "tibemsAdmin_Close"
USING BY VALUE admin,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | admin | The administrative connection to be closed. |

See Also [tibemsAdmin_Create on page 430](#)

tibemsAdmin_Create

Function

Purpose Create an administration connection to a server.

C Declaration

```
tibems_status tibemsAdmin_Create(  
    tibemsAdmin* admin,  
    const char* url,  
    const char* userName,  
    const char* password,  
    tibemsSSLParams sslparams);
```

COBOL Call

```
CALL "tibemsAdmin_Create"  
  USING BY REFERENCE admin,  
        BY REFERENCE url,  
        BY REFERENCE userName,  
        BY REFERENCE password,  
        BY VALUE sslParams,  
        RETURNING tibems-status  
END-CALL.
```



sslParams has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| admin | Store the new administrative connection in this location. |
| url | Find the EMS server at this URL. |
| userName | Authenticate the client program to the server with this username. |
| password | Authenticate the client program to the server with this password. |
| sslparams | Establish SSL communication using these parameters. See the section on SSL server parameters in the <i>TIBCO Enterprise Message Service User's Guide</i> for more information. |

Status Codes

| Status Code | Description |
|---|---|
| TIBEMS_SERVER_NOT_CONNECTED | <ul style="list-style-type: none">• No server is running at the specified URL.• The call could not communicate with a server because of mismatched SSL and TCP protocols.• Other error situations are possible. |
| TIBEMS_SECURITY_EXCEPTION | <ul style="list-style-type: none">• The server rejected the connection because the username or password was invalid.• SSL setup is incorrect. |

tibemsAdmin_GetCommandTimeout

Function

Purpose Get the command timeout.

C Declaration `tibems_status tibemsAdmin_GetCommandTimeout(
tibemsAdmin admin,
tibems_long* timeout);`

COBOL Call `CALL "tibemsAdmin_GetCommandTimeout"
USING BY VALUE admin,
BY REFERENCE timeout,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | admin | Get the command timeout of this administrative connection. |
| | timeout | The function stores the timeout in this location. |

Remarks Gets the command timeout in milliseconds. The command timeout determines how long to wait for the server to respond to a command. If the server does not respond within the timeout limit, the command throws an exception. The default timeout is 60000 (60 seconds).

See Also [tibemsAdmin_SetCommandTimeout on page 448](#)

tibemsAdmin_GetConsumer

Function

Purpose Get consumer with specified ID.

C Declaration `tibems_status tibemsAdmin_GetConsumer(
tibemsAdmin admin,
tibemsConsumerInfo* consumerInfo,
tibems_long ID);`

COBOL Call `CALL "tibemsAdmin_GetConsumer"
USING BY VALUE admin,
BY REFERENCE consumerInfo,
BY VALUE consumerID,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|---|
| | admin | Get a consumer using this administrative connection. |
| | consumerInfo | The functions stores information about the consumer in this location. |
| | ID | The consumer ID for which the function will retrieve information. |

Remarks Returns the consumer object with specified ID. The returned consumer object contains information about consumer known to server, including details, available statistics. If a consumer with the specified ID does not exist, the function returns NULL.

| Status Codes | Status Code | Description |
|--------------|------------------|---|
| | TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| | TIBEMS_NOT_FOUND | No consumer found matching the requested ID. |

See Also [tibemsConsumerInfo on page 455](#)

tibemsAdmin_GetConsumers

Function

Purpose Returns consumers matching specified filters.

C Declaration `tibems_status tibemsAdmin_GetConsumers(
tibemsAdmin admin,
tibemsCollection* collection,
tibems_long connectionID,
const char* username,
tibemsDestinationInfo destination,
tibems_bool durable,
tibems_int dataFlags)`

COBOL Call `CALL "tibemsAdmin_GetConsumers"
USING BY VALUE admin,
BY REFERENCE collection,
BY VALUE connectionID,
BY REFERENCE username,
BY VALUE destination,
BY VALUE durable,
BY VALUE dataFlags,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| admin | Get consumers using this administrative connection. |
| collection | The function stores the returned consumer data in the location specified here, as a collection of tibemsConsumerInfo objects. |
| connectionID | connectionID is reserved for future use and must be set to zero. |
| username | If specified, only consumers for connections that use the specified user name will be returned. Specify NULL if all consumers should be returned. |

| Parameter | Description |
|-------------|--|
| destination | <p>If specified, only consumers on destinations of the same type and matching this destination name will be returned. destination can be:</p> <ul style="list-style-type: none"> • A <code>tibemsQueueInfo</code> or <code>tibemsTopicInfo</code> object. • <code>TIBEMS_INVALID_ADMIN_ID</code> to return all consumers. <p>The destination name may include wildcards.</p> |
| durable | <p>When <code>TRUE</code>, this parameter specifies that only durable topic subscribers should be returned.</p> <p>This parameter is applied only to topic subscribers, and when included prevents the function from returning non-durable topic consumers. However, it does not affect which queue consumers are returned.</p> |
| dataFlags | <p>Specifies what information will be returned for each consumer that matches the filter criteria. Possible values for this parameter are:</p> <ul style="list-style-type: none"> • <code>GET_STAT</code>—gets a <code>tibemsStatData</code> for each consumer. • <code>GET_DETAILED_STAT</code>—gets a <code>tibemsCollection</code> of <code>tibemsDetailedDestStat</code> objects for each consumer <p>When no flag is specified, the returned information does not include statistics.</p> <p>If statistics are disabled in the server, no statistics will be returned regardless of the flag specified in this parameter.</p> |

Remarks Returns a list of consumers matching the specified filters. The consumers are returned in a `tibemsCollection`; if no consumers matching the filter criteria exist in the server, then no `tibemsCollection` will be returned.

The returned consumers are not sorted and are placed in the `tibemsCollection` object in any order. Your application may need to sort the consumers into a specific order if required.

Example 1 For example, this call returns all consumers known to the server, but does not include statistical information for each consumer:

```
tibemsAdmin      admin;
tibemsCollection consumerInfoCollection;
tibems_status    status;
status = tibemsAdmin_GetConsumers(admin, &consumerInfoCollection,
0L, NULL, TIBEMS_ADMIN_INVALID_ID, TIBEMS_FALSE, 0);
```

Example 2 This call returns all queue consumers and all durable topic consumers:

```
tibemsAdmin      admin;
tibemsCollection consumerInfoCollection;
tibems_status     status;
status = tibemsAdmin_GetConsumers(admin, &consumerInfoCollection,
OL, NULL, TIBEMS_ADMIN_INVALID_ID, TIBEMS_TRUE, 0);
```

Example 3 This call returns all durable topic consumers that subscribe to any topic matching topic news.*. If statistics are enabled in the server, the returned tibemsConsumerInfo objects will include detailed statistics about the consumers.

```
tibemsAdmin      admin;
tibemsCollection consumerInfoCollection;
tibems_status     status;
tibemsTopicInfo  topicInfo;

status = tibemsTopicInfoCreate(&topicInfo, "news.*");
status = tibemsAdmin_GetConsumers(admin, &consumerInfoCollection,
OL, NULL, topicInfo, TIBEMS_TRUE, TIBEMS_GET_DETAILED_STAT);
```

Example 4 This call returns all queue consumers created by user OrderProcessor and receiving messages from all queues matching name purchase.order.>. Each tibemsConsumerInfo object will include the full statistics available for the consumer.

```
tibemsAdmin      admin;
tibemsCollection consumerInfoCollection;
tibems_status     status;
tibemsQueueInfo  queueInfo;

status = tibemsQueueInfoCreate(&queueInfo, "purchase.order.>");
status = tibemsAdmin_GetConsumers(admin, &consumerInfoCollection,
OL, "OrderProcessor", queueInfo, TIBEMS_FALSE,
TIBEMS_GET_DETAILED_STAT);
```

Status Codes

| Status Code | Description |
|------------------|---|
| TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| TIBEMS_NOT_FOUND | No consumers found matching the specified filters. |

See Also [tibemsStatData on page 514](#)
[tibemsDetailedDestStat on page 479](#)

tibemsAdmin_GetInfo

Function

Purpose Get the current set of server metrics.

C Declaration `tibems_status tibemsAdmin_GetInfo(
tibemsAdmin admin,
tibemsServerInfo* serverInfo);`

COBOL Call `CALL "tibemsAdmin_GetInfo"
USING BY VALUE admin,
BY REFERENCE serverInfo,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------|--|
| admin | Get server metrics using this administrative connection. |
| serverInfo | The function stores the server metrics in this location. |

Status Codes

| Status Code | Description |
|----------------|---|
| TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |

tibemsAdmin_GetProducerStatistics

Function

Purpose Returns statistical information about producers that match the specified parameters.

C Declaration `tibems_status tibemsAdmin_GetProducerStatistics(
tibemsAdmin admin,
tibemsCollection* collection,
tibems_long connectionID,
const char* username,
tibemsDestinationInfo destination);`

COBOL Call `CALL "tibemsAdmin_GetProducerStatistics"
USING BY VALUE admin,
BY REFERENCE prodInfos,
BY REFERENCE username,
BY VALUE connectionID,
BY VALUE destination,
RETURNING tibems-status
END-CALL.`



prodInfos has usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| admin | Get the producer statistics using this administrative connection. |
| collection | The function stores the returned producer data in the location specified here, as a collection of tibemsProducerInfo objects. |
| connectionID | Must be set to zero. This parameter is reserved for future use. |
| username | If specified, only producers for connections that use the specified user name will be returned. Specify NULL if all producers should be returned. |

| Parameter | Description |
|-------------|--|
| destination | <p>If specified, only producers on destinations of the same type and matching this destination name will be returned. destination can be:</p> <ul style="list-style-type: none">• A tibemsQueueInfo or tibemsTopicInfo object.• TIBEMS_INVALID_ADMIN_ID to return all producers. <p>The destination name may include wildcards.</p> |

Remarks Returns information about message producers, including the statistical information about producers with specified parameters.

| Status Codes | Status Code | Description |
|--------------|------------------|---|
| | TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| | TIBEMS_NOT_FOUND | No producers found matching the specified parameters. |

See Also [tibemsStatData on page 514](#)
[tibemsDetailedDestStat on page 479](#)

tibemsAdmin_GetQueue

Function

Purpose Get information about a queue of the given queue name.

C Declaration `tibems_status tibemsAdmin_GetQueue(
tibemsAdmin admin,
tibemsQueueInfo* queueInfo,
const char* queueName);`

COBOL Call `CALL "tibemsAdmin_GetQueue"
USING BY VALUE admin,
BY REFERENCE queueInfo,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | admin | Get information about a queue using this administrative connection. |
| | queueInfo | The function will store information about the specified queue in this location. |
| | queueName | The name of the queue for which information will be retrieved. |

Remarks This function gets a `tibemsQueueInfo` object for the specified queue name. If the `queueName` does not exist, the function returns `TIBEMS_NOT_FOUND`.

| Status Codes | Status Code | Description |
|--------------|------------------|---|
| | TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| | TIBEMS_NOT_FOUND | No queue found matching the specified <code>queueName</code> . |

See Also [tibemsQueueInfo on page 491](#)

tibemsAdmin_GetQueues

Function

Purpose Get the queues that match the given pattern and the given permanence type.

C Declaration

```
tibems_status tibemsAdmin_GetQueues(  
    tibemsAdmin admin,  
    tibemsCollection* collection,  
    const char* pattern,  
    tibems_int permType);
```

COBOL Call

```
CALL "tibemsAdmin_GetQueues"  
  USING BY VALUE admin,  
        BY REFERENCE collection,  
        BY REFERENCE pattern,  
        BY VALUE permType,  
        RETURNING tibems-status  
END-CALL.
```



collection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| admin | Get information about queues using this administration connection. |
| collection | The function stores the returned queue data in the location specified here, as a collection of tibemsQueueInfo objects. |
| pattern | <p>The queue name pattern that must be matched.</p> <p>The pattern may contain the wildcards * and >. A pattern of > or NULL will return all queues that exist in the server. See the <i>TIBCO Enterprise Message Service User's Guide</i> for information about working with wildcards in queues.</p> |

| Parameter | Description |
|-----------|---|
| permType | <p>The permanence type of the queue must match the type given here. Possible permanence types are:</p> <ul style="list-style-type: none">TIBEMS_DEST_GET_ALL – Return all queues that match the pattern.TIBEMS_DEST_GET_STATIC – Return only static queues that match the pattern.TIBEMS_DEST_GET_DYNAMIC – Return only dynamic queues that match the pattern.TIBEMS_DEST_GET_NOTEMP – Do not return any temporary queues. <p>A NULL value matches all queues.</p> |

Status Codes

| Status Code | Description |
|------------------|---|
| TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| TIBEMS_NOT_FOUND | No queues found matching the specified pattern and performance type. |

See Also [tibemsQueueInfo](#) on page 491

tibemsAdmin_GetSubscriptions

Function

Purpose Return subscriptions matching the specified filters.

C Declaration

```
tibems_status tibemsAdmin_GetSubscriptions(  
    tibemsAdmin admin,  
    tibemsCollection* collection,  
    tibems_int filterFlags,  
    const char* name,  
    const char* topicName);
```

COBOL Call

```
CALL "tibemsAdmin_GetSubscriptions"  
  USING BY VALUE admin,  
        BY REFERENCE collection,  
        BY VALUE filterFlags,  
        BY REFERENCE name,  
        BY REFERENCE topicName,  
        RETURNING tibems-status  
END-CALL.
```



collection has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| admin | Get information about subscriptions using this administration connection. |
| collection | The function stores the returned subscription data in the location specified here, as a collection of tibemsSubscriptionInfo objects. |
| filterFlags | Value can be any combination of the flags: <ul style="list-style-type: none">TIBEMS_SUBSCRIPTIONS_FILTER_DURABLE_ONLYTIBEMS_SUBSCRIPTIONS_FILTER_NO_DURABLETIBEMS_SUBSCRIPTIONS_FILTER_SHARED_ONLYTIBEMS_SUBSCRIPTIONS_FILTER_NO_SHARED |
| name | Specifies that only subscriptions with this name should be returned. |
| topicName | Specifies that only subscriptions on this topic name should be returned. |

Remarks Returns a list of all subscriptions that match the specified filters. The subscriptions are returned in a `tibemsCollection`; if no subscription matching the filter criteria exist in the server, then no `tibemsCollection` is returned.

The returned subscriptions are not sorted and are placed in the `tibemsCollection` object in any order. Your application may need to sort the subscriptions into a specific order.

For example, the following returns all shared subscriptions known to the server:

```
tibemsAdmin      admin;
tibemsCollection subscriptionsInfo;
tibems_status    status;
status = tibemsAdim_GetSubscriptions(admin, &subscriptionsInfo, 0,
NULL, NULL);
```

The following returns all durable (shared or not shared) subscriptions known to the server:

```
tibemsAdmin      admin;
tibemsCollection subscriptionsInfo;
tibems_status    status;
status = tibemsAdim_GetSubscriptions(admin, &subscriptionsInfo,
TIBEMS_SUBSCRIPTIONS_FILTER_DURABLE_ONLY, NULL, NULL);
```

The following returns all shared durable subscriptions on any topic matching topic news.*:

```
tibemsAdmin      admin;
tibemsCollection subscriptionsInfo;
tibems_status    status;
status = tibemsAdim_GetSubscriptions(admin, &subscriptionsInfo,
TIBEMS_SUBSCRIPTIONS_FILTER_DURABLE_ONLY +
TIBEMS_SUBSCRIPTIONS_FILTER_SHARED_ONLY, NULL, "news.*");
```

Status Codes

| Status Code | Description |
|------------------|---|
| TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| TIBEMS_NOT_FOUND | No subscription found matching the specified filters. |

tibemsAdmin_GetTopic

Function

Purpose Get the topic for the given topic name.

C Declaration `tibems_status tibemsAdmin_GetTopic(
tibemsAdmin admin,
tibemsTopicInfo* topicInfo,
const char* topicName);`

COBOL Call `CALL "tibemsAdmin_GetTopic"
USING BY VALUE admin,
BY REFERENCE topicInfo,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | admin | Get information about a topic using this administrative connection. |
| | topicInfo | The function stores information about the topic in this location. |
| | topicName | The name of the topic for which information will be retrieved. |

Remarks This function gets a `tibemsTopicInfo` object for the specified topic name. If the `topicName` does not exist, the function returns `TIBEMS_NOT_FOUND`.

| Status Codes | Status Code | Description |
|--------------|------------------|---|
| | TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| | TIBEMS_NOT_FOUND | No topic found matching the specified <code>topicName</code> . |

See Also [tibemsTopicInfo on page 532](#)

tibemsAdmin_GetTopics

Function

Purpose Get the topics that match the given pattern and the given permanence type.

C Declaration `tibems_status tibemsAdmin_GetTopics(
tibemsAdmin admin,
tibemsCollection* collection,
const char* pattern,
tibems_int permType);`

COBOL Call `CALL "tibemsAdmin_GetTopics"
USING BY VALUE admin,
BY REFERENCE collection,
BY REFERENCE pattern,
BY VALUE permType,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| admin | Get information about topics using this administrative connection. |
| collection | The function stores the returned topic data in the location specified here, as a collection of tibemsTopicInfo objects. |
| pattern | The topic name pattern that must be matched. The pattern may contain the wildcards * and >. A pattern of > or NULL will return all topics. See the <i>TIBCO Enterprise Message Service User's Guide</i> for information about working with wildcards in topics. |

| Parameter | Description |
|-----------|---|
| permType | <p>The permanence type of the topic must match the type given here. Possible permanence types are:</p> <ul style="list-style-type: none">• TIBEMS_DEST_GET_ALL – Return all topics that match the pattern.• TIBEMS_DEST_GET_STATIC – Return only static topics that match the pattern.• TIBEMS_DEST_GET_DYNAMIC – Return only dynamic topics that match the pattern.• TIBEMS_DEST_GET_NOTEMP – Do not return any temporary topics. <p>A NULL value matches all topics.</p> |

Status Codes

| Status Code | Description |
|------------------|---|
| TIBEMS_TIMEOUT | The administrative query timed out while waiting for a server response. |
| TIBEMS_NOT_FOUND | No topics found matching the specified pattern and performance type. |

See Also [tibemsTopicInfo on page 532](#)

tibemsAdmin_SetCommandTimeout

Function

Purpose Sets the command timeout.

C Declaration `tibems_status tibemsAdmin_SetCommandTimeout(
tibemsAdmin admin,
tibems_long timeout);`

COBOL Call `CALL "tibemsAdmin_SetCommandTimeout"
USING BY VALUE admin,
BY VALUE timeout,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|---|
| admin | Set the command timeout on this administrative connection. |
| timeout | The length of time, in milliseconds, to wait for the server to respond to a command. When not specified, the default command timeout is 60000 (60 seconds). |

Remarks Sets the command timeout. The command timeout determines how long, in milliseconds, the command waits for the server to respond. If the server does not respond within the timeout limit, the command throws an exception. The default timeout is 60000 (60 seconds).

See Also [tibemsAdmin_GetCommandTimeout on page 432](#)

tibemsAdmin_SetExceptionListener

Function

Purpose Set an exception listener for the connection used by the administration API to communicate with the EMS server.

C Declaration

```
tibems_status tibemsAdmin_SetExceptionListener(
    tibemsAdmin admin,
    tibemsExceptionCallback listener,
    const void* closure);
```

COBOL Call

```
CALL "tibemsAdmin_SetExceptionListener_STL"
  USING BY VALUE admin,
        BY REFERENCE tibems-AdminException-Status,
        BY VALUE TIBEMS-NULLPTR,
        RETURNING tibems-status
END-CALL.
```

Parameters

| Parameter | Description |
|-----------|--|
| admin | Resister the exception listener callback on this administration connection. |
| listener | Register this exception listener callback. For more information about exception listeners, see the <i>TIBCO Enterprise Message Service User's Guide</i> . |
| closure | Register this closure argument. |


Remarks This is an alternate pathway for alerting a client program of connection problems. The program defines an exception listener callback function, and calls this function to register the callback and a closure argument. When the client library detects a connection problem, it calls the callback with a status code that identifies the problem.

See Also [tibemsConnection_SetExceptionListener on page 223](#)
[Asynchronous Errors on page 210](#).
[tibemsExceptionCallback on page 233](#)

tibemsCollection

Type

- Purpose**Represent a collection of administrative objects.
- Remarks**Collections provide an array-like set of administrative objects for use by the calling program. Administrative objects include [tibemsQueueInfo](#), [tibemsTopicInfo](#), [tibemsConsumerInfo](#), [tibemsProducerInfo](#), and [tibemsDetailedDestStat](#) objects.



Collections are not thread-safe and should only be operated on by a single application thread.

| Function | Description | Page |
|---|---|------|
| tibemsCollection_Destroy | Destroy a collection. | 451 |
| tibemsCollection_GetCount | Get the count of objects in a collection. | 452 |
| tibemsCollection_GetFirst | Get the first object in a collection. | 453 |
| tibemsCollection_GetNext | Get the next object in a collection. | 454 |

- See Also**[tibemsAdmin_GetQueues](#) on page 441
- [tibemsAdmin_GetTopics](#) on page 446
- [tibemsAdmin_GetConsumers](#) on page 434
- [tibemsAdmin_GetProducerStatistics](#) on page 438
- [tibemsConsumerInfo_GetDetailedStatistics](#) on page 464
- [tibemsProducerInfo_GetDetailedStatistics](#) on page 488

tibemsCollection_Destroy

Function

Purpose Destroy a collection.

C Declaration `tibems_status tibemsCollection_Destroy(
tibemsCollection collection);`

COBOL Call `CALL "tibemsCollection_Destroy"
USING BY VALUE collection,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| collection | The collection object to be destroyed. |

Remarks

Collections are created internally by the EMS library. Use `tibemsCollection_Destroy` to remove collections of `tibemsQueueInfo`, `tibemsTopicInfo`, `tibemsConsumerInfo`, and `tibemsProducerInfo` objects. Collections of `tibemsDetailedDestStat` objects cannot be directly destroyed by the user application. Attempting to destroy a `tibemsDetailedDestStat` object returns `TIBEMS_NOT_PERMITTED`.

Status Codes

| Status Code | Description |
|----------------------|--|
| TIBEMS_NOT_PERMITTED | The collection may not be directly destroyed by the application. |

tibemsCollection_GetCount

Function

Purpose Get the count of objects in a collection.

C Declaration `tibems_status tibemsCollection_GetCount(
tibemsCollection collection,
tibems_int* count);`

COBOL Call `CALL "tibemsCollection_GetCount"
USING BY VALUE collection,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| collection | Get the number of objects in this collection. |
| count | The function stores the count of objects in the collection in this location. |

tibemsCollection_GetFirst

Function

Purpose Get the first object in a collection.

C Declaration `tibems_status tibemsCollection_GetFirst(
tibemsCollection collection,
collectionObj* object);`

COBOL Call `CALL "tibemsCollection_GetFirst"
USING BY VALUE collection,
BY REFERENCE obj,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|------------|--|
| collection | Get the first object in this collection. |
| object | The function stores the first object in the collection in this location. |

Remarks This function must be called before any calls to tibemsCollection_GetNext.

tibemsCollection_GetNext

Function

Purpose Get the next object in a collection.

C Declaration `tibems_status tibemsCollection_GetNext(
tibemsCollection collection,
collectionObj* object);`

COBOL Call `CALL "tibemsCollection_GetNext"
USING BY VALUE collection,
BY REFERENCE obj,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|------------|---|
| collection | Get the next object in this collection. |
| object | The function stores the next object in the collection in this location. |

Remarks This function gets the next object in a collection. If there are no more objects in the collection, `tibemsCollection_GetNext` returns `TIBEMS_NOT_FOUND`.

The function `tibemsCollection_GetFirst` must be called before `tibemsCollection_GetNext` is called for the first time.

Status Codes

| Status Code | Description |
|------------------------|---|
| TIBEMS_NOT_INITIALIZED | The collection has not been initialized with a call to <code>tibemsCollection_GetFirst</code> . |
| TIBEMS_NOT_FOUND | There are no more objects in the collection. |

tibemsConsumerInfo

Type

Purpose Represent a message consumer in the server.

| Function | Description | Page |
|--|--|------|
| tibemsConsumerInfo_Destroy | Destroy a consumerInfo object. | 458 |
| tibemsConsumerInfo_GetCreateTime | Get a consumer's creation time in milliseconds. | 459 |
| tibemsConsumerInfo_GetCurrentMsgCountSentByServer | Get the number of messages sent to consumer and not yet acknowledged by consumer's session. | 460 |
| tibemsConsumerInfo_GetCurrentMsgSizeSentByServer | Get the combined size of messages sent to consumer and not yet acknowledged by consumer's session. | 461 |
| tibemsConsumerInfo_GetDestinationName | Get the consumer's destination name. | 462 |
| tibemsConsumerInfo_GetDestinationType | Get consumer's destination type. | 463 |
| tibemsConsumerInfo_GetDetailedStatistics | Get detailed statistics for a wildcarded consumer. | 464 |
| tibemsConsumerInfo_GetDurableName | Get the name of the consumer's durable subscription. | 465 |
| tibemsConsumerInfo_GetElapsedSinceLastAcknowledged | Get the approximate number of milliseconds elapsed since the last time a message sent to this consumer was acknowledged by the consumer's session. | 466 |

| Function | Description | Page |
|--|--|------|
| <code>tibemsConsumerInfo_GetElapsedSinceLastSent</code> | Get the approximate number of milliseconds elapsed since last time the server sent a message to this consumer. | 467 |
| <code>tibemsConsumerInfo_GetID</code> | Get the consumer's unique ID. | 468 |
| <code>tibemsConsumerInfo_GetPendingMessageCount</code> | Get the number of pending messages for a topic consumer. | 469 |
| <code>tibemsConsumerInfo_GetSharedSubscriptionName</code> | Get the shared subscription name for a consumer. | 471 |
| <code>tibemsConsumerInfo_GetPendingMessageSize</code> | Get the combined size of pending messages for a topic consumer. | 470 |
| <code>tibemsConsumerInfo_GetStatistics</code> | Get total statistics for a consumer. | 472 |
| <code>tibemsConsumerInfo_GetTotalAcknowledgedCount</code> | Get the total number of messages which were delivered to this consumer and have been acknowledged by the consumer's session. | 473 |
| <code>tibemsConsumerInfo_GetTotalMsgCountSentByServer</code> | Get the total number of messages the server sent to this consumer since the consumer was created. | 474 |
| <code>tibemsConsumerInfo_IsActive</code> | Get the active status of the consumer. | 475 |
| <code>tibemsConsumerInfo_IsConnected</code> | Get the connection status of the consumer. | 476 |
| <code>tibemsConsumerInfo_IsConnectionConsumer</code> | Get whether this is connection consumer. | 477 |

| Function | Description | Page |
|---|---|---------------------|
| tibemsConsumerInfo_IsShared | Get the shared subscription status of the consumer. | 478 |

Related Types [tibemsStatData on page 514](#)
 [tibemsDetailedDestStat on page 479](#)

tibemsConsumerInfo_Destroy

Function

Purpose Destroy a consumerInfo object.

C Declaration `tibems_status tibemsConsumerInfo_Destroy(
tibemsConsumerInfo consumerInfo);`

COBOL Call `CALL "tibemsConsumerInfo_Destroy"
USING BY VALUE consumerInfo,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | The consumerInfo object to be destroyed. |

tibemsConsumerInfo_GetCreateTime

Function

Purpose Get a consumer's creation time in milliseconds.

C Declaration `tibems_status tibemsConsumerInfo_GetCreateTime(
tibemsConsumerInfo consumerInfo,
tibems_long* ctime);`

COBOL Call `CALL "tibemsConsumerInfo_GetCreateTime"
USING BY VALUE consumerInfo,
BY REFERENCE created,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| consumerInfo | Get the creation time of this consumer. |
| ctime | The function stores the create time in this location. |

tibemsConsumerInfo_GetCurrentMsgCountSentByServer

Function

Purpose Get the number of messages sent to consumer and not yet acknowledged by consumer's session.

C Declaration `tibems_status tibemsConsumerInfo_GetCurrentMsgCountSentByServer(tibemsConsumerInfo consumerInfo, tibems_long* count);`

COBOL Call `CALL "tibemsConsumerInfo_GetCurrentMsgCountSentByServer"
USING BY VALUE consumerInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get the number of messages sent to this consumer. |
| count | The function stores the number of messages in this location. |

Remarks This function gets the number of messages sent to but not yet acknowledged by the consumer. For topic consumers, this number is included in the number of pending messages returned by `tibemsConsumerInfo_GetPendingMessageCount`.

See Also [tibemsConsumerInfo_GetPendingMessageCount on page 469](#)

tibemsConsumerInfo_GetCurrentMsgSizeSentByServer

Function

Purpose Get the combined size of messages sent to consumer and not yet acknowledged by consumer's session.

C Declaration `tibems_status tibemsConsumerInfo_GetCurrentMsgSizeSentByServer(tibemsConsumerInfo consumerInfo, tibems_long* size);`

COBOL Call `CALL "tibemsConsumerInfo_GetCurrentMsgSizeSentByServer"
USING BY VALUE consumerInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|---|
| | consumerInfo | Get the unacknowledged message size for this consumer. |
| | size | The function stores the total size of sent messages in this location. |

Remarks This function gets the combined size of messages sent to consumer and not yet acknowledged by consumer's session. For topic consumers this size is included into the combined size of pending messages returned by `tibemsConsumerInfo_GetPendingMessageSize`.

See Also [tibemsConsumerInfo_GetPendingMessageSize on page 470](#)

tibemsConsumerInfo_GetDestinationName

Function

Purpose Get the consumer's destination name.

C Declaration `tibems_status tibemsConsumerInfo_GetDestinationName(
tibemsConsumerInfo consumerInfo,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsConsumerInfo_GetDestinationName"
USING BY VALUE consumerInfo,
BY REFERENCE destName,
BY VALUE name_len,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get the destination name of this consumer. |
| name | The function stores the destination name in this location. |
| name_len | Length of the name buffer. |

tibemsConsumerInfo_GetDestinationType

Function

Purpose Get consumer's destination type.

C Declaration `tibems_status tibemsConsumerInfo_GetDestinationType(
tibemsConsumerInfo consumerInfo,
tibemsDestinationType* type);`

COBOL Call `CALL "tibemsConsumerInfo_GetDestinationType"
USING BY VALUE consumerInfo,
BY REFERENCE destType,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|--|
| | consumerInfo | Get the destination type of this consumer. |
| | type | The function stores the destination type in this location. |

See Also [tibemsDestinationType on page 145](#)

tibemsConsumerInfo_GetDetailedStatistics

Function

Purpose Get detailed statistics for a wildcarded consumer.

C Declaration `tibems_status tibemsConsumerInfo_GetDetailedStatistics(
tibemsConsumerInfo consumerInfo,
tibemsCollection* collection);`

COBOL Call `CALL "tibemsConsumerInfo_GetDetailedStatistics"
USING BY VALUE consumerInfo,
BY REFERENCE collection,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get statistics for this consumer. |
| collection | The function stores the collection of tibemsDetailedDestStat objects in this location. |

Remarks Returns detailed statistics for the consumer, giving a breakdown of the consumer's aggregate statistics across all destinations that it has received messages on.

This function returns NULL when there are no detailed statistics available for the consumer. This can happen for any of the following reasons:

- The consumer is not a wildcarded consumer.
- Detailed statistics are disabled in the server.
- Detailed statistics were not included into this consumerInfo object by the function tibemsAdmin_GetConsumers that was used to obtain the object.

See Also [tibemsAdmin_GetConsumers on page 434](#)
[tibemsCollection on page 450](#)

tibemsConsumerInfo_GetDurableName

Function

Purpose Get the name of the consumer's durable subscription.

C Declaration

```
tibems_status tibemsConsumerInfo_GetDurableName(  
    tibemsConsumerInfo consumerInfo,  
    char* name,  
    tibems_int name_len);
```

COBOL Call

```
CALL "tibemsConsumerInfo_GetDurableName"  
    USING BY VALUE consumerInfo,  
          BY REFERENCE durableName,  
          BY VALUE name_len,  
          RETURNING tibems-status  
END-CALL.
```

Parameters

| Parameter | Description |
|--------------|---|
| consumerInfo | Get the subscription of this consumer. |
| name | The function stores to the durable name in this location. |
| name_len | The length of the name buffer. |

Remarks This function returns the name of the consumer's durable subscription. Only durable topic consumers have a durable name. The function returns NULL if the consumer is a non-durable topic subscriber or a queue receiver.

tibemsConsumerInfo_GetElapsedSinceLastAcknowledged

Function

Purpose Get the approximate number of milliseconds elapsed since the last time a message sent to this consumer was acknowledged by the consumer's session.

C Declaration `tibems_status tibemsConsumerInfo_GetElapsedSinceLastAcknowledged(tibemsConsumerInfo consumerInfo, tibems_long* time);`

COBOL Call `CALL "tibemsConsumerInfo_GetElapsedSinceLastAcknowledged" USING BY VALUE consumerInfo, BY REFERENCE time, RETURNING tibems-status END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get the milliseconds elapsed for this consumer. |
| time | The function stores the elapsed time in this location. |

Remarks This function gets the approximate number of milliseconds that have elapsed since last time a message sent to this consumer was acknowledged by consumer's session. This value, while returned in milliseconds, has a precision of 1 second. This value should be used for informational purposes only. For example, it can be used to identify consumers which receive messages but do not acknowledge them for some reason.

tibemsConsumerInfo_GetElapsedSinceLastSent

Function

Purpose Get the approximate number of milliseconds elapsed since last time the server sent a message to this consumer.

C Declaration `tibems_status tibemsConsumerInfo_GetElapsedSinceLastSent(
tibemsConsumerInfo consumerInfo,
tibems_long* time);`

COBOL Call `CALL "tibemsConsumerInfo_GetElapsedSinceLastSent"
USING BY VALUE consumerInfo,
BY REFERENCE time,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|--|
| | consumerInfo | Get the milliseconds elapsed for this consumer. |
| | time | The function stores the elapsed milliseconds in this location. |

Remarks This function gets the approximate number of milliseconds that have elapsed since last time the server sent a message to this consumer. The value returned, while given in milliseconds, has a precision of 1 second. It should be used for informational purposes only.

tibemsConsumerInfo_GetID

Function

Purpose Get the consumer’s unique ID.

C Declaration `tibems_status tibemsConsumerInfo_GetID(
tibemsConsumerInfo consumerInfo,
tibems_long* cid);`

COBOL Call `CALL "tibemsConsumerInfo_GetID"
USING BY VALUE consumerInfo,
BY REFERENCE id,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| consumerInfo | Get the unique ID of this consumer. |
| cid | The function stores the consumer ID in this location. |

tibemsConsumerInfo_GetPendingMessageCount

Function

Purpose Get the number of pending messages for a topic consumer.

C Declaration `tibems_status tibemsConsumerInfo_GetPendingMessageCount(
tibemsConsumerInfo consumerInfo,
tibems_long* count);`

COBOL Call `CALL "tibemsConsumerInfo_GetPendingMessageCount"
USING BY VALUE consumerInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get the number of pending messages for this consumer. |
| count | The function stores the number of pending messages in this location. |

Remarks This function can be used to retrieve the number of pending messages for a topic consumer only. For queue consumers, the number of pending messages in the corresponding queue must be obtained from the queue. If the consumer is a queue consumer, the function returns 0 (zero).

See Also [tibemsQueueInfo_GetPendingMessageCount on page 503](#)

tibemsConsumerInfo_GetPendingMessageSize

Function

Purpose Get the combined size of pending messages for a topic consumer.

C Declaration `tibems_status tibemsConsumerInfo_GetPendingMessageSize(
tibemsConsumerInfo consumerInfo,
tibems_long* size);`

COBOL Call `CALL "tibemsConsumerInfo_GetPendingMessageSize"
USING BY VALUE consumerInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|--|
| | consumerInfo | Get the size for this consumer. |
| | size | The function stores the size of pending messages in this location. |

Remarks This function can be used to retrieve the combined size of the pending messages for a topic consumer. If the consumer is a queue consumer, the function returns 0 (zero).

See Also [tibemsQueueInfo_GetPendingMessageSize on page 504](#)

tibemsConsumerInfo_GetSharedSubscriptionName

Function

Purpose Get the shared subscription name for a consumer.

C Declaration `tibems_status tibemsConsumerInfo_GetSharedSubscriptionName(
tibemsConsumerInfo consumerInfo,
char* sharedName,
tibems_int name_len);`

COBOL Call `CALL "tibemsConsumerInfo_GetSharedSubscriptionName"
USING BY VALUE consumerInfo,
BY REFERENCE sharedName,
BY VALUE name-len,
RETURNING tibems-status
END-CALL.`



sharedName has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get the subscription name for this consumer. |
| sharedName | The function stores the shared subscription name in this location. |
| name_len | Length of the sharedName buffer. |

Remarks This function can be used to retrieve the shared subscription name for the consumer. Only shared consumers have a shared subscription name. The function returns NULL if the consumer is not shared or is a queue receiver.

For more information, see the section Shared Subscriptions for Topics in the *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsConsumerInfo_IsShared](#) on page 478

tibemsConsumerInfo_GetStatistics

Function

Purpose Get total statistics for a consumer.

C Declaration `tibems_status tibemsConsumerInfo_GetStatistics(
tibemsConsumerInfo consumerInfo,
tibemsStatData* statData);`

COBOL Call `CALL "tibemsConsumerInfo_GetStatistics"
USING BY VALUE consumerInfo,
BY REFERENCE stat,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get statistics for this consumer. |
| statData | The function stores the statistics in this location. |

Remarks This function returns NULL when there are no statistics available for the consumer. This can happen for any of the following reasons:

- Statistics are disabled in the server.
- Statistics were not included into this consumerInfo object by the function tibemsAdmin_GetConsumers that was used to obtain the object.

See Also [tibemsAdmin_GetConsumers on page 434](#)
[tibemsStatData on page 514](#)

tibemsConsumerInfo_GetTotalAcknowledgedCount

Function

Purpose Get the total number of messages which were delivered to this consumer and have been acknowledged by the consumer's session.

C Declaration `tibems_status tibemsConsumerInfo_GetTotalAcknowledgedCount(
tibemsConsumerInfo consumerInfo,
tibems_long* count);`

COBOL Call `CALL "tibemsConsumerInfo_GetTotalAcknowledgedCount"
USING BY VALUE consumerInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| consumerInfo | Get the number of messages for this consumer. |
| count | The function stores the message count in this location. |

tibemsConsumerInfo_GetTotalMsgCountSentByServer

Function

Purpose Get the total number of messages the server sent to this consumer since the consumer was created.

C Declaration `tibems_status tibemsConsumerInfo_GetTotalMsgCountSentByServer(tibemsConsumerInfo consumerInfo, tibems_long* count);`

COBOL Call `CALL "tibemsConsumerInfo_GetTotalMsgCountSentByServer"
USING BY VALUE consumerInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| consumerInfo | Get the number of messages for this consumer. |
| count | The function stores the message count in this location. |

Remarks This function returns total number of messages the server sent to this consumer since consumer was created. This value include duplicates of messages that were resent after a consumer's session recovery or rollback. Therefore, the count may not represent true number of unique messages received by this consumer and should be used only for statistical and informational purposes.

tibemsConsumerInfo_IsActive

Function

Purpose Get the active status of the consumer.

C Declaration `tibems_status tibemsConsumerInfo_IsActive(
tibemsConsumerInfo consumerInfo,
tibems_bool* active);`

COBOL Call `CALL "tibemsConsumerInfo_IsActive"
USING BY VALUE consumerInfo,
BY REFERENCE active,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|--|
| | consumerInfo | Get the status of this consumer. |
| | active | The function stores the status of the consumer in this location. |

Remarks If the consumer is active, the active status is TRUE. Otherwise, active is FALSE. A consumer is active if the server can send messages to it. Only queue consumers which have never called a receive function remain in inactive state.

Queue consumers which called have called [tibemsMsgConsumer_Receive](#), [tibemsMsgConsumer_ReceiveNoWait](#), or [tibemsMsgConsumer_ReceiveTimeout](#) at least once or are configured with a message callback, and all topic consumers are always active. This function can identify inactive queue consumers which have never called a receive function which and have never received any messages from the server, even when pending messages exist in the corresponding queue.

See Also [tibemsMsgConsumer_Receive on page 170](#)
[tibemsMsgConsumer_ReceiveNoWait on page 171](#)
[tibemsMsgConsumer_ReceiveTimeout on page 172](#)

tibemsConsumerInfo_IsConnected

Function

Purpose Get the connection status of the consumer.

C Declaration `tibems_status tibemsConsumerInfo_IsConnected(
tibemsConsumerInfo consumerInfo,
tibems_bool* connected);`

COBOL Call `CALL "tibemsConsumerInfo_IsConnected"
USING BY VALUE consumerInfo,
BY REFERENCE connected,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| consumerInfo | Get the status of this consumer. |
| connected | The function stores the connection status in this location. |

Remarks The connection status will be set to TRUE if this consumer is connected to the server, and FALSE otherwise. Only durable topic subscribers may be in a disconnected state. This function always sets the connection status to TRUE for queue receivers and non-durable topic consumers.

tibemsConsumerInfo_IsConnectionConsumer

Function

Purpose Get whether this is connection consumer.

C Declaration `tibems_status tibemsConsumerInfo_IsConnectionConsumer(
tibemsConsumerInfo consumerInfo,
tibems_bool* connectionConsumer);`

COBOL Call `CALL "tibemsConsumerInfo_IsConnectionConsumer"
USING BY VALUE consumerInfo,
BY REFERENCE connectionConsumer,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------------|---|
| consumerInfo | Get whether this consumer is a connection consumer. |
| connectionConsumer | The function stores consumer connection status in this location. TRUE indicates that the consumer is a connection consumer. |

Remarks Sets the connection status to TRUE if the consumer is a connection consumer, and FALSE otherwise. Notice that for disconnected durable topic subscribers the function returns FALSE even if the durable was created as connection consumer.

tibemsConsumerInfo_IsShared

Function

Purpose Get the shared subscription status of the consumer.

C Declaration `tibems_status tibemsConsumerInfo_IsShared(
tibemsConsumerInfo consumerInfo,
tibems_bool* shared);`

COBOL Call `CALL "tibemsConsumerInfo_IsShared"
USING BY VALUE consumerInfo,
BY REFERENCE shared,
RETURNING tibems-status
END-CALL.`



shared has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| consumerInfo | Get the shared status of this consumer. |
| shared | The function stores the consumer's shared status in this location. |

Remarks If the consumer is shared, the shared status will be set to TRUE. Otherwise, shared is FALSE.

For more information, see the section Shared Subscriptions for Topics in the *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsConsumerInfo_GetSharedSubscriptionName on page 471](#)

tibemsDetailedDestStat

Type

| | |
|----------------|---|
| Purpose | Represents detailed destination statistics about objects such as topics, message consumers, or message producers. |
| Remarks | Detailed statistics are optionally collected by the server for wildcarded consumers, unidentified producers and routes. |

| Function | Description | Page |
|---|--|------|
| tibemsDetailedDestStat_GetDestinationName | Get the name of the destination. | 480 |
| tibemsDetailedDestStat_GetDestinationType | Get the type of the destination. | 481 |
| tibemsDetailedDestStat_GetDestinationType | Get statistics for a unidirectional destination. | 481 |

| | |
|----------------------|---|
| Related Types | tibemsStatData on page 514 |
| See Also | tibemsMsg_GetDestination on page 42 |

tibemsDetailedDestStat_GetDestinationName

Function

Purpose Get the name of the destination.

C Declaration `tibems_status tibemsDetailedDestStat_GetDestinationName(
tibemsDetailedDestStat detailedDestStat,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsDetailedDestStat_GetDestinationName"
USING BY VALUE detailedDestStat,
BY REFERENCE destName,
BY VALUE name_len,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| detailedDestStat | Get the name of this destination. |
| name | The function stores the destination name in this location. |
| name_len | Length of the name buffer. |

See Also [tibemsDestinationType on page 145](#)

tibemsDetailedDestStat_GetDestinationType

Function

Purpose Get the type of the destination.

C Declaration `tibems_status tibemsDetailedDestStat_GetDestinationType(
tibemsDetailedDestStat detailedDestStat,
tibemsDestinationType* destType);`

COBOL Call `CALL "tibemsDetailedDestStat_GetDestinationType"
USING BY VALUE detailedDestStat,
BY REFERENCE destType,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|------------------|--|
| | detailedDestStat | Get the type of this destination. |
| | destType | The function stores the destination type in this location. |

See Also [tibemsDestinationType on page 145](#)

tibemsDetailedDestStat_GetStatData

Function

Purpose Get statistics for a unidirectional destination.

C Declaration `tibems_status tibemsDetailedDestStat_GetStatData(
tibemsDetailedDestStat detailDestStat,
tibemsStatData* statData);`

COBOL Call `CALL "tibemsDetailedDestStat_GetStatData"
USING BY VALUE detailedDestStat,
BY REFERENCE stat,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| detailedDestStat | Get statistics for this destination. |
| statData | The function stores the statistics in this location. |

Remarks This function retrieves unidirectional destination statistics. Unidirectional destinations statistics are collected for both producers and consumers.

tibemsProducerInfo

Type

Purpose Represent a message producer.

| Function | Description | Page |
|--|---|------|
| tibemsProducerInfo_Destroy | Destroy a producerInfo object. | 484 |
| tibemsProducerInfo_GetCreateTime | Get the producer create time in milliseconds. | 485 |
| tibemsProducerInfo_GetDestinationName | Get the producer's destination name. | 486 |
| tibemsProducerInfo_GetDestinationType | Get the producer's destination type. | 487 |
| tibemsProducerInfo_GetDetailedStatistics | Get detailed statistics for an unidentified producer. | 488 |
| tibemsProducerInfo_GetID | Get the producer's ID. | 489 |
| tibemsProducerInfo_GetStatistics | Get total statistics for a producer. | 490 |

Related Types [tibemsDetailedDestStat](#) on page 479
 [tibemsStatData](#) on page 514

tibemsProducerInfo_Destroy

Function

Purpose Destroy a producerInfo object.

C Declaration `tibems_status tibemsProducerInfo_Destroy(
tibemsProducerInfo producerInfo);`

COBOL Call `CALL "tibemsProducerInfo_Destroy"
USING BY VALUE producerInfo,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|--|
| | producerInfo | The <code>tibemsProducerInfo</code> object to destroy. |

tibemsProducerInfo_GetCreateTime

Function

Purpose Get the producer create time in milliseconds.

C Declaration `tibems_status tibemsProducerInfo_GetCreateTime(
tibemsProducerInfo producerInfo,
tibems_long* created);`

COBOL Call `CALL "tibemsProducerInfo_GetCreateTime"
USING BY VALUE producerInfo,
BY REFERENCE created,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| producerInfo | Get the create time for this producer. |
| created | The function stores the create time in this location. |

tibemsProducerInfo_GetDestinationName

Function

Purpose Get the producer's destination name.

C Declaration `tibems_status tibemsProducerInfo_GetDestinationName(
tibemsProducerInfo producerInfo,
char* name
tibems_int name_len);`

COBOL Call `CALL "tibemsProducerInfo_GetDestinationName"
USING BY VALUE producerInfo,
BY REFERENCE destName,
BY VALUE name_len,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| producerInfo | Get the destination name of this producer. |
| name | The function stores the destination name in this location. |
| name_len | Length of the name buffer. |

tibemsProducerInfo_GetDestinationType

Function

Purpose Get the producer's destination type.

C Declaration `tibems_status tibemsProducerInfo_GetDestinationType(
tibemsProducerInfo producerInfo,
tibemsDestinationType* type);`

COBOL Call `CALL "tibemsProducerInfo_GetDestinationType"
USING BY VALUE producerInfo,
BY REFERENCE destType,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|--|
| producerInfo | Get the destination type of this producer. |
| type | The function stores the destination type in this location. |

See Also [tibemsDestinationType on page 145](#)

tibemsProducerInfo_GetDetailedStatistics

Function

Purpose Get detailed statistics for an unidentified producer.

C Declaration `tibems_status tibemsProducerInfo_GetDetailedStatistics(
tibemsProducerInfo producerInfo,
tibemsCollection* collection;`

COBOL Call `CALL "tibemsProducerInfo_GetDetailedStatistics"
USING BY VALUE producerInfo,
BY REFERENCE collection,
RETURNING tibems-status
END-CALL.`



collection has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| producerInfo | Get statistics for this producer. |
| collection | The function stores the statistics in this location, as a collection of <code>tibemsDetailedDestStat</code> objects. |

Remarks Gets detailed statistics for an unidentified producer, giving a breakdown of the producer's aggregate statistics across all destinations that it has published messages on.

This function returns `NULL` when there are no detailed statistics available for the producer. This can happen when, for example, detailed statistics for producers are disabled in the server.

See Also [tibemsDetailedDestStat on page 479](#)

tibemsProducerInfo_GetID

Function

Purpose Get the producer's ID.

C Declaration `tibems_status tibemsProducerInfo_GetID(
 tibemsProducerInfo producerInfo,
 tibems_long* id);`

COBOL Call `CALL "tibemsProducerInfo_GetID"
 USING BY VALUE producerInfo,
 BY REFERENCE id,
 RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| producerInfo | Get the ID for this producer. |
| id | The function stores the producer ID in this location. |

tibemsProducerInfo_GetStatistics

Function

Purpose Get total statistics for a producer.

C Declaration `tibems_status tibemsProducerInfo_GetStatistics(
tibemsProducerInfo producerInfo,
tibemsStatData* statData);`

COBOL Call `CALL "tibemsProducerInfo_GetStatistics"
USING BY VALUE producerInfo,
BY REFERENCE stat,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|--------------|---|
| producerInfo | Get statistics for this producer. |
| statData | The function stores the statistics in this location. The stored value will be NULL if statistics are disabled in the server and so there are none available for the producer. |

See Also [tibemsStatData on page 514](#)

tibemsQueueInfo

Type

Purpose Represent a message queue that is configured in the EMS server.

| Function | Description | Page |
|--|--|------|
| tibemsQueueInfo_Create | Create a tibemsQueueInfo object. | 493 |
| tibemsQueueInfo_Destroy | Destroy a tibemsQueueInfo object. | 494 |
| tibemsQueueInfo_GetDeliveredMessageCount | Get the total number of messages that have been delivered to consumer applications but have not yet been acknowledged. | 495 |
| tibemsQueueInfo_GetFlowControlMaxBytes | Get the volume of pending messages at which flow control is enabled for the queue. | 496 |
| tibemsQueueInfo_GetInboundStatistics | Get inbound statistics for this queue. | 497 |
| tibemsQueueInfo_GetMaxBytes | Get the maximum number of bytes that the server stores of pending messages bound for this queue. | 498 |
| tibemsQueueInfo_GetMaxMsgs | Get the maximum number of pending messages bound for the queue that the server will store. | 499 |
| tibemsQueueInfo_GetName | Get the name of this queue. | 500 |
| tibemsQueueInfo_GetOutboundStatistics | Get outbound statistics for this queue. | 501 |
| tibemsQueueInfo_GetOverflowPolicy | Get the overflow policy for this queue. | 502 |
| tibemsQueueInfo_GetPendingMessageCount | Get the total number of pending messages for this queue. | 503 |
| tibemsQueueInfo_GetPendingMessageSize | Get the total size of all pending messages for this queue. | 504 |
| tibemsQueueInfo_GetPendingPersistentMessageCount | Get the total number of pending messages for this queue that were sent persistently. | 505 |

| Function | Description | Page |
|---|--|------|
| tibemsQueueInfo_GetPendingPersistentMessageSize | Get the total size of all pending messages for this queue that were sent persistently. | 506 |
| tibemsQueueInfo_GetReceiverCount | Get the number of active receivers on this queue. | 507 |

Related Types [tibemsQueue](#) on page 152
 [tibemsStatData](#) on page 514

tibemsQueueInfo_Create

Function

Purpose Create a tibemsQueueInfo object.

C Declaration `tibems_status tibemsQueueInfo_Create(
tibemsQueueInfo* queueInfo,
const char* queueName);`

COBOL Call `CALL "tibemsQueueInfo_Create"
USING BY REFERENCE queueInfo,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | queueInfo | Store the new tibemsQueueInfo object in this location. |
| | queueName | Create the tibemsQueueInfo object with this name. The queueName can include wildcards. |

Remarks This function is used to create a tibemsQueueInfo object with the specified name. The tibemsQueueInfo object may then be passed as the tibemsDestinationInfo argument to the [tibemsAdmin_GetConsumers](#) and [tibemsAdmin_GetProducerStatistics](#) functions. The name may include wildcards.

For more information on wildcards, see [Wildcards on page 77](#) of the *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsTopicInfo_Create on page 534](#)
[tibemsAdmin_GetConsumers on page 434](#)
[tibemsAdmin_GetProducerStatistics on page 438](#)

tibemsQueueInfo_Destroy

Function

Purpose Destroy a tibemsQueueInfo object.

C Declaration `tibems_status tibemsQueueInfo_Destroy(
tibemsQueueInfo queueInfo);`

COBOL Call `CALL "tibemsQueueInfo_Destroy"
USING BY VALUE queueInfo,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | queueInfo | The tibemsQueueInfo object to destroy. |

See Also [tibemsTopicInfo_Destroy on page 535](#)

tibemsQueueInfo_GetDeliveredMessageCount

Function

Purpose Get the total number of messages that have been delivered to consumer applications but have not yet been acknowledged.

C Declaration `tibems_status tibemsQueueInfo_GetDeliveredMessageCount(
tibemsQueueInfo queueInfo,
tibems_long* count);`

COBOL Call `CALL "tibemsQueueInfo_GetDeliveredMessageCount"
USING BY VALUE queueInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get the number of unacknowledged messages in this queue. |
| count | The function stores the message count in this location. |

tibemsQueueInfo_GetFlowControlMaxBytes

Function

Purpose Get the volume of pending messages at which flow control is enabled for the queue.

C Declaration `tibems_status tibemsQueueInfo_GetFlowControlMaxBytes(
tibemsQueueInfo queueInfo,
tibems_long* maxBytes);`

COBOL Call `CALL "tibemsQueueInfo_GetFlowControlMaxBytes"
USING BY VALUE queueInfo,
BY REFERENCE maxBytes,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get the volume for this queue. |
| maxBytes | The function stores the volume in this location. The value stored indicates the volume of pending messages, in bytes, that the server will store in the queue before enabling flow control. A value of 0 indicates that flow control will never be enabled. |

See Also [tibemsTopicInfo_GetFlowControlMaxBytes on page 539](#)

tibemsQueueInfo_GetInboundStatistics

Function

Purpose Get inbound statistics for this queue.

C Declaration `tibems_status tibemsQueueInfo_GetInboundStatistics(
tibemsQueueInfo queueInfo,
tibemsStatData* statData);`

COBOL Call `CALL "tibemsQueueInfo_GetInboundStatistics"
USING BY VALUE queueInfo,
BY REFERENCE statData,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get statistics for this queue. |
| statData | The function stores the statistics in this location. |

Remarks This function retrieves the inbound statistics for the queue. Inbound statistics include all messages sent into the queue by EMS clients and routed servers.

See Also [tibemsTopicInfo_GetInboundStatistics on page 540](#)

tibemsQueueInfo_GetMaxBytes

Function

Purpose Get the maximum number of bytes that the server stores of pending messages bound for this queue.

C Declaration `tibems_status tibemsQueueInfo_GetMaxBytes(
tibemsQueueInfo queueInfo,
tibems_long* maxBytes);`

COBOL Call `CALL "tibemsQueueInfo_GetMaxBytes"
USING BY VALUE queueInfo,
BY REFERENCE maxBytes,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|---|
| queueInfo | Get the maximum bytes for this queue. |
| maxBytes | The function stores the number of bytes in this location. |

See Also [tibemsTopicInfo_GetMaxBytes on page 541](#)

tibemsQueueInfo_GetMaxMsgs

Function

Purpose Get the maximum number of pending messages bound for the queue that the server will store.

C Declaration `tibems_status tibemsQueueInfo_GetMaxMsgs(
tibemsQueueInfo queueInfo,
tibems_long* maxMsgs);`

COBOL Call `CALL "tibemsQueueInfo_GetMaxMsgs"
USING BY VALUE queueInfo,
BY REFERENCE maxMsgs,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | queueInfo | |
| | maxMsgs | The function stores the number of messages in this location. |

See Also [tibemsTopicInfo_GetMaxMsgs on page 542](#)

tibemsQueueInfo_GetName

Function

Purpose Get the name of this queue.

C Declaration `tibems_status tibemsQueueInfo_GetName(
tibemsQueueInfo queueInfo,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsQueueInfo_GetName"
USING BY VALUE queueInfo,
BY REFERENCE name,
BY VALUE name_len,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | queueInfo | Get the name of this queue. |
| | name | The function stores the queue name in this location. |
| | name_len | Length of the name buffer. |

See Also [tibemsTopicInfo_GetName on page 543](#)

tibemsQueueInfo_GetOutboundStatistics

Function

Purpose Get outbound statistics for this queue.

C Declaration `tibems_status tibemsQueueInfo_GetOutboundStatistics(
 tibemsQueueInfo queueInfo,
 tibemsStatData* statData);`

COBOL Call `CALL "tibemsQueueInfo_GetOutboundStatistics"
 USING BY VALUE queueInfo,
 BY REFERENCE statData,
 RETURNING tibems-status
 END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get statistics for this queue. |
| statData | The function stores the statistics in this location. |

Remarks This function retrieves the outbound statistics for the queue. Outbound statistics include all messages delivered from the queue to EMS clients and routed servers.

See Also [tibemsTopicInfo_GetOutboundStatistics on page 544](#)

tibemsQueueInfo_GetOverflowPolicy

Function

Purpose Get the overflow policy for this queue.

C Declaration `tibems_status tibemsQueueInfo_GetOverflowPolicy(
tibemsQueueInfo queueInfo,
tibems_int* overflowPolicy);`

COBOL Call `CALL "tibemsQueueInfo_GetOverflowPolicy"
USING BY VALUE queueInfo,
BY REFERENCE overflowPolicy,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|----------------|---|
| | queueInfo | Get the policy for this queue. |
| | overflowPolicy | The function stores the overflow policy in this location. |

Remarks This function retrieves the overflow policy for the queue. Possible values are:

- TIBEMS_OVERFLOW_DEFAULT
- TIBEMS_OVERFLOW_DISCARD_OLD
- TIBEMS_OVERFLOW_REJECT_INCOMING

For more information about overflow policies, see the *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsTopicInfo_GetOverflowPolicy on page 545](#)

tibemsQueueInfo_GetPendingMessageCount

Function

Purpose Get the total number of pending messages for this queue.

C Declaration `tibems_status tibemsQueueInfo_GetPendingMessageCount(
tibemsQueueInfo queueInfo,
tibems_long* count);`

COBOL Call `CALL "tibemsQueueInfo_GetPendingMessageCount"
USING BY VALUE queueInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get the number of messages for this queue. |
| count | The function stores the number of messages in this location. |

See Also [tibemsTopicInfo_GetPendingMessageCount on page 546](#)

tibemsQueueInfo_GetPendingMessageSize

Function

Purpose Get the total size of all pending messages for this queue.

C Declaration `tibems_status tibemsQueueInfo_GetPendingMessageSize(
tibemsQueueInfo queueInfo,
tibems_long* size);`

COBOL Call `CALL "tibemsQueueInfo_GetPendingMessageSize"
USING BY VALUE queueInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get the size of pending messages for this queue. |
| size | The function stores the size of pending messages in this location. |

See Also [tibemsTopicInfo_GetPendingMessageSize on page 547](#)

tibemsQueueInfo_GetPendingPersistentMessageCount

Function

Purpose Get the total number of pending messages for this queue that were sent persistently.

C Declaration `tibems_status tibemsQueueInfo_GetPendingPersistentMessageCount(tibemsQueueInfo queueInfo, tibems_long* count);`

COBOL Call `CALL "tibemsQueueInfo_GetPendingPersistentMessageCount"
USING BY VALUE queueInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | queueInfo | Get the number of messages for this queue. |
| | count | The function stores the number of messages in this location. |

See Also [tibemsTopicInfo_GetPendingPersistentMessageCount on page 548](#)

tibemsQueueInfo_GetPendingPersistentMessageSize

Function

Purpose Get the total size of all pending messages for this queue that were sent persistently.

C Declaration `tibems_status tibemsQueueInfo_GetPendingPersistentMessageSize(tibemsQueueInfo queueInfo, tibems_long* size);`

COBOL Call `CALL "tibemsQueueInfo_GetPendingPersistentMessageSize"
USING BY VALUE queueInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| queueInfo | Get the size of pending messages for this queue. |
| size | The function stores the size of pending messages in this location. |

See Also [tibemsTopicInfo_GetPendingPersistentMessageSize on page 549](#)

tibemsQueueInfo_GetReceiverCount

Function

Purpose Get the number of active receivers on this queue.

C Declaration `tibems_status tibemsQueueInfo_GetReceiverCount(
tibemsQueueInfo queueInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsQueueInfo_GetReceiverCount"
USING BY VALUE queueInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|---|
| queueInfo | Get the number of receivers on this queue. |
| count | The function stores the number of receivers in this location. |

tibemsServerInfo

Type

- Purpose** Represent a TIBCO Enterprise Message Service server.
- Remarks** This type represents metrics for an EMS server.

| Function | Description | Page |
|---|---|---------------------|
| tibemsServerInfo_Destroy | Destroy a tibemsServerInfo object. | 509 |
| tibemsServerInfo_GetConsumerCount | Get the total number of consumers. | 510 |
| tibemsServerInfo_GetProducerCount | Get the total number of producers. | 511 |
| tibemsServerInfo_GetQueueCount | Get the total number of queues in the server. | 512 |
| tibemsServerInfo_GetTopicCount | Get the total number of topics in the server. | 513 |

tibemsServerInfo_Destroy

Function

Purpose Destroy a tibemsServerInfo object.

C Declaration `tibems_status tibemsServerInfo_Destroy(
tibemsServerInfo serverInfo);`

COBOL Call `CALL "tibemsServerInfo_Destroy"
USING BY VALUE serverInfo,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|------------|---|
| | serverInfo | The tibemsServerInfo object to destroy. |

tibemsServerInfo_GetConsumerCount

Function

Purpose Get the total number of consumers.

C Declaration `tibems_status tibemsServerInfo_GetConsumerCount(
tibemsServerInfo serverInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsServerInfo_GetConsumerCount"
USING BY VALUE serverInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------|---|
| serverInfo | Get the number of consumers for this server. |
| count | The function stores the number of consumers in this location. |

tibemsServerInfo_GetProducerCount

Function

Purpose Get the total number of producers.

C Declaration `tibems_status tibemsServerInfo_GetProducerCount(
tibemsServerInfo serverInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsServerInfo_GetProducerCount"
USING BY VALUE serverInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------|---|
| serverInfo | Get the number of producers for this server. |
| count | The function stores the number of producers in this location. |

tibemsServerInfo_GetQueueCount

Function

Purpose Get the total number of queues in the server.

C Declaration `tibems_status tibemsServerInfo_GetQueueCount(
tibemsServerInfo serverInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsServerInfo_GetQueueCount"
USING BY VALUE serverInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------|--|
| serverInfo | Get the number of queues in this server. |
| count | The function stores the number of queues in this location. |

tibemsServerInfo_GetTopicCount

Function

Purpose Get the total number of topics in the server.

C Declaration `tibems_status tibemsServerInfo_GetTopicCount(
tibemsServerInfo serverInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsServerInfo_GetTopicCount"
USING BY VALUE serverInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------|--|
| serverInfo | Get the number of topics in this server. |
| count | The function stores the number of topics in this location. |

tibemsStatData

Type

- Purpose**Represent statistical data about another object, such as a topic or queue.
- Remarks**Statistical data contains the total number of messages and their cumulative size. It can also provide message rates, as the number of messages sent each second and number of bytes each second. Whether or not rate information is available is controlled by the server configuration. If rate collection is turned off, all rate numbers are set to 0. However, in those cases the application can calculate the rates based on absolute numbers taken at periodic intervals.

| Function | Description | Page |
|---|--|------|
| tibemsStatData_GetByteRate | Get the average rate of bytes sent or received each second. | 515 |
| tibemsStatData_GetMessageRate | Get the rate of messages sent or received each second. | 516 |
| tibemsStatData_GetTotalBytes | Get the total size of messages sent or received each second. | 517 |
| tibemsStatData_GetTotalMessages | Get the total number of messages sent or received each second. | 518 |

- Related Types**
 - [tibemsQueue](#) on page 152
 - [tibemsTopic](#) on page 158
 - [tibemsConsumerInfo](#) on page 455
 - [tibemsProducerInfo](#) on page 483
 - [tibemsQueueInfo](#) on page 491
 - [tibemsTopicInfo](#) on page 532

tibemsStatData_GetByteRate

Function

Purpose Get the average rate of bytes sent or received each second.

C Declaration `tibems_status tibemsStatData_GetByteRate(
tibemsStatData statData,
tibems_long* byteRate);`

COBOL Call `CALL "tibemsStatData_GetByteRate"
USING BY VALUE statData,
BY REFERENCE rate_size,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | statData | Get the rate for this message consumer, producer, topic, or queue. |
| | byteRate | The function stores the average byte rate in this location. |

Remarks This function gets the average byte rate for messages sent or received per second. For message consumers, this rate reflects the number of messages received by the consumer. For messages producers, it is the rate of messages sent, and for topics and queues the rate includes both inbound and outbound messages.

tibemsStatData_GetMessageRate

Function

Purpose Get the rate of messages sent or received each second.

C Declaration `tibems_status tibemsStatData_GetMessageRate(
tibemsStatData statData,
tibems_long* messageRate);`

COBOL Call `CALL "tibemsStatData_GetMessageRate"
USING BY VALUE statData,
BY REFERENCE rate_msgs,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-------------|--|
| | statData | Get the rate for this message consumer, producer, topic, or queue. |
| | messageRate | The function stores the average message rate in this location. |

Remarks This function gets the average number of messages sent or received per second. For message consumers, this rate reflects the number of messages received by the consumer. For messages producers, it is the rate of messages sent, and for topics and queues the rate includes both inbound and outbound messages.

tibemsStatData_GetTotalBytes

Function

Purpose Get the total size of messages sent or received each second.

C Declaration `tibems_status tibemsStatData_GetTotalBytes(
 tibemsStatData statData,
 tibems_long* bytes);`

COBOL Call `CALL "tibemsStatData_GetTotalBytes"
 USING BY VALUE statData,
 BY REFERENCE size,
 RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| statData | Get the total message size for this consumer, producer, topic, or queue. |
| bytes | The function stores the size of messages in this location. |

Remarks This function gets the total size of messages sent or received. For message consumers, this is the size of messages received by the consumer. For messages producers, it is the size of messages sent, and for topics and queues the size includes both inbound and outbound messages.

tibemsStatData_GetTotalMessages

Function

Purpose Get the total number of messages sent or received each second.

C Declaration `tibems_status tibemsStatData_GetTotalMessages(
tibemsStatData statData,
tibems_long* messages);`

COBOL Call `CALL "tibemsStatData_GetTotalMessages"
USING BY VALUE statData,
BY REFERENCE msgs,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | statData | Get the total number of messages for this consumer, producer, topic, or queue. |
| | messages | The function stores the number of messages in this location. |

Remarks This function gets the total number of messages sent or received. For message consumers, this is the number of messages received by the consumer. For messages producers, it is the number of messages sent, and for topics and queues the number includes both inbound and outbound messages.

tibemsSubscriptionInfo

Type

Purpose Represent a subscription in the server.

| Function | Description | Page |
|---|---|------|
| tibemsSubscriptionInfo_Destroy | Destroy a subscriptionInfo object. | 520 |
| tibemsSubscriptionInfo_GetConsumerCount | Get the number of consumers for this subscription. | 521 |
| tibemsSubscriptionInfo_GetCreateTime | Get a subscription's creation time in milliseconds. | 522 |
| tibemsSubscriptionInfo_GetID | Get the subscription's unique ID. | 523 |
| tibemsSubscriptionInfo_GetName | Get the name of the subscription. | 524 |
| tibemsSubscriptionInfo_GetPendingMessageCount | Get the number of pending messages for a subscription. | 525 |
| tibemsSubscriptionInfo_GetPendingMessageSize | Get the combined size of pending messages for a subscription. | 526 |
| tibemsSubscriptionInfo_GetSelector | Returns this subscription's selector. | 527 |
| tibemsSubscriptionInfo_GetTopicName | Get the topic name that this subscription is for. | 528 |
| tibemsSubscriptionInfo_HasSelector | Gets whether the subscription has a selector. | 529 |
| tibemsSubscriptionInfo_IsDurable | Get whether this is a durable subscription. | 530 |
| tibemsSubscriptionInfo_IsShared | Get whether this is a shared subscription. | 531 |

Related Types [tibemsConsumerInfo](#) on page 455

tibemsSubscriptionInfo_Destroy

Function

Purpose Destroy a subscriptionInfo object.

C Declaration `tibems_status tibemsSubscriptionInfo_Destroy(
tibemsSubscriptionInfo subscriptionInfo)`

COBOL Call `CALL "tibemsSubscriptionInfo_Destroy"
USING BY VALUE subscriptionInfo,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| subscriptionInfo | The subscriptionInfo object to be destroyed. |

tibemsSubscriptionInfo_GetConsumerCount

Function

Purpose Get the number of consumers for this subscription.

C Declaration `tibems_status tibemsSubscriptionInfo_GetConsumerCount(
tibemsSubscriptionInfo subscriptionInfo,
tibems_int* consumerCount);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetConsumerCount"
USING BY VALUE subscriptionInfo,
BY REFERENCE consumerCount,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|------------------|---|
| | subscriptionInfo | Get the number of consumers for this subscription. |
| | consumerCount | The function stores the number of consumers in this location. |

Remarks Returns the number of consumers for this subscription. If the subscription is not shared, the count cannot exceed 1. If the subscription is shared, the count can exceed 1, since a shared subscription can have many shared consumers.

For durable subscriptions (shared and unshared), this count can be 0 if there is no active durable consumer.

See Also [tibemsSubscriptionInfo_IsDurable on page 530](#)
[tibemsSubscriptionInfo_IsShared on page 531](#)

tibemsSubscriptionInfo_GetCreateTime

Function

Purpose Get a subscription’s creation time in milliseconds.

C Declaration `tibems_status tibemsSubscriptionInfo_GetCreateTime(
tibemsSubscriptionInfo subscriptionInfo,
tibems_long* created);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetCreateTime"
USING BY VALUE subscriptionInfo,
BY REFERENCE created,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|---|
| subscriptionInfo | Get the creation time of this subscription. |
| created | The function stores the create time in this location. |

tibemsSubscriptionInfo_GetID

Function

Purpose Get the subscription’s unique ID.

C Declaration `tibems_status tibemsSubscriptionInfo_GetID(
tibemsSubscriptionInfo subscriptionInfo,
tibems_long* id);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetID"
USING BY VALUE subscriptionInfo,
BY REFERENCE id,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|---|
| subscriptionInfo | Get the unique ID of this subscription. |
| id | The function stores the subscription ID in this location. |

tibemsSubscriptionInfo_GetName

Function

Purpose Get the name of the subscription.

C Declaration `tibems_status tibemsSubscriptionInfo_GetName(
tibemsSubscriptionInfo subscriptionInfo,
char* name,
tibems_int* nameLength);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetName"
USING BY VALUE subscriptionInfo,
BY REFERENCE name,
BY REFERENCE nameLength,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|---|
| subscriptionInfo | Get the name of this subscription. |
| name | The function copies the subscription name in the provided buffer. |
| nameLength | Length of the name buffer. |

tibemsSubscriptionInfo_GetPendingMessageCount

Function

Purpose Get the number of pending messages for a subscription.

C Declaration `tibems_status tibemsSubscriptionInfo_GetPendingMessageCount(
tibemsSubscriptionInfo subscriptionInfo,
tibems_long* msgCount);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetPendingMessageCount"
USING BY VALUE subscriptionInfo,
BY REFERENCE msgCount,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| subscriptionInfo | Get the number of pending messages for this subscription. |
| msgCount | The function stores the number of pending messages in this location. |

See Also [tibemsSubscriptionInfo_GetPendingMessageSize on page 526](#)

tibemsSubscriptionInfo_GetPendingMessageSize

Function

Purpose Get the combined size of pending messages for a subscription.

C Declaration `tibems_status tibemsSubscriptionInfo_GetPendingMessageSize(
tibemsSubscriptionInfo subscriptionInfo,
tibems_long* msgSize);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetPendingMessageSize"
USING BY VALUE subscriptionInfo,
BY REFERENCE msgSize,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|---|
| subscriptionInfo | Get the combined pending messages size for this subscription. |
| msgSize | The function stores the combined size of pending messages in this location. |

See Also [tibemsSubscriptionInfo_GetPendingMessageCount on page 525](#)

tibemsSubscriptionInfo_GetSelector

Function

Purpose Returns this subscription's selector.

C Declaration `tibems_status tibemsSubscriptionInfo_GetSelector(
tibemsSubscriptionInfo subscriptionInfo,
char* selector,
tibems_int selectorLength);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetSelector"
USING BY VALUE subscriptionInfo,
BY REFERENCE selector,
BY VALUE selectorLength,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| subscriptionInfo | Get the selector for this subscription. |
| selector | The function copies the selector into the given buffer. If there is no selector, the empty string is copied. |
| selectorLength | Length of the selector buffer. |

tibemsSubscriptionInfo_GetTopicName

Function

Purpose Get the topic name that this subscription is for.

C Declaration `tibems_status tibemsSubscriptionInfo_GetTopicName(
tibemsSubscriptionInfo subscriptionInfo,
char* topicName,
tibems_int topicNameLength);`

COBOL Call `CALL "tibemsSubscriptionInfo_GetTopicName"
USING BY VALUE subscriptionInfo,
BY REFERENCE topicName,
BY VALUE topicNameLength,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| subscriptionInfo | Get the topic name that this subscription is for. |
| topicName | The function copies the topic name in this buffer. |
| topicNameLength | Length of the topicName buffer. |

tibemsSubscriptionInfo_HasSelector

Function

Purpose Gets whether the subscription has a selector.

C Declaration `tibems_status tibemsSubscriptionInfo_HasSelector(
tibemsSubscriptionInfo subscriptionInfo,
tibems_bool* hasSelector);`

COBOL Call `CALL "tibemsSubscriptionInfo_HasSelector"
USING BY VALUE subscriptionInfo,
BY REFERENCE hasSelector,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| subscriptionInfo | Get the selector status for this subscription. |
| hasSelector | The function stores the status of the selector in this location. The value is TIBEMS_TRUE if the subscription has a selector, TIBEMS_FALSE if not. |

See Also [tibemsSubscriptionInfo_GetSelector on page 527](#)

tibemsSubscriptionInfo_IsDurable

Function

Purpose Get whether this is a durable subscription.

C Declaration `tibems_status tibemsSubscriptionInfo_IsDurable(
tibemsSubscriptionInfo subscriptionInfo,
tibems_bool* durable);`

COBOL Call `CALL "tibemsSubscriptionInfo_IsDurable"
USING BY VALUE subscriptionInfo,
BY REFERENCE durable,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|------------------|--|
| | subscriptionInfo | Get wether this subscription is a durable subscription. |
| | durable | The function stores subscription durable status in this location. TIBEMS_TRUE indicates that the subscription is a durable subscription. |

tibemsSubscriptionInfo_IsShared

Function

Purpose Get whether this is a shared subscription.

C Declaration `tibems_status tibemsSubscriptionInfo_IsShared(
tibemsSubscriptionInfo subscriptionInfo,
tibems_bool* shared);`

COBOL Call `CALL "tibemsSubscriptionInfo_IsShared"
USING BY VALUE subscriptionInfo,
BY REFERENCE shared,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|------------------|--|
| subscriptionInfo | Get wether this subscription is a shared subscription. |
| shared | The function stores subscription shared status in this location. TIBEMS_TRUE indicates that subscription is a shared subscription. |

tibemsTopicInfo

Type

Purpose Represent a topic that is configured in the server.

| Function | Description | Page |
|--|--|---------------------|
| tibemsTopicInfo_Create | Create a tibemsTopicInfo object. | 534 |
| tibemsTopicInfo_Destroy | Destroy a tibemsTopicInfo object. | 535 |
| tibemsTopicInfo_GetActiveDurableCount | Get the current number of active durable subscribers for this topic. | 536 |
| tibemsTopicInfo_GetDurableSubscriptionCount | Get the current number of durable subscriptions for this topic. | 538 |
| tibemsTopicInfo_GetFlowControlMaxBytes | Get the volume of pending message bytes at which flow control is enabled for the topic. | 539 |
| tibemsTopicInfo_GetInboundStatistics | Get inbound statistics for this topic. | 540 |
| tibemsTopicInfo_GetMaxBytes | Get the maximum number of bytes of pending messages bound for this topic that the server will store. | 541 |
| tibemsTopicInfo_GetMaxMsgs | Get the maximum number of pending messages bound for the topic that the server will store. | 542 |
| tibemsTopicInfo_GetName | Get the name of this topic. | 543 |
| tibemsTopicInfo_GetOutboundStatistics | Get outbound statistics for this topic. | 544 |
| tibemsTopicInfo_GetOverflowPolicy | Get the overflow policy for this topic. | 545 |
| tibemsTopicInfo_GetPendingMessageCount | Get the total number of pending messages for this topic. | 546 |
| tibemsTopicInfo_GetPendingMessageSize | Get the total size of all pending messages for this topic. | 547 |
| tibemsTopicInfo_GetPendingPersistentMessageCount | Get the total number of pending messages for this topic that were sent persistently. | 548 |

| Function | Description | Page |
|---|--|------|
| tibemsTopicInfo_GetPendingPersistentMessageSize | Get the total size of all pending messages for this topic that were sent persistently. | 549 |
| tibemsTopicInfo_GetSubscriberCount | Get the number of subscribers on this topic. | 550 |
| tibemsTopicInfo_GetSubscriptionCount | Get the current number of subscriptions for this topic. | 551 |

Related Types [tibemsStatData](#) on page 514

tibemsTopicInfo_Create

Function

Purpose Create a tibemsTopicInfo object.

C Declaration `tibems_status tibemsTopicInfo_Create(
tibemsTopicInfo* topicInfo,
const char* topicName);`

COBOL Call `CALL "tibemsTopicInfo_Create"
USING BY REFERENCE topicInfo,
BY REFERENCE name,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Store the new tibemsTopicInfo object in this location. |
| | topicName | Create the tibemsTopicInfo object with this name. The topicName can include wildcards. |

Remarks This function is used to create a tibemsTopicInfo object with the specified name. The tibemsTopicInfo object may then be passed as the tibemsDestinationInfo argument to the [tibemsAdmin_GetConsumers](#) and [tibemsAdmin_GetProducerStatistics](#) functions. The name may include wildcards.

For more information on wildcards, see [Wildcards on page 77](#) of the *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsQueueInfo_Create on page 493](#)
[tibemsAdmin_GetConsumers on page 434](#)
[tibemsAdmin_GetProducerStatistics on page 438](#)

tibemsTopicInfo_Destroy

Function

Purpose Destroy a tibemsTopicInfo object.

C Declaration `tibems_status tibemsTopicInfo_Destroy(
tibemsTopicInfo topicInfo);`

COBOL Call `CALL "tibemsTopicInfo_Destroy"
USING BY VALUE topicInfo,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--------------------------------------|
| | topicInfo | Destroy this tibemsTopicInfo object. |

See Also [tibemsQueueInfo_Destroy on page 494](#)

tibemsTopicInfo_GetActiveDurableCount

Function

Purpose Get the current number of active durable subscribers for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetActiveDurableCount(
tibemsTopicInfo topicInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsTopicInfo_GetActiveDurableCount"
USING BY VALUE topicInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| topicInfo | Get the number of subscribers to this topic. |
| count | The function stores the number of active durable subscribers in this location. |

See Also [tibemsTopicInfo_GetSubscriberCount on page 550](#)
[tibemsTopicInfo_GetSubscriptionCount on page 551](#)
[tibemsTopicInfo_GetDurableSubscriptionCount on page 538](#)

tibemsTopicInfo_GetDurableCount

Function



This function is deprecated in Software Release 8.0.0, and will no longer be supported in future releases. Applications should be updated to use the [tibemsTopicInfo_GetDurableSubscriptionCount](#) function.

Purpose Get the current number of durable subscribers for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetDurableCount(
tibemsTopicInfo topicInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsTopicInfo_GetDurableCount"
USING BY VALUE topicInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|---|
| topicInfo | Get the number of subscribers to this topic. |
| count | The function stores the number of subscribers in this location. |

See Also [tibemsTopicInfo_GetActiveDurableCount on page 536](#)
[tibemsTopicInfo_GetSubscriberCount on page 550](#)

tibemsTopicInfo_GetDurableSubscriptionCount

Function

Purpose Get the current number of durable subscriptions for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetDurableSubscriptionCount(
tibemsTopicInfo topicInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsTopicInfo_GetDurableSubscriptionCount"
USING BY VALUE topicInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`



count has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| topicInfo | Get the count for this topic. |
| count | The function stores the number of shared subscriptions in this location. |

See Also [tibemsTopicInfo_GetSubscriptionCount on page 551](#)
[tibemsTopicInfo_GetActiveDurableCount on page 536](#)
[tibemsTopicInfo_GetSubscriberCount on page 550](#)

tibemsTopicInfo_GetFlowControlMaxBytes

Function

Purpose Get the volume of pending message bytes at which flow control is enabled for the topic.

C Declaration `tibems_status tibemsTopicInfo_GetFlowControlMaxBytes(
tibemsTopicInfo topicInfo,
tibems_long* maxBytes);`

COBOL Call `CALL "tibemsTopicInfo_GetFlowControlMaxBytes"
USING BY VALUE topicInfo,
BY REFERENCE maxBytes,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | topicInfo | Get the volume for this topic. |
| | maxBytes | The function stores the volume in this location. The value stored indicates the volume of pending messages, in bytes, that the server will store for the topic before enabling flow control. A value of 0 indicates that flow control will never be enabled. |

See Also [tibemsQueueInfo_GetFlowControlMaxBytes on page 496](#)

tibemsTopicInfo_GetInboundStatistics

Function

Purpose Get inbound statistics for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetInboundStatistics(
tibemsTopicInfo topicInfo,
tibemsStatData* statData);`

COBOL Call `CALL "tibemsTopicInfo_GetInboundStatistics"
USING BY VALUE topicInfo,
BY REFERENCE statData,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Get statistics for this topic. |
| | statData | The function stores the statistics in this location. |

Remarks This function retrieves the inbound statistics for the topic. Inbound statistics include all messages sent by EMS clients and routed servers.

See Also [tibemsQueueInfo_GetInboundStatistics on page 497](#)

tibemsTopicInfo_GetMaxBytes

Function

Purpose Get the maximum number of bytes of pending messages bound for this topic that the server will store.

C Declaration `tibems_status tibemsTopicInfo_GetMaxBytes(
tibemsTopicInfo topicInfo,
tibems_long* maxBytes);`

COBOL Call `CALL "tibemsTopicInfo_GetMaxBytes"
USING BY VALUE topicInfo,
BY REFERENCE maxBytes,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|---|
| topicInfo | Get the number of bytes for this server. |
| maxBytes | The function stores the number of bytes in this location. |

See Also [tibemsQueueInfo_GetMaxBytes on page 498](#)

tibemsTopicInfo_GetMaxMsgs

Function

Purpose Get the maximum number of pending messages bound for the topic that the server will store.

C Declaration `tibems_status tibemsTopicInfo_GetMaxMsgs(
tibemsTopicInfo topicInfo,
tibems_long* maxMsgs);`

COBOL Call `CALL "tibemsTopicInfo_GetMaxMsgs"
USING BY VALUE topicInfo,
BY REFERENCE maxMsgs,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| topicInfo | Get the number of messages for this topic. |
| maxMsgs | The function stores the number of messages in this location. |

See Also [tibemsQueueInfo_GetMaxMsgs on page 499](#)

tibemsTopicInfo_GetName

Function

Purpose Get the name of this topic.

C Declaration `tibems_status tibemsTopicInfo_GetName(
tibemsTopicInfo topicInfo,
char* name,
tibems_int name_len);`

COBOL Call `CALL "tibemsTopicInfo_GetName"
USING BY VALUE topicInfo,
BY REFERENCE name,
BY VALUE name_len,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Get the name of this topic. |
| | name | The function stores the topic name in this location. |
| | name_len | Length of the name buffer. |

See Also [tibemsQueueInfo_GetName on page 500](#)

tibemsTopicInfo_GetOutboundStatistics

Function

Purpose Get outbound statistics for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetOutboundStatistics(
tibemsTopicInfo topicInfo,
tibemsStatData* statData);`

COBOL Call `CALL "tibemsTopicInfo_GetOutboundStatistics"
USING BY VALUE topicInfo,
BY REFERENCE statData,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Get statistics for this topic. |
| | statData | The function stores the statistics in this location. |

Remarks This function retrieves the outbound statistics for the topic. Outbound statistics include all messages delivered by the topic to EMS clients and routed servers.

See Also [tibemsQueueInfo_GetOutboundStatistics on page 501](#)

tibemsTopicInfo_GetOverflowPolicy

Function

Purpose Get the overflow policy for this topic.

C Declaration

```
tibems_status tibemsTopicInfo_GetOverflowPolicy(  
    tibemsTopicInfo topicInfo,  
    tibems_int* overflowPolicy);
```

COBOL Call

```
CALL "tibemsTopicInfo_GetOverflowPolicy"  
    USING BY VALUE topicInfo,  
          BY REFERENCE overflowPolicy,  
          RETURNING tibems-status  
END-CALL.
```

Parameters

| Parameter | Description |
|----------------|---|
| topicInfo | |
| overflowPolicy | The function stores the overflow policy in this location. |

Remarks This function retrieves the overflow policy for the queue. Possible values are:

- TIBEMS_OVERFLOW_DEFAULT
- TIBEMS_OVERFLOW_DISCARD_OLD
- TIBEMS_OVERFLOW_REJECT_INCOMING

For more information about overflow policies, see the *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsQueueInfo_GetOverflowPolicy on page 502](#)

tibemsTopicInfo_GetPendingMessageCount

Function

Purpose Get the total number of pending messages for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetPendingMessageCount(
tibemsTopicInfo topicInfo,
tibems_long* count);`

COBOL Call `CALL "tibemsTopicInfo_GetPendingMessageCount"
USING BY VALUE topicInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| topicInfo | Get the number of messages for this topic. |
| count | The function stores the number of messages in this location. |

See Also [tibemsQueueInfo_GetPendingMessageCount on page 503](#)

tibemsTopicInfo_GetPendingMessageSize

Function

Purpose Get the total size of all pending messages for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetPendingMessageSize(
tibemsTopicInfo topicInfo,
tibems_long* count);`

COBOL Call `CALL "tibemsTopicInfo_GetPendingMessageSize"
USING BY VALUE topicInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Get the size of messages for this topic. |
| | count | The function stores the size of pending messages in this location. |

See Also [tibemsQueueInfo_GetPendingMessageSize on page 504](#)

tibemsTopicInfo_GetPendingPersistentMessageCount

Function

Purpose Get the total number of pending messages for this topic that were sent persistently.

C Declaration `tibems_status tibemsTopicInfo_GetPendingPersistentMessageCount(tibemsTopicInfo topicInfo, tibems_long* count);`

COBOL Call `CALL "tibemsTopicInfo_GetPendingPersistentMessageCount"
USING BY VALUE topicInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Get the number of messages for this topic. |
| | count | The function stores the number of messages in this location. |

See Also [tibemsQueueInfo_GetPendingPersistentMessageCount on page 505](#)

tibemsTopicInfo_GetPendingPersistentMessageSize

Function

Purpose Get the total size of all pending messages for this topic that were sent persistently.

C Declaration `tibems_status tibemsTopicInfo_GetPendingPersistentMessageSize(
tibemsTopicInfo topicInfo,
tibems_long* size);`

COBOL Call `CALL "tibemsTopicInfo_GetPendingPersistentMessageSize"
USING BY VALUE topicInfo,
BY REFERENCE size,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|--|
| | topicInfo | Get the size of messages for this topic. |
| | count | The function stores the size of pending messages in this location. |

See Also [tibemsQueueInfo_GetPendingPersistentMessageSize on page 506](#)

tibemsTopicInfo_GetSubscriberCount

Function

Purpose Get the number of subscribers on this topic.

C Declaration `tibems_status tibemsTopicInfo_GetSubscriberCount(
tibemsTopicInfo topicInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsTopicInfo_GetSubscriberCount"
USING BY VALUE topicInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`

Parameters

| Parameter | Description |
|-----------|--|
| topicInfo | Get the count for this topic. |
| count | The function stores the number of active subscribers in this location. |

See Also [tibemsTopicInfo_GetActiveDurableCount on page 536](#)
[tibemsTopicInfo_GetSubscriptionCount on page 551](#)
[tibemsTopicInfo_GetDurableSubscriptionCount on page 538](#)

tibemsTopicInfo_GetSubscriptionCount

Function

Purpose Get the current number of subscriptions for this topic.

C Declaration `tibems_status tibemsTopicInfo_GetSubscriptionCount(
tibemsTopicInfo topicInfo,
tibems_int* count);`

COBOL Call `CALL "tibemsTopicInfo_GetSubscriptionCount"
USING BY VALUE topicInfo,
BY REFERENCE count,
RETURNING tibems-status
END-CALL.`



count has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| topicInfo | Get the count for this topic. |
| count | The function stores the number of subscriptions in this location. |

See Also [tibemsTopicInfo_GetDurableSubscriptionCount on page 538](#)

Chapter 16 **Exception**

This chapter presents exceptions related to EMS.

Topics

- [tibems_status](#), page 554
- [tibemsErrorContext](#), page 561

tibems_status

Type

Purpose Functions return status codes to indicate return conditions.

Table 15 Status Codes

| Constant | Code | Description |
|----------------------------|------|--|
| TIBEMS_OK | 0 | The call completed normally. |
| TIBEMS_ILLEGAL_STATE | 1 | <p>A function call or server request occurred in an inappropriate context.</p> <p>For example, <code>tibemsSession_Commit</code> indicates this status when the session is non-transactional.</p> |
| TIBEMS_INVALID_CLIENT_ID | 2 | <p>The provider rejects the connection’s client ID.</p> <p>Setting a connection’s client ID to an invalid or duplicate value results in this exception. (A duplicate value is one that is already in use by another connection.)</p> |
| TIBEMS_INVALID_DESTINATION | 3 | <code>tibemsd</code> cannot locate the destination. |
| TIBEMS_INVALID_SELECTOR | 4 | The client passed a message selector with invalid syntax; see Message Selectors on page 17 . |
| TIBEMS_EXCEPTION | 5 | Non-specific error code. |
| TIBEMS_SECURITY_EXCEPTION | 6 | <p>The function cannot complete because of a security restriction.</p> <p>For example, the provider rejects a user or the user’s authentication.</p> |

Table 15 Status Codes

| Constant | Code | Description |
|-----------------------------|------|---|
| TIBEMS_MSG_EOF | 7 | <p>The data stream within a message ended unexpectedly.</p> <p>tibemsBytesMsg contains a stream of bytes. tibemsStreamMsg contains a stream of characters. If any of their read functions detects the end of a stream unexpectedly, it indicates this status.</p> |
| TIBEMS_MSG_NOT_READABLE | 9 | Attempt to read from a message in write-only mode. |
| TIBEMS_MSG_NOT_WRITEABLE | 10 | <p>Attempt to write to a message in read-only mode.</p> <p>See also, tibemsMsg_MakeWriteable on page 55.</p> |
| TIBEMS_SERVER_NOT_CONNECTED | 11 | <ul style="list-style-type: none"> • An attempt to connect to the server has failed. • The operation requires a server connection, but the program is not connected. |
| TIBEMS_SUBJECT_COLLISION | 13 | The server cannot create a topic or durable because the name is already in use. (Also applies to collisions with external subjects, such as Rendezvous.) |
| TIBEMS_INVALID_PROTOCOL | 15 | Cannot create a connection or transaction because the specified protocol does not exist. |
| TIBEMS_INVALID_HOSTNAME | 17 | <p>The connection URL includes an invalid hostname, or an attempt to lookup the host address failed.</p> <p>Host names must be less than 128 characters.</p> |
| TIBEMS_INVALID_PORT | 18 | The connection URL includes an invalid port number. |

Table 15 Status Codes

| Constant | Code | Description |
|---------------------------|------|--|
| TIBEMS_NO_MEMORY | 19 | The program exceeded available memory during the call. |
| TIBEMS_INVALID_ARG | 20 | The function received an illegal value as an argument. |
| TIBEMS_SERVER_LIMIT | 21 | The server has exceeded the maximum number of licensed connections or hosts that it can service. |
| TIBEMS_NOT_PERMITTED | 27 | The function call is not permitted (for example, closing a connection within a callback). |
| TIBEMS_SERVER_RECONNECTED | 28 | Exception callback handler functions receive this code to indicate that the server has reconnected. See tibemsExceptionCallback on page 233 |
| TIBEMS_INVALID_NAME | 30 | In a lookup request, the name has incorrect syntax. The most common syntax error is a prefix other than <code>tibjmsnaming://</code> (or a misspelling). See also, tibemsLookupContext on page 334 . |
| TIBEMS_INVALID_SIZE | 32 | An argument is outside the range of valid values. |
| TIBEMS_NOT_FOUND | 35 | 1. The name lookup repository cannot find a name; the name is not bound. See also, tibemsLookupContext on page 334 2. A function that gets a message field or property value cannot find the specified item because the name is not bound in the message. |

Table 15 Status Codes

| Constant | Code | Description |
|-----------------------------------|------|---|
| TIBEMS_CONVERSION_FAILED | 38 | A datatype conversion failed while parsing a message (converting UTF-8 data to native datatypes). |
| TIBEMS_INVALID_MSG | 42 | The message is uninitialized or corrupt. |
| TIBEMS_INVALID_FIELD | 43 | The message contains an invalid field. The message might be corrupt. |
| TIBEMS_CORRUPT_MSG | 45 | The message is corrupt. |
| TIBEMS_TIMEOUT | 50 | The timeout has expired while waiting for a message. See tibemsMsgConsumer_ReceiveTimeout on page 172. |
| TIBEMS_INTR | 51 | A blocking operation has been interrupted. See tibemsMsgConsumer_Receive on page 170. |
| TIBEMS_DESTINATION_LIMIT_EXCEEDED | 52 | A server queue or topic has exceeded its size limit, and cannot add a new message. |
| TIBEMS_MEM_LIMIT_EXCEEDED | 53 | The server has exceeded its memory limit. |
| TIBEMS_USER_INTR | 54 | IBM z/OS only. A blocking operation has been interrupted. See tibx_MVSConsole_SetConsumer() on page 572. |
| TIBEMS_INVALID_IO_SOURCE | 65 | The function detected an invalid I/O source (such as a socket or file). |
| TIBEMS_OS_ERROR | 68 | An operating system error occurred during the call. |
| TIBEMS_INSUFFICIENT_BUFFER | 70 | The result of the call overflowed the buffer supplied by the program. |
| TIBEMS_EOF | 71 | The call detected an unexpected end-of-file. |
| TIBEMS_INVALID_FILE | 72 | The function detected an invalid file. |

Table 15 Status Codes

| Constant | Code | Description |
|------------------------------------|------|---|
| TIBEMS_FILE_NOT_FOUND | 73 | The specified file does not exist. |
| TIBEMS_IO_FAILED | 74 | An operating system I/O call failed. |
| TIBEMS_ALREADY_EXISTS | 91 | Cannot create an item that already exists. |
| TIBEMS_INVALID_CONNECTION | 100 | The connection is invalid. |
| TIBEMS_INVALID_SESSION | 101 | The session is invalid. |
| TIBEMS_INVALID_CONSUMER | 102 | The consumer is invalid. |
| TIBEMS_INVALID_PRODUCER | 103 | The producer is invalid. |
| TIBEMS_INVALID_USER | 104 | The server could not authenticate the user. |
| TIBEMS_TRANSACTION_FAILED | 106 | A transaction failed at the server during a commit call. |
| TIBEMS_TRANSACTION_ROLLBACK | 107 | Failure during prepare or commit caused automatic rollback of a transaction. This type of rollback can occur during fault tolerance failover. |
| TIBEMS_TRANSACTION_RETRY | 108 | A transaction failed during two-phase commit; the program may attempt to commit it again. |
| TIBEMS_INVALID_XARESOURCE | 109 | When a session uses an XA transaction manager, the XA resource is the correct locus for all commit and rollback requests. Local commit or rollback calls are not permitted, and indicate this status. |
| TIBEMS_FT_SERVER_LACKS_TRANSACTION | 110 | The producer attempted to send a message immediately after a fault tolerance failover to another server. The new server has no record of the transaction. |
| TIBEMS_NOT_INITIALIZED | 200 | Initialization of the tibems library failed. For example, this code could be generated if the library failed to allocate memory while building its basic structures. |

Table 15 Status Codes

| Constant | Code | Description |
|-----------------------------|------|--|
| SSL | | |
| TIBEMS_INVALID_CERT | 150 | SSL detected an invalid X.509 certificate. |
| TIBEMS_INVALID_CERT_NOT_YET | 151 | SSL detected an X.509 certificate that is not yet valid; that is, the current date is before the first date for which the certificate becomes valid. |
| TIBEMS_INVALID_CERT_EXPIRED | 152 | SSL detected an X.509 certificate that is no longer valid; that is, the current date is after the expiration date. |
| TIBEMS_INVALID_CERT_DATA | 153 | SSL detected an X.509 certificate containing corrupt data. |
| TIBEMS_ALGORITHM_ERROR | 154 | Error loading a cipher suite algorithm. |
| TIBEMS_SSL_ERROR | 155 | Generic SSL error code. |
| TIBEMS_INVALID_PRIVATE_KEY | 156 | SSL detected a private key that does not match its public key. |
| TIBEMS_INVALID_ENCODING | 157 | SSL detected a certificate encoding that it cannot read. |
| TIBEMS_NOT_ENOUGH_RANDOM | 158 | SSL lacks sufficient random data to complete an operation securely. |
| Unimplemented | | |
| TIBEMS_NOT_IMPLEMENTED | 255 | The function is not implemented. |

tibemsStatus_GetText

Function

Purpose Get the text string corresponding to a status code.

C Declaration `const char* tibemsStatus_GetText(
tibems_status status);`

COBOL Call `CALL "tibemsStatus_GetText"
USING BY VALUE status
RETURNING tibems-Pointer
END-CALL.`

| Parameters | Parameter | Description |
|------------|-----------|---|
| | status | Get the text corresponding to this status code. |

tibemsErrorContext

Type

Purpose Enable additional error tracking

Remarks The `tibemsErrorContext` objects collect additional error information beyond the status returned by most EMS calls. When a `tibemsErrorContext` is created, EMS records detailed error information and a stack trace for the last error detected inside the EMS client library. Upon encountering an EMS error, the error information is written to the `tibemsErrorContext` object and then cleared at the start of the next public EMS function call.

Because each thread of execution in an application may contain specific error information, `tibemsErrorContext` objects should be created at the start of each thread and then destroyed before exiting the thread. Threads spawned internally by EMS will automatically create `tibemsErrorContext` objects.

| Function | Description | Page |
|---|---|------|
| tibemsErrorContext_Create | Create a new error context object. | 562 |
| tibemsErrorContext_Close | Close and free memory associated with an error context. | 563 |
| tibemsErrorContext_GetLastErrorString | Retrieve any available detailed error string associated with the last EMS call. | 564 |
| tibemsErrorContext_GetLastErrorStackTrace | Retrieve a stack trace associated with the last EMS call. | 565 |

tibemsErrorContext_Create

Function

Purpose Create a new error context object.

C Declaration `tibems_status tibemsErrorContext_Create(
tibemsErrorContext* errorContext);`

COBOL Call `CALL "tibemsErrorContext_Create"
USING BY REFERENCE errorContext,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|---|
| | errorContext | The function stores the new error context in this location. |

Remarks Create a new error context object and enables detailed error information and stack tracing for the thread that calls this function.

Returns TIBEMS_OK, TIBEMS_INVALID_ARG, or TIBEMS_NO_MEMORY.

See Also [tibemsErrorContext_Close on page 563](#)

tibemsErrorContext_Close

Function

Purpose Close and free memory associated with an error context.

C Declaration `tibems_status tibemsErrorContext_Close(
tibemsErrorContext errorContext);`

COBOL Call `CALL "tibemsErrorContext_Close"
USING BY VALUE errorContext,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|---------------------------|
| | errorContext | Close this error context. |

Remarks Returns TIBEMS_OK, TIBEMS_INVALID_ARG.

See Also [tibemsErrorContext_Create on page 562](#)

tibemsErrorContext_GetLastErrorString

Purpose Retrieve any available detailed error string associated with the last EMS call.

C Declaration `tibems_status tibemsErrorContext_GetLastErrorString(
tibemsErrorContext errorContext,
const char** string);`

COBOL Call `CALL "tibemsErrorContext_GetLastErrorString"
USING BY VALUE errorContext,
BY REFERENCE string,
RETURNING tibems-status
END-CALL.`

| Parameters | Parameter | Description |
|------------|--------------|--|
| | errorContext | The error context. |
| | string | Location of the detailed error string. |

Remarks Error string includes the day and time the error occurred.

Passing NULL for the errorContext parameter will default to the error context of the current thread. This is useful for retrieving information from within a listener or exception callback. This function returns a pointer, not a copy of the error string. If the last call was considered a non-error, an empty string is returned.

Returns TIBEMS_OK, TIBEMS_INVALID_ARG (string is null, or passing an object created in a different thread), TIBEMS_NOT_INITIALIZED (no error context for this thread)

See Also [tibemsErrorContext_GetLastErrorStackTrace on page 565](#)

tibemsErrorContext_GetLastErrorStackTrace

Purpose Retrieve a stack trace associated with the last EMS call.

C Declaration `tibems_status tibemsErrorContext_GetLastErrorStackTrace(
tibemsErrorContext errorContext,
const char** string);`

COBOL Call CALL "tibemsErrorContext_GetLastErrorStackTrace"
USING BY VALUE errorContext,
BY REFERENCE string,
RETURNING tibems-status
END-CALL.

| Parameters | Parameter | Description |
|------------|--------------|-------------------------------------|
| | errorContext | The error context. |
| | string | Location of the stack trace string. |

Remarks Passing NULL for the errorContext parameter will default to the error context of the current thread. This is useful for retrieving information from within a listener or exception callback. This function returns a pointer, not a copy of the stack trace string. If the last call was considered a non-error, an empty string is returned.

Returns TIBEMS_OK, TIBEMS_INVALID_ARG (string is null, or passing an object created in a different thread), TIBEMS_NOT_INITIALIZED (no error context for this thread)

See Also [tibemsErrorContext_GetLastErrorString on page 564](#)

Chapter 17 **IBM z/OS and IBM i**

This chapter presents items of interest only to programmers coding for IBM z/OS and IBM i native operating systems.

Topics

- [IBM EBCDIC Platform Calls, page 568](#)
 - [tibems_SetCodePages\(\), page 569](#)
- [IBM z/OS Functions, page 571](#)
 - [tibx_MVSConsole_SetConsumer\(\), page 572](#)
 - [tibx_MVSConsole_Create\(\), page 573](#)
 - [Console_Response, page 575](#)
- [SSL Implementation on IBM EBCDIC Systems, page 576](#)

IBM EBCDIC Platform Calls

The calls we present on the following pages are implemented only on IBM EBCDIC platforms.

tibems_SetCodePages()

Function

Purpose Set code pages for string conversion on EBCDIC platforms (when non-default code pages are required).

C Declaration `tibems_status tibems_SetCodePages(
char* host_codepage,
char* net_codepage);`

COBOL Call `CALL "tibems_SetCodePages"
USING BY REFERENCE host-codepage,
BY REFERENCE net-codepage,
RETURNING TIBEMS-STATUS
END-CALL.`

| Parameters | Parameter | Description |
|------------|---------------|---|
| | host_codepage | Set this code page as the native (EBCDIC) character encoding for the host computer. |
| | net_codepage | Set this code page as the ASCII or UTF-8 character set for the network. |

String Conversion EMS software uses the operating system’s `iconv()` call to automatically convert strings within messages. Conversion occurs only as needed:

- Programs running in EBCDIC environments represent all strings using an EBCDIC code page (called the *host code page*). Before sending a message, the EMS client library converts its strings to an ASCII or UTF-8 character set (the *network code page*).
- Conversely, when a message arrives from the network, the EMS client library converts its strings to the EBCDIC host code page before presenting the message to the program.

Remarks This call sets the host and network code pages for string conversions in EBCDIC environments.

Call this function when the system code pages differ from the EMS default code pages (see the table of [Default Code Pages on page 570](#)). Throughout an enterprise, all sending and receiving programs must use the same code pages.

Both arguments are string names of code pages. To determine valid code page names for your operating system, see documentation from the operating system vendor.

Programs may call this function at most once. The call *must* precede the first call to any message function, and the arrival of the first message from the network.

Default Code Pages To use a default code page, programs may supply NULL for either parameter. Using the default code pages in both parameter positions has the same effect as not calling this function at all.

| Default Host Code Page | Default Network Code Page |
|------------------------|---------------------------|
| "IBM-1047" | "ISO8859-1" |

See Also [Strings and Character Encodings on page 4](#)

IBM z/OS Functions

These functions are implemented only on IBM z/OS platforms.

tibx_MVSConsole_SetConsumer()

Function

Purpose Exit from a blocking listener.

C Declaration

```
tibx_MVSConsole_SetConsumer(  
    void* pConsole,  
    tibemsMsgConsumer tibemsMsgConsumer,  
    char* tibems_MVS_BreakFunction);  
  
signed long int tibems_MVS_BreakFunction(  
    void* pConsole );
```

COBOL Call

```
SET WS-PROCEDURE-PTR TO ENTRY 'tibems_MVS_BreakFunction'  
  
CALL "tibx_MVSConsole_SetConsumer"  
    USING BY VALUE    pConsole,  
          BY VALUE    tibemsMsgConsumer,  
          BY VALUE    pFunction,  
          RETURNING   tibems-status  
END-CALL.
```



pConsole has usage pointer.
Before this call, you must set the entry to the MVS break function.

Parameters

| Parameter | Description |
|--------------------------|---|
| pConsole | Set the consumer of this MVS console object. |
| tibemsMsgConsumer | Use this message consumer. |
| pFunction | In COBOL, use this tibems_MVS_BreakFunction function address. |
| tibems_MVS_BreakFunction | In C, use this break function name. |

Remarks Programs in single-threaded environments (such as COBOL) need a way to interrupt blocking receive calls (such as [tibemsMsgConsumer_Receive](#)).
After registering this function in COBOL, a console stop or shut command causes the receive call to return with a status code TIBEMS_USER_INTR (54).

See Also [tibemsMsgConsumer_Receive](#) on page 170
[tibx_MVSConsole_Create\(\)](#) on page 573

tibx_MVSConsole_Create()

Function

Purpose Create or destroy an MVS console.

C Declaration

```
signed long int tibx_MVSConsole_Create (
    void** pConsole,
    char** pConsoleMsg,
    Console_Response pCallBack)

signed long int tibx_MVSConsole_Destroy(
    void* pConsole );
```

COBOL Call

```
CALL "tibx_MVSConsole_Create"
    USING BY REFERENCE pConsole,
          BY REFERENCE pConsoleMsg,
          BY VALUE      TIBEMS-NULLPTR,
          RETURNING     tibems-status
END-CALL.

CALL "tibx_MVSConsole_Destroy"
    USING BY VALUE pConsole,
          RETURNING tibems-status
END-CALL.
```



pConsole and pConsole-Msg have usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| pConsole | The create call stores the MVS console handle in this location. The destroy call destroys this MVS console. |
| pConsoleMsg | When the return status code is non-zero, the function stores an error message in this location. |
| pCallBack | C programs define this callback function to receive the results of MVS console commands. |

Remarks Some consumer application programs wait indefinitely for messages to arrive. You can use this function in conjunction with `tibems_MVS_BreakFunction` to arrange console input to such programs, in order to interrupt them from waiting to receive a message, so they can exit cleanly (see [tibx_MVSConsole_SetConsumer\(\)](#) on page 572).

C programs can receive console command results through a callback function. COBOL programs cannot receive console command results, but can react to the MVS `stop` and `shut` commands.

See Also [tibemsMsgConsumer_Receive on page 170](#)
 [tibx_MVSConsole_SetConsumer\(\) on page 572](#)

Console_Response

Function Type

Purpose Callback function to relay the results of MVS console commands to C programs.

C Declaration

```
signed long int  
Console_Response(  
    signed long int rc,  
    char* ops_command );
```

Parameters

| Parameter | Description |
|---------------------|--|
| rc | This parameter receives the return status code from the MVS console. |
| ops_command | This parameter receives the operator command from the MVS console. |
| <i>return value</i> | Zero indicates a normal return. All other values indicate a special console command—namely, stop or shut. |

Remarks Available only in C for z/OS MVS.
COBOL does not support callback functions.

See Also [tibx_MVSConsole_Create\(\) on page 573](#)

SSL Implementation on IBM EBCDIC Systems

On z/OS and IBM i systems, secure connections are created using IBM System SSL. To implement IBM System SSL for TIBCO Enterprise Message Service, you must set the necessary environment variables, and use the API documented in the sections below.

Additionally, the EMS client application must run within the context of a user ID which has the necessary privileges to access the IBM System SSL facility. For details about these requirements, see the section on SSL requirements in the *TIBCO EMS Client for z/OS (MVS) Installation and Reference*, or the *TICBO EMS Client for IBM i Installation and Reference*.

IBM System SSL Environment Variables on z/OS

There are some System SSL environment variables related to tracing and debug messages which must be specified before the EMS library is loaded.



Tracing is supported only on z/OS systems.

These environment variables are discussed in the IBM System Secure Sockets Layer programming guide, but a short summary is provided here:

- Set the file name (USS only) for raw trace records:

— `GSK_TRACE_FILE <trace file name>`

— `GSK_TRACE <mask>` — specify 255 to trace everything

These two values enable detailed tracing of all GSK calls to a file. The file may subsequently be formatted for viewing using the `gsktrace` command.

- `GSK_HW_CRYPT0 <crypto mask>` — 65535 to enable all, 0 to disable all hardware cryptographic functions.
- `GSK_SSL_HW_DETECT_MESSAGE` — if set, causes brief messages regarding the state of the installed hardware to be written to `stdout` when the application is started.

Call Summary

Table 16 provides a list of the API calls used to configure IBM System SSL.

Table 16 IBM System SSL Calls

| IBM System SSL API | Use On | Corresponding Open SSL API |
|---|---------------|---|
| tibemsSSL_System_GetTrace tibemsSSL_System_GetDebugTrace | z/OS IBM i | tibemsSSL_GetTrace tibemsSSL_GetDebugTrace |
| tibemsSSL_System_SetFipsMode | z/OS | IBM System SSL only |
| tibemsSSL_System_SetTrace tibemsSSL_System_SetDebugTrace | z/OS IBM i | tibemsSSL_SetTrace tibemsSSL_SetDebugTrace |
| tibemsSSL_System_Version | z/OS IBM i | tibemsSSL_OpenSSLVersion |
| tibemsSSLParams_System_Create | z/OS IBM i | tibemsSSLParams_Create |
| tibemsSSLParams_System_Destroy | z/OS IBM i | tibemsSSLParams_Destroy |
| tibemsSSLParams_System_SetApplicationId | IBM i | IBM System SSL only |
| tibemsSSLParams_System_SetAuthOnly | z/OS IBM i | tibemsSSLParams_SetAuthOnly |
| tibemsSSLParams_System_SetCiphers | z/OS IBM i | tibemsSSLParams_SetCiphers |
| tibemsSSLParams_System_SetEnableSSLV3 | z/OS IBM i | IBM System SSL only |
| tibemsSSLParams_System_SetEnableTLS1 | z/OS IBM i | IBM System SSL only |
| tibemsSSLParams_System_SetExpectedHostName | z/OS IBM i | tibemsSSLParams_SetExpectedHostName |
| tibemsSSLParams_System_SetKeyRingFile | z/OS IBM i | IBM System SSL only |
| tibemsSSLParams_System_SetLabel | z/OS IBM i | IBM System SSL only |

Table 16 IBM System SSL Calls

| IBM System SSL API | Use On | Corresponding Open SSL API |
|--|---------------|---|
| tibemsSSLParams_System_SetLdapServerPassword | z/OS | IBM System SSL only |
| tibemsSSLParams_System_SetLdapServerUrl | z/OS | IBM System SSL only |
| tibemsSSLParams_System_SetLdapServerUserid | z/OS | IBM System SSL only |
| tibemsSSLParams_System_SetVerifyHostName | z/OS IBM i | tibemsSSLParams_SetVerifyHost |

tibemsSSL_System_GetTrace

Function

Purpose Determine whether SSL tracing is enabled.

C Declaration `tibems_bool tibemsSSL_System_GetTrace(void);`
`tibems_bool tibemsSSL_System_GetDebugTrace(void);`

COBOL Call `CALL "tibemsSSL_System_GetTrace"`
`RETURNING value-Boolean`
`END-CALL.`
`CALL "tibemsSSL_System_GetDebugTrace"`
`RETURNING value-Boolean`
`END-CALL.`

Remarks Two levels of SSL tracing are available—regular tracing and debug tracing (more detailed).

If tracing is enabled, these calls return TIBEMS_TRUE.

If tracing is disabled, they return TIBEMS_FALSE.

See Also [tibemsSSL_GetTrace on page 236](#)

tibemsSSL_System_SetFipsMode

Function

Purpose Enable or disable FIPS 140-2 mode.

C Declaration `tibems_status tibemsSSL_System_SetFipsMode(
tibems_bool enabled)`

COBOL Call CALL "tibemsSSLParams_System_SetFipsMode"
USING BY VALUE fipsEnabled,
RETURNING tibems-status
END-CALL.

IBM i This function is not supported on IBM i systems.

| Parameters | Parameter | Description |
|------------|-------------|---|
| | fipsEnabled | When TIBEMS_TRUE, FIPS mode is enabled. When TIBEMS_FALSE, FIPS mode is disabled. |

Remarks This call, while closely associated with the SSL parameters calls, does not actually set or reset a parameter value. Rather, it enables at an application-wide scope the use (or disuse) of FIPS mode.

This call must be made before any other System SSL related calls and before instantiating an SSL connection factory.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

tibemsSSL_System_SetTrace

Function

Purpose Enable or disable trace messages on the creation of TIBCO Enterprise Message Service connections. These messages indicate the status of various stages of connection creation.

C Declaration

```
void tibemsSSL_System_SetTrace(  
    tibems_bool trace );  
  
void tibemsSSL_System_SetDebugTrace(  
    tibems_bool trace );
```

COBOL Call

```
CALL "tibemsSSL_System_SetTrace"  
    USING BY VALUE trace  
END-CALL.  
  
CALL "tibemsSSL_System_SetDebugTrace"  
    USING BY VALUE trace  
END-CALL.
```

| Parameters | Parameter | Description |
|------------|-----------|--|
| | trace | TIBEMS_TRUE enables tracing. TIBEMS_FALSE disables tracing. |

Remarks Two levels of SSL tracing are available—regular tracing and debug tracing (more detailed). Trace messages are written to standard output while connecting or reconnecting to the server. These messages can be helpful in diagnosing a failure to connect.

See Also [tibemsSSL_SetTrace on page 238](#)

tibemsSSL_System_Version

Function

Purpose Get a string representing the IBM System SSL version number.

C Declaration

```
const char* tibemsSSL_System_Version(  
    char* buffer,  
    tibems_int buf_size );
```

COBOL Call

```
MOVE LENGTH OF buffer TO buf-size.  
  
CALL "tibemsSSL_System_Version"  
    USING BY REFERENCE buffer,  
          BY VALUE buf-size,  
          RETURNING value-Pointer  
END-CALL.
```



buffer has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| buffer | The function copies the version string in this buffer. |
| buf_size | Length (in bytes) of the buffer. |

Remarks On z/OS, the version string has the format *major.minor.update*.
On IBM i, version number information is not available. A string representing the underlying System SSL programming interface is copied to the buffer.
A null character terminates the version string.

See Also [tibemsSSL_OpenSSLVersion on page 237](#)

tibemsSSLParams_System_Create

Function

Purpose Create a new IBM System SSL parameter object.

C Declaration `tibemsSSLParams tibemsSSLParams_System_Create(void);`

COBOL Call CALL "tibemsSSLParams_System_Create"
RETURNING SSLParams
END-CALL.



SSLParams has usage pointer.

Remarks Storage is allocated to contain the values associated with various SSL parameters. This call must precede any call that requires an SSL parameters object as an argument.

See Also [tibemsSSLParams_Create on page 242](#)

tibemsSSLParams_System_Destroy

Function

Purpose Destroy an IBM System SSL parameter object.

C Declaration `void tibemsSSLParams_System_Destroy(
tibemsSSLParams SSLParams);`

COBOL Call `CALL "tibemsSSLParams_System_Destroy"
USING BY VALUE SSLParams
END-CALL.`



SSLParams has usage pointer.

| Parameters | Parameter | Description |
|------------|-----------|------------------------------------|
| | SSLParams | Destroy this SSL parameter object. |

Remarks Storage related to the parameters object and all individual parameters therein is released.

See Also [tibemsSSLParams_Destroy on page 243](#)

tibemsSSLParams_System_SetApplicationId

Function

Purpose Set the application ID to be used by this application.

C Declaration `tibems_status tibemsSSLParams_System_SetApplicationId(
tibemsSSLParams params,
const char* application_id);`

COBOL Call `CALL "tibemsSSLParams_System_SetApplicationId"
USING BY VALUE params,
BY REFERENCE application-id,
RETURNING tibems-status
END-CALL.`



application-id has usage pointer.

IBM z/OS This function is not supported on IBM z/OS systems.

Parameters

| Parameter | Description |
|----------------|--|
| params | Set the value in this SSL parameter object. |
| application_id | The application ID for the application definition. |

Remarks The IBM i Digital Certificate Manager may be used to create a client application definition and assign it a certificate to be used during an SSL handshake. Part of the application definition is the application ID, which uniquely identifies the application definition. More information about application definitions may be found in the IBM i Information Center, Security, Digital Certificate Manager.

This is a global parameter. As a result, the first connection made by the application establishes the application ID to be used by all other connections within this address space. Any attempt to specify a different application ID for subsequent connections will be ignored.

Because a connection requires either an application ID *or* a certificate store and label—but not both—setting this parameter causes any parameters set with [tibemsSSLParams_System_SetKeyRingFile](#) and [tibemsSSLParams_System_SetLabel](#) to be ignored.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

See Also [tibemsSSLParams_System_SetKeyRingFile](#)
[tibemsSSLParams_System_SetLabel](#)

tibemsSSLParams_System_SetAuthOnly

Function

Purpose Limit the use of IBM System SSL to improve performance.

C Declaration `tibems_status tibemsSSLParams_System_SetAuthOnly(
tibemsSSLParams SSLParams,
tibems_bool auth_only);`

COBOL Call `CALL "tibemsSSLParams_System_SetAuthOnly"
USING BY VALUE SSLParams,
BY VALUE auth_only,
RETURNING tibems-status
END-CALL.`



SSLParams has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| SSLParams | Set the value in this SSL parameter object. |
| auth_only | TIBEMS_TRUE instructs the SSL parameter object to request a connection that uses SSL only for authentication. TIBEMS_FALSE instructs the SSL parameter object to request a connection that uses SSL to secure all data. |

Remarks This parameter is connection-specific and can be specified for each connection.
For background information, see [SSL Authentication Only on page 518](#) in *TIBCO Enterprise Message Service User's Guide*.

See Also [tibemsSSLParams_SetAuthOnly on page 246](#)

tibemsSSLParams_System_SetCiphers

Function

Purpose Set the cipher suites for IBM System SSL connections.

C Declaration `tibems_status tibemsSSLParams_System_SetCiphers(
tibemsSSLParams SSLParams,
const char* ciphers);`

COBOL Call `CALL "tibemsSSLParams_System_SetCiphers"
USING BY VALUE SSLParams,
BY REFERENCE ciphers,
RETURNING tibems-status
END-CALL.`



SSLParams has usage pointer.

Parameters

| Parameter | Description |
|-----------|---|
| SSLParams | Set the value in this SSL parameter object. |
| ciphers | <p>Specify the cipher suites that the client can use.</p> <p>The ciphers provided should conform to the cipher suite specifications for IBM System SSL:</p> <ul style="list-style-type: none"> For a detailed description of these ciphers on z/OS, see the IBM Cryptographic Services, System Secure Sockets Layer Programming bookshelf. For a description of the ciphers on IBM i, refer to the IBM i Information Center, Programming, Communications, Socket Programming, Advanced socket concepts, Secure Sockets, Global Security Toolkit (GSKit) APIs. <p>Note that only the SSLV3 and TLSV1 protocol and associated ciphers are enabled.</p> <p>Supported ciphers are listed below.</p> |

Remarks This parameter is connection-specific and can be specified for each connection. On z/OS, only the indicated CIPHERS are allowed in FIPS mode.

[Table 17](#) below list the supported ciphers.

Table 17 Ciphers Supported in IBM System SSL

| Cipher | Description | Use On | FIPS |
|--------|---|---------------|------|
| 03 | 40-bit RC4 encryption with MD5 message authentication and RSA key exchange. | z/OS | No |
| 04 | 128-bit RC4 encryption with MD5 message authentication and RSA key exchange. | z/OS IBM i | No |
| 05 | 128-bit RC4 encryption with SHA-1 message authentication and RSA key exchange. | z/OS IBM i | No |
| 06 | 40-bit RC2 encryption with MD5 message authentication and RSA key exchange. | z/OS | No |
| 09 | 56-bit DES encryption with SHA-1 message authentication and RSA key exchange. | z/OS IBM i | No |
| 0A | 168-bit Triple DES encryption with SHA-1 message authentication and RSA key exchange. | z/OS IBM i | Yes |
| 15 | 56-bit DES encryption with SHA-1 message authentication and ephemeral Diffie-Hellman key exchange signed with an RSA certificate. | z/OS | No |
| 16 | 168-bit Triple DES encryption with SHA-1 message authentication and ephemeral Diffie-Hellman key exchange signed with an RSA certificate. | z/OS | Yes |
| 2F | 128-bit AES encryption with SHA-1 message authentication and RSA key exchange. | z/OS IBM i | Yes |
| 33 | 128-bit AES encryption with SHA-1 message authentication and ephemeral Diffie-Hellman key exchange signed with an RSA certificate. | z/OS | Yes |
| 35 | 256-bit AES encryption with SHA-1 message authentication and RSA key exchange. | z/OS IBM i | Yes |
| 39 | 256-bit AES encryption with SHA-1 message authentication and ephemeral Diffie-Hellman key exchange signed with an RSA certificate. | z/OS | Yes |

These ciphers are specified in a string with no spaces or other delimiters. For example "333539".

See Also [tibemsSSLParams_SetCiphers on page 247](#)

tibemsSSLParams_System_SetEnableSSLV3

Function

Purpose Enable or disable the SSLV3 protocol.

C Declaration `tibems_status` tibemsSSLParams_System_SetEnableSSLV3(
 `tibemsSSLParams` params,
 `tibems_bool` SSLV3enabled)

COBOL Call CALL "tibemsSSLParams_System_SetEnableSSLV3"
 USING BY VALUE params,
 BY VALUE SSLV3enabled,
 RETURNING tibems_status
 END-CALL.



params has usage pointer.

Parameters

| Parameter | Description |
|--------------|--|
| params | The SSL parameter object. |
| SSLV3enabled | Specify TIBEMS_TRUE or TIBEMS_FALSE to enable or disable the SSLV3 protocol. This protocol is enabled by default. |

Remarks Note that by default the SSLV3 and TLSV1 protocols are enabled. Disabling both of them results in a "No SSL cipher specifications" error mesage (if tracing is enabled).

This parameter is connection-specific and can be specified for each connection.

tibemsSSLParams_System_SetEnableTLS1

Function

Purpose Enable or disable the TLSV1 protocol.

C Declaration `tibems_status tibemsSSLParams_System_SetEnableTLS1(
tibemsSSLParams params,
tibems_bool TLS1enabled)`

COBOL Call `CALL "tibemsSSLParams_System_SetEnableTLS1"
USING BY VALUE params,
BY VALUE TLS1enabled,
RETURNING tibems_status
END-CALL.`



params has usage pointer.

Parameters

| Parameter | Description |
|-------------|--|
| params | The SSL parameter object. |
| TLS1enabled | Specify TIBEMS_TRUE or TIBEMS_FALSE to enable or disable the TLSV1 protocol. This protocol is enabled by default. |

Remarks Note that by default the SSLV3 and TLSV1 protocols are enabled. Disabling both of them will result in a "No SSL cipher specifications" error mesage (if tracing is enabled).

This parameter is connection-specific and can be specified for each connection.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

tibemsSSLParams_System_SetExpectedHostName

Function

Purpose Set the expected host name.

C Declaration `tibems_status tibemsSSLParams_System_SetExpectedHostName(
tibemsSSLParams SSLParams,
const char* expected_hostname);`

COBOL Call `CALL "tibemsSSLParams_System_SetExpectedHostName"
USING BY VALUE SSLParams,
BY REFERENCE expected-hostname,
RETURNING tibems-status
END-CALL.`



SSLParams and expected_hostname have usage pointer.

Parameters

| Parameter | Description |
|-------------------|---|
| SSLParams | Set the value in this SSL parameter object. |
| expected_hostname | Use this value. |

Remarks This parameter applies when establishing an SSL connection to the EMS server. If host name verification is enabled, the EMS client compares the name specified in this call to the CN of the certificate presented by the server during the initial SSL handshake. If they are not the same, the connection fails.

This parameter is connection-specific and can be specified for each connection.

See Also [tibemsSSLParams_SetExpectedHostName on page 248](#)

tibemsSSLParams_System_SetKeyRingFile

Function

Purpose Set the SAF key ring to be used by this application.

C Declaration `tibems_status tibemsSSLParams_System_SetKeyRingFile(
tibemsSSLParams params,
const char* keyring_file)`

COBOL Call `CALL "tibemsSSLParams_System_SetKeyRingFile"
USING BY VALUE params,
BY REFERENCE keyring_file,
RETURNING tibems-status
END-CALL.`



params and keyring_file have usage pointer.

Parameters

| Parameter | Description |
|--------------|---|
| params | The SSL parameter object. |
| keyring_file | On z/OS, the name of the SAF key ring on which the certificates for this application reside. On IBM i, the name of the certificate store defined within the Digital Certificate Manager. For example, *SYSTEM. |

Remarks This is a global parameter which means that the first connection made by the application will establish the key ring or certificate store to be used by all other connections within this address space. Any attempt to specify a different key ring for subsequent connections will be ignored.

On z/OS, this parameter is required to make a connection. On IBM i this parameter is required to make a connection if no application ID parameter has been set. If an application ID is set, the key ring file parameter is ignored.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

See Also [tibemsSSLParams_System_SetLabel on page 594](#)
[tibemsSSLParams_System_SetApplicationId on page 585](#)

tibemsSSLParams_System_SetLabel

Function

Purpose Set the certificate to be used to make the connection.

C Declaration `tibems_status tibemsSSLParams_System_SetLabel(
tibemsSSLParams params,
const char* keyring_label)`

COBOL Call `CALL "tibemsSSLParams_System_SetLabel"
USING BY VALUE SSLParams,
BY REFERENCE keyring_label,
RETURNING tibems-status
END-CALL.`



SSLParams and keyring_label have usage pointer.

Parameters

| Parameter | Description |
|---------------|--|
| params | The SSL parameter object. |
| keyring_label | The name of the certificate label on the chosen SAF key ring or certificate store to use when creating the connection. |

Remarks This is a connection-specific parameter and can be separately specified for each connection. The label parameter is optional. If it is not specified, the system uses the default certificate on the key ring. If there is no default certificate, the connection fails.

On IBM i, this parameter setting is ignored if the application ID parameter has been set.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

See Also [tibemsSSLParams_System_SetKeyRingFile on page 593](#)
[tibemsSSLParams_System_SetApplicationId on page 585](#)

tibemsSSLParams_System_SetLdapServerPassword

Function

Purpose Set the password to be used to access LDAP for certificates and CRLs.

C Declaration `tibems_status tibemsSSLParams_System_SetLdapServerPassword(
tibemsSSLParams params,
const char* password)`

COBOL Call `CALL "tibemsSSLParams_System_SetLdapServerPassword"
USING BY VALUE SSLParams,
BY REFERENCE password,
RETURNING tibems-status
END-CALL.`



SSLParams and password have usage pointer.

IBM i This function is not supported on IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | params | The SSL parameter object. |
| | password | The password to be used when authenticating with the LDAP server. |

Remarks Once LDAP parameters are established, these parameters remain in effect for the life of the client application, and cannot be overridden by subsequent specifications. The first connection to be established sets the LDAP parameters for all subsequent connections.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

See Also [tibemsSSLParams_System_SetLdapServerUrl on page 596](#)
[tibemsSSLParams_System_SetLdapServerUserid on page 597](#)

tibemsSSLParams_System_SetLdapServerUrl

Function

Purpose Set the server URLs to be used to access LDAP for certificates and CRLs.

C Declaration `tibems_status tibemsSSLParams_System_SetLdapServerUrl(
tibemsSSLParams params,
const char* urls)`

COBOL Call `CALL "tibemsSSLParams_System_SetLdapServerUrl"
USING BY VALUE SSLParams,
BY REFERENCE urls,
RETURNING tibems-status
END-CALL.`



SSLParams and password have usage pointer.

IBM i This function is not supported on IBM i systems.

Parameters

| Parameter | Description |
|-----------|--|
| params | The SSL parameter object. |
| urls | The URLs of the LDAP servers to be used for obtaining trusted certificates and CRLs. The format of the URL is: server[:port] server2[:port2] where <i>server</i> is the EMS server name or IP address and port is the server port number. If the server runs on the standard LDAP port, 389, specifying the <i>port</i> parameter is optional. Specify multiple servers in a space delimited string. |

Remarks Once LDAP parameters are established, these parameters remain in effect for the life of the client application, and cannot be overridden by subsequent specifications. The first connection to be established sets the LDAP parameters for all subsequent connections.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

See Also [tibemsSSLParams_System_SetLdapServerPassword on page 595](#)
[tibemsSSLParams_System_SetLdapServerUserid on page 597](#)

tibemsSSLParams_System_SetLdapServerUserId

Function

Purpose Set the user ID to be used to access LDAP for certificates and CRLs.

C Declaration `tibems_status tibemsSSLParams_System_SetLdapServerUserId(
tibemsSSLParams params,
const char* userid)`

COBOL Call `CALL "tibemsSSLParams_System_SetLdapServerUserId"
USING BY VALUE SSLParams,
BY REFERENCE userid,
RETURNING tibems-status
END-CALL.`



SSLParams and password have usage pointer.

IBM i This function is not supported on IBM i systems.

| Parameters | Parameter | Description |
|------------|-----------|---|
| | params | The SSL parameter object. |
| | userid | The user IDto be used when authenticating with the LDAP server. |

Remarks Once the LDAP parameters are established, these parameters remain in effect for the life of the client application, and cannot be overridden by subsequent specifications. That is, the first connection to be established sets the LDAP parameters for all subsequent connections.

Returns TIBEMS_OK if it succeeds, otherwise TIBEMS_SSL_ERROR.

See Also [tibemsSSLParams_System_SetLdapServerPassword on page 595](#)
[tibemsSSLParams_System_SetLdapServerUrl on page 596](#)

tibemsSSLParams_System_SetVerifyHostName

Function

Purpose Enables or disables the verification of the server's hostname during connection creation.

C Declaration `tibems_status tibemsSSLParams_System_SetVerifyHostName(
tibemsSSLParams SSLParams,
tibems_bool verify);`

COBOL Call `CALL "tibemsSSLParams_System_SetVerifyHostName"
USING BY VALUE SSLParams,
BY VALUE verify,
RETURNING tibems-status
END-CALL.`



SSLParams has usage pointer.

Parameters

| Parameter | Description |
|-----------|--|
| SSLParams | Set the value in this SSL parameter object. |
| verify | TIBEMS_TRUE enables verification. TIBEMS_FALSE disables verification. |

Remarks `tibemsSSLParams_System_SetVerifyHostName` enables checking the server’s actual host name against an expected server host name. If no "expected hostname" has been established, the server's fully qualified hostname is compared with the CN in the certificate presented by the server during the initial handshake. If they are not equal, the connection fails.

This parameter is connection-specific and can be specified for each connection.

This verification action is enabled by default (unless a program explicitly disables it).

See Also [tibemsSSLParams_System_SetExpectedHostName](#) on page 592

Index

A

Acknowledge [25](#)

B

body type [140](#)
 body types, message [9](#)
 BytesMessage
 Write methods [86](#)

C

changes from the previous release [xx](#)
 character encoding [4](#), [4](#)
 clear body [27](#)
 clear properties [28](#)
 client tracing
 tibems_SetTraceFile [421](#)
 code pages [569](#)
 Connection [210](#)
 connection factories [257](#)
 ConnectionConsumer (not supported) [3](#)
 Console_Response [575](#)
 console, MVS [573](#)
 conversion, data type [20](#)
 copy a message [30](#)
 create a message [29](#)
 create message from byte array [31](#)
 customer support [xxvi](#)

D

data type conversion [20](#)
 delivery mode [129](#)
 Destination
 overview [142](#)
 destroy message [32](#)
 dynamic destination [142](#)

E

EBCDIC [569](#)
 encoding, character [4](#)
 exceptions [553](#)

F

fault tolerance
 ActiveURL [217](#)

G

Get
 MapMessage [92](#)
 get
 message properties [47](#)

H

headers, message [10](#)

L

LookupContext [334](#)

M

MapMessage

 Get methods [92](#)

 set methods [98](#)

Message

 Acknowledge [25](#)

 body types [9](#)

 headers [10](#)

 parts of [8](#)

 properties [14](#)

 recover [59](#)

 set property methods [68](#)

message

 get property [47](#)

 selectors [17](#)

message body type [140](#)

MessageConsumer [164](#)

MessageProducer.Close [182](#)

MessageProducer.Send [178](#), [191](#)

multicast

 enable client [277](#)

 exception callback [234](#)

 multicast daemon [276](#)

MVS console [573](#)

O

ObjectMessage [105](#)

P

property, message [14](#)

 set [68](#)

proxy, SSL [284](#), [285](#)

Q

Queue [152](#)

QueueBrowser [328](#)

R

Read

 StreamMethod [113](#)

read

 tibemsBytesMsg [79](#)

read-only [27](#), [31](#)

recover message [59](#)

request [10](#)

S

selectors, message [17](#)

ServerSession (not supported) [3](#)

ServerSessionPool (not supported) [3](#)

Set

 MapMessage [98](#)

 message property [68](#)

set

 code pages [569](#)

SSL proxy [284](#), [285](#)

static destination [142](#)

StreamMessage

 Read methods [113](#)

 Write methods [119](#)

string and character encoding [4](#)

string encoding

 EBCDIC [569](#)

support, contacting [xxvi](#)

T

technical support [xxvi](#)

temporary destination [142](#)

TIBCO_HOME [xxiii](#)
 tibems_Close [391](#)
 tibems_GetAllowCloseInCallback [392](#)
 tibems_GetConnectAttemptCount [393](#)
 tibems_GetConnectAttemptDelay [394](#)
 tibems_GetConnectAttemptTimeout [395](#)
 tibems_GetExceptionOnFTEvents [396](#)
 tibems_getExceptionOnFTSwitch [397, 412](#)
 tibems_GetMulticastDaemon [398](#)
 tibems_GetMulticastEnabled [399](#)
 tibems_GetReconnectAttemptCount [400](#)
 tibems_GetReconnectAttemptDelay [401](#)
 tibems_GetReconnectAttemptTimeout [402](#)
 tibems_GetSocketReceiveBufferSize [403](#)
 tibems_GetSocketSendBufferSize [404](#)
 tibems_IsConsumerMulticast [405](#)
 tibems_MVS_BreakFunction [572](#)
 tibems_SetAllowCloseInCallback [407](#)
 tibems_SetCodePages() [569](#)
 tibems_SetConnectAttemptCount [408](#)
 tibems_SetConnectAttemptDelay [409](#)
 tibems_SetConnectAttemptTimeout [410](#)
 tibems_SetExceptionOnFTEvents [411](#)
 tibems_SetMulticastDaemon [413](#)
 tibems_SetMulticastEnabled [414](#)
 tibems_SetMulticastExceptionListener [415](#)
 tibems_SetReconnectAttemptCount [416](#)
 tibems_SetReconnectAttemptDelay [417](#)
 tibems_SetReconnectAttemptTimeout [418](#)
 tibems_SetSocketReceiveBufferSize [419](#)
 tibems_SetSocketSendBufferSize [420](#)
 tibems_SetTraceFile [421](#)
 tibems_Sleep [422](#)
 tibems_status [554](#)
 tibems_Version [423](#)
 tibemsAcknowledgeMode [324](#)
 tibemsAdmin [427](#)
 tibemsAdmin_Close [429](#)
 tibemsAdmin_Create [430](#)
 tibemsAdmin_GetCommandTimeout [432](#)
 tibemsAdmin_GetConsumer [433](#)
 tibemsAdmin_GetConsumers [434](#)
 tibemsAdmin_GetInfo [437](#)
 tibemsAdmin_GetProducerStatistics [438](#)
 tibemsAdmin_GetQueue [440](#)
 tibemsAdmin_GetQueues [441](#)
 tibemsAdmin_GetSubscriptions [443](#)
 tibemsAdmin_GetTopic [445](#)
 tibemsAdmin_GetTopics [446](#)
 tibemsAdmin_SetCommandTimeout [448](#)
 tibemsAdmin_SetExceptionListener [449](#)
 tibemsBytesMsg [75](#)
 read [79](#)
 tibemsBytesMsg_Create [76](#)
 tibemsBytesMsg_GetBodyLength [77](#)
 tibemsBytesMsg_GetBytes [78](#)
 tibemsBytesMsg_ReadBoolean [79](#)
 tibemsBytesMsg_ReadByte [79](#)
 tibemsBytesMsg_ReadBytes [82](#)
 tibemsBytesMsg_ReadChar [79](#)
 tibemsBytesMsg_ReadDouble [79](#)
 tibemsBytesMsg_ReadFloat [79](#)
 tibemsBytesMsg_ReadInt [79](#)
 tibemsBytesMsg_ReadLong [79](#)
 tibemsBytesMsg_ReadShort [79](#)
 tibemsBytesMsg_ReadUnsignedByte [79](#)
 tibemsBytesMsg_ReadUnsignedShort [79](#)
 tibemsBytesMsg_Reset [84](#)
 tibemsBytesMsg_SetBytes [85](#)
 tibemsBytesMsg_WriteBoolean [86](#)
 tibemsBytesMsg_WriteByte [86](#)
 tibemsBytesMsg_WriteBytes [89](#)
 tibemsBytesMsg_WriteChar [86](#)
 tibemsBytesMsg_WriteDouble [86](#)
 tibemsBytesMsg_WriteFloat [86](#)
 tibemsBytesMsg_WriteInt [86](#)
 tibemsBytesMsg_WriteLong [86](#)
 tibemsBytesMsg_WriteShort [86](#)
 tibemsCollection [450](#)
 tibemsCollection_Destroy [451](#)
 tibemsCollection_GetCount [452](#)
 tibemsCollection_GetFirst [453](#)
 tibemsCollection_GetNext [454](#)
 tibemsConnection_Close [212](#)
 tibemsConnection_Create [214](#)
 tibemsConnection_CreateSession [216](#)
 tibemsConnection_CreateSSL [214](#)
 tibemsConnection_GetActiveURL [217](#)
 tibemsConnection_GetClientId [218](#)
 tibemsConnection_GetExceptionListener [219](#)

- [tibemsConnection_GetMetaData](#) 220
- [tibemsConnection_IsDisconnected](#) 221
- [tibemsConnection_SetClientId](#) 222
- [tibemsConnection_SetExceptionListener](#) 223
- [tibemsConnection_Start](#) 224
- [tibemsConnection_Stop](#) 225
- [tibemsConnectionFactory](#) 258
- [tibemsConnectionFactory_Create](#) 261
- [tibemsConnectionFactory_CreateConnection](#) 262
- [tibemsConnectionFactory_CreateXAConnection](#) 263
- [tibemsConnectionFactory_Destroy](#) 264
- [tibemsConnectionFactory_Print](#) 269
- [tibemsConnectionFactory_PrintToBuffer](#) 270
- [tibemsConnectionFactory_SetClientID](#) 271
- [tibemsConnectionFactory_SetConnectAttemptCount](#) 272
- [tibemsConnectionFactory_SetConnectAttemptDelay](#) 273
- [tibemsConnectionFactory_SetConnectAttemptTimeout](#) 274
- [tibemsConnectionFactory_SetMetric](#) 275
- [tibemsConnectionFactory_SetMulticastDaemon](#) 276
- [tibemsConnectionFactory_SetMulticastEnabled](#) 277
- [tibemsConnectionFactory_SetPkPassword](#) 278
- [tibemsConnectionFactory_SetReconnectAttemptCount](#) 279
- [tibemsConnectionFactory_SetReconnectAttemptDelay](#) 280
- [tibemsConnectionFactory_SetReconnectAttemptTimeout](#) 281
- [tibemsConnectionFactory_SetServerURL](#) 282
- [tibemsConnectionFactory_SetSSLParams](#) 283
- [tibemsConnectionFactory_SetSSLProxy](#) 284
- [tibemsConnectionFactory_SetSSLProxyAuth](#) 285
- [tibemsConnectionFactory_SetSSLProxyHost](#) 265
- [tibemsConnectionFactory_SetSSLProxyPassword](#) 268
- [tibemsConnectionFactory_SetSSLProxyPort](#) 266
- [tibemsConnectionFactory_SetSSLProxyUser](#) 267
- [tibemsConnectionFactory_SetUserName](#) 286
- [tibemsConnectionFactory_SetUserPassword](#) 287
- [tibemsConnectionMetaData](#) 227
- [tibemsConnectionMetaData_GetEMSMajorVersion](#) 228
- [tibemsConnectionMetaData_GetEMSMinorVersion](#) 228
- [tibemsConnectionMetaData_GetEMSProviderName](#) 232, 232
- [tibemsConnectionMetaData_GetEMSVersion](#) 228
- [tibemsConnectionMetaData_GetProviderMajorVersion](#) 230, 230
- [tibemsConnectionMetaData_GetProviderMinorVersion](#) 230, 230
- [tibemsConnectionMetaData_GetProviderVersion](#) 230, 230
- [tibemsConsumerInfo](#) 455
- [tibemsConsumerInfo_Destroy](#) 458
- [tibemsConsumerInfo_GetCreateTime](#) 459
- [tibemsConsumerInfo_GetCurrentMsgCountSentByServer](#) 460
- [tibemsConsumerInfo_GetCurrentMsgSizeSentByServer](#) 461
- [tibemsConsumerInfo_GetDestinationName](#) 462
- [tibemsConsumerInfo_GetDestinationType](#) 463
- [tibemsConsumerInfo_GetDetailedStatistics](#) 464
- [tibemsConsumerInfo_GetDurableName](#) 465
- [tibemsConsumerInfo_GetElapsedSinceLastAcknowledged](#) 466
- [tibemsConsumerInfo_GetElapsedSinceLastSent](#) 467
- [tibemsConsumerInfo_GetID](#) 468
- [tibemsConsumerInfo_GetPendingMessageCount](#) 469
- [tibemsConsumerInfo_GetPendingMessageSize](#) 470
- [tibemsConsumerInfo_GetSharedSubscriptionName](#) 471
- [tibemsConsumerInfo_GetStatistics](#) 472
- [tibemsConsumerInfo_GetTotalAcknowledgedCount](#) 473
- [tibemsConsumerInfo_GetTotalMsgCountSentByServer](#) 474
- [tibemsConsumerInfo_isActive](#) 475
- [tibemsConsumerInfo_IsConnected](#) 476
- [tibemsConsumerInfo_IsConnectionConsumer](#) 477
- [tibemsConsumerInfo_IsShared](#) 478
- [tibemsd](#) 258, 333
- [tibemsDeliveryMode](#) 129
- [tibemsDestination](#) 146
- [tibemsDestination_Copy](#) 147
- [tibemsDestination_Create](#) 148
- [tibemsDestination_Destroy](#) 149
- [tibemsDestination_GetName](#) 150
- [tibemsDestination_GetType](#) 151

tibemsDetailedDestStat 479
 tibemsDetailedDestStat_GetDestinationName 480
 tibemsDetailedDestStat_GetDestinationType 481
 tibemsDetailedDestStat_GetStatData 482
 tibemsExceptionCallback 233, 234
 tibemsFactoryLoadBalanceMetric 291
 tibemsLookupContext_Create 335
 tibemsLookupContext_CreateExternal 337
 tibemsLookupContext_CreateSSL 335
 tibemsLookupContext_Destroy 338
 tibemsLookupContext_Lookup 339
 tibemsLookupContext_LookupConnectionFactory 33
 9
 tibemsLookupContext_LookupDestination 339
 tibemsLookupParams 341
 tibemsLookupParams_Create 342
 tibemsLookupParams_Destroy 343
 tibemsLookupParams_GetLdapServerUrl 344
 tibemsLookupParams_SetLdapBaseDN 345
 tibemsLookupParams_SetLdapCAFile 346
 tibemsLookupParams_SetLdapCAPath 347
 tibemsLookupParams_SetLdapCertFile 348
 tibemsLookupParams_SetLdapCiphers 349
 tibemsLookupParams_SetLdapConnType 350
 tibemsLookupParams_SetLdapCredential 351
 tibemsLookupParams_SetLdapKeyFile 352
 tibemsLookupParams_SetLdapPrincipal 353
 tibemsLookupParams_SetLdapRandFile 354
 tibemsLookupParams_SetLdapSearchScope 355
 tibemsLookupParams_SetLdapServerUrl 356
 tibemsMapMsg 90
 tibemsMapMsg_Create 91
 tibemsMapMsg_GetBoolean 92
 tibemsMapMsg_GetByte 92
 tibemsMapMsg_GetBytes 92
 tibemsMapMsg_GetChar 92
 tibemsMapMsg_GetDouble 92
 tibemsMapMsg_GetField 92
 tibemsMapMsg_GetFloat 92
 tibemsMapMsg_GetInt 92
 tibemsMapMsg_GetLong 92
 tibemsMapMsg_GetMapMsg 93
 tibemsMapMsg_GetMapNames 96
 tibemsMapMsg_GetShort 93
 tibemsMapMsg_GetString 93
 tibemsMapMsg_ItemExists 97
 tibemsMapMsg_SetBoolean 98
 tibemsMapMsg_SetByte 98
 tibemsMapMsg_SetBytes 103
 tibemsMapMsg_SetChar 98
 tibemsMapMsg_SetDouble 98
 tibemsMapMsg_SetDoubleArray 99
 tibemsMapMsg_SetFloat 98
 tibemsMapMsg_SetFloatArray 99
 tibemsMapMsg_SetInt 98
 tibemsMapMsg_SetIntArray 99
 tibemsMapMsg_SetLong 98
 tibemsMapMsg_SetLongArray 99
 tibemsMapMsg_SetMapMsg 99
 tibemsMapMsg_SetReferencedBytes 103
 tibemsMapMsg_SetShort 98
 tibemsMapMsg_SetShortArray 99
 tibemsMapMsg_SetStreamMsg 99
 tibemsMapMsg_SetString 98
 tibemsMsg 21
 tibemsMsg_Acknowledge 25
 tibemsMsg_ClearBody 27
 tibemsMsg_ClearProperties 28
 tibemsMsg_Create 29
 tibemsMsg_CreateCopy 30
 tibemsMsg_CreateFromBytes 31
 tibemsMsg_Destroy 32
 tibemsMsg_GetAsBytes 33
 tibemsMsg_GetAsBytesCopy 34
 tibemsMsg_GetBodyType 36
 tibemsMsg_GetBooleanProperty 47
 tibemsMsg_GetByteProperty 47
 tibemsMsg_GetByteSize 37
 tibemsMsg_GetCorrelationID 38
 tibemsMsg_GetDeliveryMode 40
 tibemsMsg_GetDeliveryTime 41
 tibemsMsg_GetDestination 42
 tibemsMsg_GetDoubleProperty 47
 tibemsMsg_GetEncoding 43
 tibemsMsg_GetExpiration 44
 tibemsMsg_GetFloatProperty 47
 tibemsMsg_GetIntProperty 47
 tibemsMsg_GetLongProperty 47
 tibemsMsg_GetMessageID 45
 tibemsMsg_GetPriority 46

tibemsMsg_GetProperty 47
 tibemsMsg_GetPropertyNames 50
 tibemsMsg_GetRedelivered 51
 tibemsMsg_GetReplyTo 52
 tibemsMsg_GetShortProperty 47
 tibemsMsg_GetStringProperty 47
 tibemsMsg_GetTimestamp 53
 tibemsMsg_GetType 54
 tibemsMsg_MakeWriteable 55
 tibemsMsg_Print 56
 tibemsMsg_PrintToBuffer 57
 tibemsMsg_PropertyExists 58
 tibemsMsg_Recover 59
 tibemsMsg_SetBooleanProperty 68
 tibemsMsg_SetByteProperty 68
 tibemsMsg_SetCorrelationID 60
 tibemsMsg_SetDeliveryMode 62
 tibemsMsg_SetDestination 63
 tibemsMsg_SetDoubleProperty 68
 tibemsMsg_SetEncoding 64
 tibemsMsg_SetExpiration 65
 tibemsMsg_SetFloatProperty 68
 tibemsMsg_SetIntProperty 68
 tibemsMsg_SetLongProperty 68
 tibemsMsg_SetMessageID 66
 tibemsMsg_SetPriority 67
 tibemsMsg_SetRedelivered 71
 tibemsMsg_SetReplyTo 72
 tibemsMsg_SetShortProperty 68
 tibemsMsg_SetStringProperty 68
 tibemsMsg_SetTimestamp 73
 tibemsMsg_SetType 74
 tibemsMsg_Callback 174
 tibemsMsgConsumer_Close 165
 tibemsMsgConsumer_GetDestination 166
 tibemsMsgConsumer_GetMsgListener 167
 tibemsMsgConsumer_GetMsgSelector 168
 tibemsMsgConsumer_GetNoLocal 169
 tibemsMsgConsumer_Receive 170
 tibemsMsgConsumer_ReceiveNoWait 171
 tibemsMsgConsumer_ReceiveTimeout 172
 tibemsMsgConsumer_SetMsgListener 173
 tibemsMsgEnum_Destroy 133
 tibemsMsgEnum_GetNextName 134
 tibemsMsgField_Print 138
 tibemsMsgField_PrintToBuffer 139
 tibemsMsgProducer 176
 tibemsMsgProducer_AsyncSend 178
 tibemsMsgProducer_Close 182
 tibemsMsgProducer_GetDeliveryDelay 183
 tibemsMsgProducer_GetDeliveryMode 184
 tibemsMsgProducer_GetDestination 185
 tibemsMsgProducer_GetDisableMessageID 186
 tibemsMsgProducer_GetDisableMessageTimestamp 187
 tibemsMsgProducer_GetPriority 189
 tibemsMsgProducer_GetTimeToLive 190
 tibemsMsgProducer_Send 191
 tibemsMsgProducer_SendEx 178, 191
 tibemsMsgProducer_SendToDestination 178, 191
 tibemsMsgProducer_SendToDestinationEx 178, 191
 tibemsMsgProducer_SetDeliveryDelay 194
 tibemsMsgProducer_SetDeliveryMode 195
 tibemsMsgProducer_SetDisableMessageID 196
 tibemsMsgProducer_SetDisableMessageTimestamp 197
 tibemsMsgProducer_SetPriority 200
 tibemsMsgProducer_SetTimeToLive 201
 tibemsMsgRequestor 204
 tibemsMsgRequestor_Close 205
 tibemsMsgRequestor_Create 206
 tibemsMsgRequestor_Request 208
 tibemsMsgType 140
 tibemsObjectMsg_Create 106
 tibemsObjectMsg_GetObjectBytes 107
 tibemsObjectMsg_SetObjectBytes 108
 tibemsProducerInfo 483
 tibemsProducerInfo_Destroy 484
 tibemsProducerInfo_GetCreateTime 485
 tibemsProducerInfo_GetDestinationName 486
 tibemsProducerInfo_GetDestinationType 487
 tibemsProducerInfo_GetDetailedStatistics 488
 tibemsProducerInfo_GetID 489
 tibemsProducerInfo_GetStatistics 490
 tibemsQueue_Create 153
 tibemsQueue_Destroy 154
 tibemsQueue_GetQueueName 155
 tibemsQueueBrowser_Close 329
 tibemsQueueBrowser_GetMsgSelector 330
 tibemsQueueBrowser_GetNext 331

- [tibemsQueueBrowser_GetQueue](#) 332
- [tibemsQueueInfo](#) 491
- [tibemsQueueInfo_Create](#) 493
- [tibemsQueueInfo_Destroy](#) 494
- [tibemsQueueInfo_GetDeliveredMessageCount](#) 495
- [tibemsQueueInfo_GetFlowControlMaxBytes](#) 496
- [tibemsQueueInfo_GetInboundStatistics](#) 497
- [tibemsQueueInfo_GetMaxBytes](#) 498
- [tibemsQueueInfo_GetMaxMsgs](#) 499
- [tibemsQueueInfo_GetName](#) 500
- [tibemsQueueInfo_GetOutboundStatistics](#) 501
- [tibemsQueueInfo_GetOverflowPolicy](#) 502
- [tibemsQueueInfo_GetPendingMessageCount](#) 503
- [tibemsQueueInfo_GetPendingMessageSize](#) 504
- [tibemsQueueInfo_GetPendingPersistentMessageCount](#) 505
- [tibemsQueueInfo_GetPendingPersistentMessageSize](#) 506
- [tibemsQueueInfo_GetReceiverCount](#) 507
- [tibemsServerInfo](#) 508
- [tibemsServerInfo_Destroy](#) 509
- [tibemsServerInfo_GetConsumerCount](#) 510
- [tibemsServerInfo_GetProducerCount](#) 511
- [tibemsServerInfo_GetQueueCount](#) 512
- [tibemsServerInfo_GetTopicCount](#) 513
- [tibemsSession](#) 294
- [tibemsSession_Close](#) 297
- [tibemsSession_Commit](#) 298
- [tibemsSession_CreateBrowser](#) 299
- [tibemsSession_CreateBytesMessage](#) 300
- [tibemsSession_CreateConsumer](#) 301
- [tibemsSession_CreateDurableSubscriber](#) 303
- [tibemsSession_CreateMapMessage](#) 306
- [tibemsSession_CreateMessage](#) 307
- [tibemsSession_CreateProducer](#) 308
- [tibemsSession_CreateSharedConsumer](#) 309
- [tibemsSession_CreateSharedDurableConsumer](#) 311
- [tibemsSession_CreateStreamMessage](#) 313
- [tibemsSession_CreateTemporaryQueue](#) 314
- [tibemsSession_CreateTemporaryTopic](#) 315
- [tibemsSession_CreateTextMessage](#) 316
- [tibemsSession_CreateTextMessageEx](#) 316
- [tibemsSession_DeleteTemporaryQueue](#) 317
- [tibemsSession_DeleteTemporaryTopic](#) 318
- [tibemsSession_GetAcknowledgeMode](#) 319
- [tibemsSession_GetTransacted](#) 320
- [tibemsSession_Recover](#) 321
- [tibemsSession_Rollback](#) 322
- [tibemsSession_Unsubscribe](#) 323
- [tibemsSSL_GetDebugTrace](#) 236, 236
- [tibemsSSL_GetTrace](#) 236
- [tibemsSSL_OpenSSLVersion](#) 237
- [tibemsSSL_SetDebugTrace](#) 238
- [tibemsSSL_SetTrace](#) 238
- [tibemsSSL_System_GetDebugTrace](#) 579
- [tibemsSSL_System_GetTrace](#) 579
- [tibemsSSL_System_SetFipsMode](#) 580
- [tibemsSSL_System_SetTrace](#) 581
- [tibemsSSL_System_Version](#) 582
- [tibemsSSLHostNameVerifier](#) 254
- [tibemsSSLParams_AddIssuerCert](#) 240
- [tibemsSSLParams_AddIssuerCertFile](#) 240
- [tibemsSSLParams_AddTrustedCert](#) 241
- [tibemsSSLParams_AddTrustedCertFile](#) 241
- [tibemsSSLParams_Create](#) 242
- [tibemsSSLParams_Destroy](#) 243
- [tibemsSSLParams_GetIdentity](#) 244
- [tibemsSSLParams_GetPrivateKey](#) 245
- [tibemsSSLParams_SetAuthOnly](#) 246
- [tibemsSSLParams_SetCiphers](#) 247
- [tibemsSSLParams_SetExpectedHostName](#) 248
- [tibemsSSLParams_SetHostNameVerifier](#) 249
- [tibemsSSLParams_SetIdentity](#) 250
- [tibemsSSLParams_SetIdentityFile](#) 250
- [tibemsSSLParams_SetPrivateKey](#) 251
- [tibemsSSLParams_SetPrivateKeyFile](#) 251
- [tibemsSSLParams_SetRandData](#) 252
- [tibemsSSLParams_SetRandEGD](#) 252
- [tibemsSSLParams_SetRandFile](#) 252
- [tibemsSSLParams_SetVerifyHost](#) 253
- [tibemsSSLParams_SetVerifyHostName](#) 253
- [tibemsSSLParams_System_Create](#) 583
- [tibemsSSLParams_System_Destroy](#) 584
- [tibemsSSLParams_System_SetApplicationId](#) 585
- [tibemsSSLParams_System_SetAuthOnly](#) 586
- [tibemsSSLParams_System_SetCiphers](#) 587
- [tibemsSSLParams_System_SetEnableSSLV3](#) 590
- [tibemsSSLParams_System_SetEnableTLS1](#) 591
- [tibemsSSLParams_System_SetExpectedHostName](#) 59

- [tibemsSSLParams_System_SetKeyRingFile 593](#)
- [tibemsSSLParams_System_SetLabel 594](#)
- [tibemsSSLParams_System_SetLdapServerPassword 595](#)
- [tibemsSSLParams_System_SetLdapServerUrl 596](#)
- [tibemsSSLParams_System_SetLdapServerUserid 597](#)
- [tibemsSSLParams_System_SetVerifyHostName 598](#)
- [tibemsStatData 514](#)
- [tibemsStatData_GetByteRate 515](#)
- [tibemsStatData_GetMessageRate 516](#)
- [tibemsStatData_GetTotalBytes 517](#)
- [tibemsStatData_GetTotalMessages 518](#)
- [tibemsStatus_GetText 560](#)
- [tibemsStreamMsg 109](#)
- [tibemsStreamMsg_Create 111](#)
- [tibemsStreamMsg_FreeField 112](#)
- [tibemsStreamMsg_ReadBoolean 113](#)
- [tibemsStreamMsg_ReadByte 113](#)
- [tibemsStreamMsg_ReadBytes 116](#)
- [tibemsStreamMsg_ReadChar 113](#)
- [tibemsStreamMsg_ReadDouble 113](#)
- [tibemsStreamMsg_ReadField 117](#)
- [tibemsStreamMsg_ReadFloat 113](#)
- [tibemsStreamMsg_ReadInt 113](#)
- [tibemsStreamMsg_ReadLong 113](#)
- [tibemsStreamMsg_ReadShort 113](#)
- [tibemsStreamMsg_ReadString 113](#)
- [tibemsStreamMsg_Reset 118](#)
- [tibemsStreamMsg_WriteBoolean 119](#)
- [tibemsStreamMsg_WriteByte 119](#)
- [tibemsStreamMsg_WriteBytes 123](#)
- [tibemsStreamMsg_WriteChar 119](#)
- [tibemsStreamMsg_WriteDouble 119](#)
- [tibemsStreamMsg_WriteDoubleArray 119](#)
- [tibemsStreamMsg_WriteFloat 119](#)
- [tibemsStreamMsg_WriteFloatArray 119](#)
- [tibemsStreamMsg_WriteInt 119](#)
- [tibemsStreamMsg_WriteIntArray 119](#)
- [tibemsStreamMsg_WriteLong 119](#)
- [tibemsStreamMsg_WriteLongArray 120](#)
- [tibemsStreamMsg_WriteMapMsg 120](#)
- [tibemsStreamMsg_WriteShort 119](#)
- [tibemsStreamMsg_WriteShortArray 120](#)
- [tibemsStreamMsg_WriteStreamMsg 120](#)
- [tibemsStreamMsg_WriteString 119](#)
- [tibemsSubscriptionInfo 519](#)
- [tibemsSubscriptionInfo_Destroy 520](#)
- [tibemsSubscriptionInfo_GetConsumerCount 521](#)
- [tibemsSubscriptionInfo_GetCreateTime 522](#)
- [tibemsSubscriptionInfo_GetID 523](#)
- [tibemsSubscriptionInfo_GetName 524](#)
- [tibemsSubscriptionInfo_GetPendingMessageCount 525](#)
- [tibemsSubscriptionInfo_GetPendingMessageSize 526](#)
- [tibemsSubscriptionInfo_GetSelector 527](#)
- [tibemsSubscriptionInfo_GetTopicName 528](#)
- [tibemsSubscriptionInfo_IsDurable 530](#)
- [tibemsSubscriptionInfo_IsShared 531](#)
- [tibemsTemporaryQueue 156](#)
- [tibemsTemporaryTopic 157](#)
- [tibemsTextMsg 124](#)
- [tibemsTextMsg_Create 125](#)
- [tibemsTextMsg_GetText 126](#)
- [tibemsTextMsg_SetText 127](#)
- [tibemsTopic_Create 159](#)
- [tibemsTopic_Destroy 160](#)
- [tibemsTopic_GetTopicName 161](#)
- [tibemsTopicInfo 532](#)
- [tibemsTopicInfo_Create 534](#)
- [tibemsTopicInfo_Destroy 535](#)
- [tibemsTopicInfo_GetActiveDurableCount 536](#)
- [tibemsTopicInfo_GetDurableCount 537](#)
- [tibemsTopicInfo_GetDurableSubscriptionCount 538](#)
- [tibemsTopicInfo_GetFlowControlMaxBytes 539](#)
- [tibemsTopicInfo_GetInboundStatistics 540](#)
- [tibemsTopicInfo_GetMaxBytes 541](#)
- [tibemsTopicInfo_GetMaxMsgs 542](#)
- [tibemsTopicInfo_GetName 543](#)
- [tibemsTopicInfo_GetOutboundStatistics 544](#)
- [tibemsTopicInfo_GetOverflowPolicy 545](#)
- [tibemsTopicInfo_GetPendingMessageCount 546](#)
- [tibemsTopicInfo_GetPendingMessageSize 547](#)
- [tibemsTopicInfo_GetPendingPersistentMessageCount 548](#)
- [tibemsTopicInfo_GetPendingPersistentMessageSize 549](#)
- [tibemsTopicInfo_GetSubscriberCount 550](#)
- [tibemsTopicInfo_GetSubscriptionCount 551](#)
- [tibemsUFOConnectionFactory_Create 288](#)
- [tibemsUFOConnectionFactory_CreateFromConnectio](#)

nFactory 289
 tibemsUFOConnectionFactory_RecoverConnection 2
 90
 tibemsXAConnection_Close 359
 tibemsXAConnection_Create 361
 tibemsXAConnection_CreateSSL 361
 tibemsXAConnection_CreateXASession 363
 tibemsXAConnection_Get 364
 tibemsXAConnection_GetXASession 365
 tibemsXAResource 367
 tibemsXAResource_Commit 368
 tibemsXAResource_End 369
 tibemsXAResource_Forget 370
 tibemsXAResource_GetRMID 371
 tibemsXAResource_GetTransactionTimeout 372
 tibemsXAResource_isSameRM 373
 tibemsXAResource_Prepare 374
 tibemsXAResource_Recover 375
 tibemsXAResource_Rollback 377
 tibemsXAResource_SetRMID 378
 tibemsXAResource_SetTransactionTimeout 379
 tibemsXAResource_Start 380
 tibemsXASession_Close 382
 tibemsXASession_GetSession 383
 tibemsXASession_GetXAResource 384
 tibx_MVSConsole_Create 573
 tibx_MVSConsole_Destroy 573
 tibx_MVSConsole_SetConsumer 572
 Topic 158
 tracing
 client 421
 translation, character encoding 4
 type conversion 20

U

Unicode 4

W

Write

BytesMessage 86
 StreamMessage 119

X

XA (not supported) 3

XID 366