



# **TIBCO Foresight® EDISIM®**

## Using XML

Version 6.21.0 | January 2025

# Contents

---

<b>Contents</b>	<b>2</b>
<b>Introduction</b>	<b>4</b>
Intended Audience	4
TIBCO Foresight Products that work with XML	4
Overview	5
Demos	6
Tutorial	7
Importing the Schema into EDISIM	7
Editing the Schema in TIBCO Foresight EDISIM	8
Validating data with TIBCO Foresight EDISIM Validator or TIBCO Foresight HIPAA Validator Desktop	12
Validating data with TIBCO Foresight Instream	13
Printing Guideline Documentation	13
<b>Using Standards Editor with Schemas and DTDs</b>	<b>15</b>
Importing a Schema or DTD	15
Opening a Schema or DTD	15
Top Pane	16
Bottom Pane	17
Details View Pane	17
Code Values Pane	20
Cross Reference Pane	20
Editing a Schema or DTD	20
SCHEMA Section	20
Values	21
Types	22
Localizing an Element	29

Reference Example .....	31
Business Rules .....	32
Business Rules that Do Not Apply to XML .....	40
Properties .....	40
Exporting a schema or DTD .....	42
SEF .....	43
<b>Printing DTDs and schemas .....</b>	<b>45</b>
Printing formatted guideline documentation .....	45
Printing a text report .....	47
<b>Using TIBCO Foresight EDISIM Validator with XML .....</b>	<b>49</b>
Before you validate XML .....	49
TIBCO Foresight programs that validate XML .....	49
Opening TIBCO Foresight EDISIM Validator .....	50
Validating XML data .....	50
Validating with TIBCO Foresight EDISIM Validator .....	50
Viewing the results .....	51
Creating an HTML report of XML validation results .....	52
<b>Splitting XML data .....</b>	<b>53</b>
XML splitting Demo .....	53
INI file for splitting XML data .....	54
Guideline and APF changes for splitting XML data .....	57
Docsplitter command line for splitting XML data .....	58
<b>TIBCO Documentation and Support Services .....</b>	<b>59</b>
<b>Legal-and-Third-Party-Notices .....</b>	<b>61</b>

# Introduction

---

## Intended Audience

This document is intended for users who wish to use TIBCO Foresight programs with XML data.

## TIBCO Foresight Products that work with XML



**Note:** TIBCO Foresight products can use XML on the Windows platforms only.

Program	What you can do	For more information, see ...
TIBCO Foresight® EDISIM® 6.7 or later (Standards Editor, Doc Builder, EDISIM® Validator)	Import, create, edit, print schemas and DTDs Validate XML data Create documentation	Foresight® EDISIM®'s Documentation directory: <ul style="list-style-type: none"> <li>• <i>TIBCO Foresight® EDISIM® Standards Editor User Guide</i></li> <li>• <i>TIBCO Foresight® EDISIM® Document Builder User Guide</i></li> <li>• <i>TIBCO Foresight® EDISIM® Validator User Guide</i></li> </ul>
TIBCO Foresight® HIPAA Validator® Desktop Desktop	Validate XML data	See in <i>TIBCO Foresight® EDISIM® Validator User Guide</i> Foresight® HIPAA Validator Desktop's Doc directory
TIBCO Foresight® Instream® (validate, Document Splitter)	Validate XML data Split into good	Foresight® Instream's Doc directory: <ul style="list-style-type: none"> <li>• <i>TIBCO Foresight® Instream® Validation</i></li> </ul>

Program	What you can do	For more information, see ...
	and bad data	<i>Technical Manual</i> <ul style="list-style-type: none"> <li><i>TIBCO Foresight® Instream® Document Splitter</i></li> </ul>

## Overview

You can:

- Import a schema or DTD into Foresight EDISIM Standards Editor, where you can edit it, including adding business rules.
- Validate XML data against the schema or DTD in Foresight EDISIM Validator, Foresight HIPAA Validator Desktop, or Foresight Instream.
- Split good from bad data with Document Splitter.

Since XML is not firmly based on standards the way EDI is, you will notice differences in how it is implemented in TIBCO Foresight products:

- EDI has guidelines, XML has schemas and DTDs.
- You must have Foresight EDISIM to use XML at TIBCO Foresight. It creates a TIBCO Foresight “guideline” (STD file) from the schema or DTD.
- Foresight EDISIM Standards Editor imports, edits, and exports schemas and DTDs. Any valid schema or DTD will work.
- In Foresight EDISIM, XML enumerated values are stored in application value lists rather than code lists.
- You can create a schema or DTD from scratch in Foresight EDISIM but it is currently much easier to create it another way and then import it.
- APF files are honored by XML validations.
- Foresight Instream validates and splits XML under Windows only.
- Foresight HIPAA Validator Desktop’s Library does not work with XML guidelines.
- Some XML resources

- <http://www.w3schools.com/xml/default.asp>  
XML tutorial
- <http://www.w3schools.com/schema/default.asp>  
Schema tutorial
- <http://www.w3.org/XML/Schema>  
Schema reference
- <http://www.xml.com/axml/testaxml.htm> .  
Annotated XML specification

## Demos

For a complete list of demos, see *TIBCO Foresight® Instream® Index of TIBCO Foresight Validation Demo Files*.

Program	Data file	Validate with ...
Foresight EDISIM	<b>XML_PO_f.xml</b>	<b>XML_PO_F</b>
	<b>XML_PO_g.xml</b>	<b>XML_PO_G</b>
	in EDISIM's <b>Samples</b> directory	(use EDISIM Validator)
Foresight HIPAA Validator Desktop	<b>XML_PO_f.xml</b> in HIPAA Validator Desktop's <b>DemoData</b> directory	<b>XML_PO_F</b>
Foresight HIPAA Validator Desktop	<b>XML_275.txt</b> in HIPAA Validator Desktop's <b>DemoData</b> directory	Start with 275_X151  Select XHL7 when it reaches the Bin segment
Program	Script	Output
Foresight Instream	<b>V_XML_PO</b> in the <b>Scripts</b> directory of	<b>XML_PO_f_Results.txt</b> or <b>XML_PO_Results.txt</b>

Program	Data file	Validate with ...
	Instream	in Instream's <b>Output</b> directory
Foresight Instream (HIPAA)	V_DS_XML_split_PO ValidationHighlighter_XML	Various files in the <b>Output</b> directory of Instream
Validation Highlighter	<b>ValidationHighlighter_XML</b>  in the <b>Scripts</b> directory of Instream	<b>XML_PO_f.html</b>  or <b>XML_PO.html</b>  in the <b>Output</b> directory of Instream
TIBCO Foresight® Translator	T_837I_4010_to_XML_and_back	<b>837Iclean_edi.txt</b>  <b>837Iclean_xml.xml</b>  In Translator's <b>Output</b> directory

## Tutorial


This tutorial will walk you through the most basic steps in editing a schema and validating XML data with it.

## Importing the Schema into EDISIM


1. Open EDISIM Standards Editor.
2. Choose **File > Import > Import XML Schema** and open it.
3. Go to EDISIM's **Samples** directory and choose **XML\_PO\_f.xsd**.
4. In the Import Standard box, use **XML\_PO\_f** and click **OK**.
5. Set up the version.

To do this, expand the SCHEMA line and notice that the root element is called PO.

In TIBCO Foresight XML guidelines, we use the name of the root element as the version.




Choose **File > Properties > General** tab and type PO for Version (it will initially have VRI, which is just a placeholder):



## Editing the Schema in TIBCO Foresight EDISIM

1. Expand the PO element and select the PO\_NUMBER element:





2. In the bottom pane, enter the Purchase Order Number for **Description** and change its **Minimum Occurrences** to **1** to indicate that it must be used.
3. Select **PO\_DATE** in the top pane. In the bottom pane, enter the Purchase Order Date for its Description, and add this **Length** and **Pattern**:

Type:	:string
Length:	8
Pattern:	[0-9]+

The pattern can be anything from the full set of regular expressions. This one means that it can contain only digits. See the Help menu for more examples.

4. Acceptable XML data values are called enumerations. These go in application values lists rather than in the code value pane.

Right-click on **BT\_COUNTRY** and choose **Application Values...**

Set up the application value list like this:

Current Location :  
Attached Value List : Country

Value List: Country

Description: Billing Address Country

Country

Value 0 of 1      1 reference(s)

US

Value

Buttons: Detach, Delete List, View Refs..., Attach, Close, Modify, Delete

Click **Attach**. This requires that the value for this element always be the US.

5. Under **ORDERS > Group**, set the Min to **1** in the top pane for

LINE\_ITEM

PROD\_QTY

PROD\_UNITS


UNIT\_PRICE

PROD\_NUM

ORDERS			0	>1
Group	Seq		1	1
LINE_ITEM	:string		1	1
PROD_QTY	:string		1	1
PROD_QTY2	:string		0	1
PROD_UNITS	:string		1	1
UNIT_PRICE	:string		1	1
PROD_NUM	:string		1	1
PROD_DESC	:string		0	1

This means that these are required.


6. We want to ensure that we get either a BT\_NAME or a ST\_NAME.



Set up a variable on the first one.


Right-click on **BT\_NAME**.

Capture the contents in a variable called BILLNAME:



Click **OK**


7. Right-click on the other element in the condition, ST\_NAME, and set up this variable:



Close and re-open the business rules dialog and click **NEW**:



Make these selections in the When to Run Rule area:



Select **DisplayErrorByNumber** in the What Rule to Run dropbox, and set this up to display an error message if the elements don't exist. (If the grid doesn't appear, click the Text button.)

What Rule to Run

DisplayErrorByNumber  ☐ Look-Ahead Rule

Text	Parameter Name	Parameter Value
	ErrorNumber	0
	Severity	0
	<b>MessageText</b>	"Must send BT_NAME or ST_NAME"

Click **OK** twice.


8. Save.

See *TIBCO Foresight® Instream® Business Rules* for more information.

## Validating data with TIBCO Foresight EDISIM Validator or TIBCO Foresight HIPAA Validator Desktop

You can now validate XML data using **XML\_PO\_f**.

1. Click the Foresight EDISIM Validator toolbar button within Standards Editor:



This opens the Foresight EDISIM Validator, which is installed in Foresight EDISIM's **Bin** directory.

(If you want to use Foresight HIPAA Validator Desktop instead, copy **XML\_PO\_f.std** from Foresight EDISIM's User Files\Public Guidelines directory to Foresight HIPAA Validator Desktop's Database directory and then open Desktop. You may have the Foresight HIPAA Validator Desktop toolbar button in Standards Editor.)

2. Choose **File > Open**, navigate to Foresight EDISIM's **Samples** directory, and select **XML\_PO\_f.xml**.
3. In the Select Standard box, choose our **XML guideline XML\_PO\_f**

4. When the validation completes, click on the blue errors at the top and look at the XML data in the bottom pane to see where the error occurred:

The USA is not valid. The application value list specified a value of the US.

PROD\_NUM appears twice and it is only allowed once

## Validating data with TIBCO Foresight Instream

Guideline **XML\_PO\_f** is already installed in the **Database** directory of Foresight Instream.

1. Move the existing installed directory from the Database directory of Foresight Instream, to use the guideline which you have created.
2. Copy the desired directory from EDISIM's **User Files\Public Guidelines**.
3. Go to the **Scripts** directory of Foresight Instream and view the contents of the **XML\_PO\_F** script.

Notice that the guideline parameter is


**-xgXML\_PO\_F**. The **-xg** indicates an XML guideline.

4. Close the script and execute it.
5. Go to the **Output** directory of Foresight Instream and view the contents of **XML\_PO\_f\_Results.txt**. Notice the error detailed in the **EDTL** record and the following EMSG record. These records are described in the *TIBCO Foresight® Instream® Validation Technical Manual* in the Doc directory of Foresight Instream.

## Printing Guideline Documentation

To create formatted documentation:

1. Open Foresight EDISIM Document Builder.
2. Choose **File > Open Standard**, choose **XML\_PO\_f**, and click **OK**.
3. Click **Print Preview**:



4. Click in the document to see the various levels of magnification and use the scroll bar to see the entire page.
5. Use the **Next Page** button to see other pages.
6. Click **Close** to close Print Preview.
7. Close Document Builder.

See [Printing DTDs and schemas](#).

# Using Standards Editor with Schemas and DTDs

---

## Importing a Schema or DTD

To import:

1. Open Standards Editor.
2. To import a schema, choose **File > Import > Import XML Schema** and open it. To import a DTD, choose **File > Import > Import XML DTD** and open it.
3. Navigate to the schema or DTD file and then choose **Open**.

During the import, the Standards Editor saves it as an STD file in EDISIM's **User Files\Public Guidelines** directory.

If the schema has to import or include elements, the referenced schemas will be imported as part of the master schema that contains them – if they are available to Foresight EDISIM.

You can then edit it or:

- Use Foresight EDISIM Validator to validate XML data.
- Use Foresight HIPAA Validator Desktop or Foresight Instream to validate XML data.
- Use Docsplitter to split an XML file into good and bad XML data files.

## Opening a Schema or DTD

If you have already imported your schema or DTD into EDISIM, you can open it just as you do any other guideline:

1. Open Standards Editor.
2. Choose **File > Open** and choose the **User Guidelines** tab.

- 3. Select the guideline and click **Open**.

# Top Pane

The Standards Editor top pane for an XML guideline looks similar to the top pane for an EDI guideline in that it has a Dictionary Section and a local SCHEMA or DTD section (like a Set or Message).

Column	Contents
Key	<div></div>
Group	<p>Available in group elements to define the order and requirement of elements it contains. SCHEMA or DTD order indicators that define the order in which the child elements can occur:</p> <p><b>Group</b> – Use only in the dictionary when defining a complex type. Defines this as a group of elements.</p> <p><b>All</b> - Child elements can appear in any order; each child element can occur 0 or 1 time.</p> <p><b>Choice</b> – Only one of the child elements can occur.</p> <p><b>Seq</b> - Child elements must appear in the sequence in which they are listed.</p>
Type	<p>The element’s type. If it is a built-in XML type, it is preceded with a colon.</p> <p>Examples:</p> <p>:date</p> <p>:integer</p> <p>If it is from one of the Types dictionaries, it does not have the colon. To change the type, click on it in the top pane, or use the bottom detail pane’s</p>



Column	Contents
	<b>Type</b> field or <b>Change Type</b> button.
Use	<i>This column is not used for XML guidelines.</i>
Min	<p>The minOccurs occurrence indicator: the element must occur at least this many times at this location in the data</p> <p>0 means the element is optional and can be left out of the data altogether.</p> <p>Any other number means it must be used at least that many times.</p>
Max	<p>The maxOccurs occurrence indicator: the element cannot appear any more than this number of times at this location in the data.</p> <p>&gt;1 means unbounded</p>
Indicators	<p>These abbreviations are visual cues to characteristics such as level notes, business rules, code values, and other items that do not always appear on the screen. For a list, search for “indicators” in <i>TIBCO Foresight® EDISIM® Standards Editor User Guide</i>.</p>

## Bottom Pane

### Details View Pane

The Details View pane can be floating or docked. By default, the pane appears docked at the bottom of the Standards Editor window. Single click the top bar of the pane and drag the pane to a new position. Double click the top bar of the pane to toggle between its most recent floating and docked positions. Size and position are saved when you exit the guideline.

Not all fields appear for every object in the top pane.

Field	Contents
Description	For your use.
ID	For your use.
Reference	<p>This element points to another item for its definition.</p> <p>To identify the item to which it points, click the <b>Change Type</b> button at the end of the Type field, choose <b>Reference</b>, and use the drop-down list.</p>
Type	<p>Same as Type column in the top pane. You can type in the type, or use the Change Type button at the end of the line.</p> <p>For more details, see <a href="#">Types</a>.</p>
Length	For data that must be a fixed length. An integer that specifies the exact number of digits or characters for the value.
Min Length	An integer that specifies the minimum length for the value.
Max Length	An integer greater than 0 that specifies the maximum length for the value.
Pattern	An optional regular expression to describe the sequence of characters that are acceptable in the value. Use this instead of the application value list regular expressions unless you need to use an application value list to enforce literal values or multiple patterns.
Abstract	<p>This element is abstract, meaning it cannot be used in the data. Instead, it should be replaced by a member of its substitution group.</p> <p>If this is a type, declaring it abstract requires the use of another type that is derived from it.</p>
Nullable	The element must be present in the data but can be empty.
Substitution Group	The current element may be substituted for the element entered here.

Field	Contents
Form	Optional. Determines whether this item has to be qualified with the namespace prefix. Default is the value of the elementFormDefault attribute of the schema element. Not available for elements directly under the schema element.
Block	Determines whether other elements can be substituted for this one.
Final	Only used on elements that have the schema element as a parent. Sets the default value of the final attribute.
Minimum Occurrences	Same as Min column in the top pane.
Maximum Occurrences	Same as the Max column in the top pane.
Default Value	<p>For optional elements, this value will be assumed if the element appears in the data without a value. If the element is not in the data at all, then the default value is ignored.</p> <p>Does not apply to the required elements, since the XML must contain a value.</p> <p>For attributes, this value applies even when the attribute is missing in the data.</p>
Fixed Value	If the XML data includes this element or attribute, it must contain this value. If the XML omits this element or attribute, this value will be assumed.
Edit Notes	Add level notes to this item. These are for your own use and can optionally print in Doc Builder.
Edit Rules	Add business rules to this item. Please see <i>TIBCO Foresight® Instream® Business Rules</i> .

## Code Values Pane

The Code Values pane is not used for XML. The XML equivalent, enumerations, should be put into an application values list and attached to the element.

## Cross Reference Pane

Cross-referencing is not available with XML data.

## Editing a Schema or DTD

After importing, you can edit it much like you would any EDI guideline.

## SCHEMA Section

The local SCHEMA or DTD section contains the global elements.

Each object has a Type field that identifies that object's base type if it has one. The basic w3c schema types all start with a colon: :string, :TOKEN, etc. You can define others under Dictionary Objects.

In the top pane, open the root element SCHEMA to see the elements and columns that describe them.

Key	Group	Type	Use	Min	Max
Dictionary Objects					
SCHEMA					
KAVER850g				1	1
Group	Seq			1	1
PURCHAGTNAME		:string		0	1
PO_NUMBER		:string		0	1
PO_DATE		:string		0	1
BT_NAME		:string		0	1

## Values

Enumerations define a list of acceptable values. The Code Values tab is not used with XML data since the data does not necessarily conform to EDI limitations for codes.

Instead, use any of these with simple elements or attributes:

- Application value lists to enforce specific values
- The Pattern field in the bottom pane to enforce a pattern
- Business rules like CodeLookup > FindUserCode

### Application Value Lists

This is one way to enforce literal values and patterns (regular expressions). This operates exactly like application values when using EDI data. Please see Application Value Lists in *TIBCO Foresight® EDISIM® Standards Editor User Guide*. They are best for values that do not change much.

### Pattern field

The bottom Detail pane contains a Pattern field where you can type in any regular expression to enforce a pattern. For example, to require that the value start with TC and be followed by digits, you would type this:

```
^TC[0-9] +
```

Please see Regular Expressions in *TIBCO Foresight® EDISIM® Standards Editor User Guide* for examples and details.


### Business rules to enforce values

Many extended business rules enforce values: List > ListCheck rules, CodeLookup > FindUserCode, etc.

#### Example

This rule checks an external list of values in a separate file, and returns an error message if the current value is not in the list:

What Rule to Run

FindUserCode  ☐ Look-Ahead Rule

**Text**

Parameter Name	Parameter Value
CodeTable	STcountry
CodeValue	Current_Element
notFoundRule	DisplayErrorByNumber
> ErrorNumber	0
> Severity	0
> <b>MessageText</b>	"The ST_COUNTRY value is not an approved country abbrevia
foundRule	

The list called **Stcountry** would be in a file designated by the UserTable entry in Foresight EDISIM's or Foresight Instream's \$Dir.ini. Please see *TIBCO Foresight® EDISIM® Business Rules* for details.

## Types

### Creating a Type

The Dictionary lets you create types in:

- The Simple Types Dictionary, which contains Simple Types and Global Attributes, and
- The Complex Types Dictionary, which contains Complex Types and Attribute Groups


You can create new types in the dictionary and then use them in the SCHEMA. For elements that are used more than once, this is a good alternative to simply adding them directly in the SCHEMA.

It also lets you edit the type in one place (the dictionary) and have it affect all places where it is used as a type in the SCHEMA.

#### Example - Simple Type

Create a simple type PHONE\_NUM in the dictionary and then use it twice in the schema.

1. Open **Dictionary Objects** at the top and click **Simple Types**.



2. Select **Edit > Create a new item ... > Schema Simple Type** and fill out the box like this:

 A screenshot of a 'Create Dictionary' dialog box. It has a blue title bar. Below the title bar, there are three input fields: 'ID:' with the value 'PHONE\_NUM', 'Description:' with the value '9-character phone number, digits only', and 'Purpose:' which is empty.

Close the box.

3. Click in the Type column for PHONE\_NUM and select :string from the dropdown list.

 A screenshot of a configuration window for a 'Schema Object'. The 'Selected Item' is 'Schema Object 'PHONE\_NUM'' with 'Type: :string (Simple Type)'. Below this, there are two radio buttons for 'Type': 'None' and 'Simple', with 'Simple' selected. To the right of these is a dropdown list showing various data types: ':string', ':positiveInteger', ':QName', ':short', ':string' (highlighted), ':time', ':token', ':unsignedByte', and ':unsignedInt'. At the bottom, there are two radio buttons for 'Children': 'Keep Children' and 'Discard Children', with 'Discard Children' selected.

4. Click on another line in the top pane, and then click again on PHONE\_NUM to refresh the bottom pane.
5. Fill out the bottom pane like this:

Description: 9-character phone number, digits only

ID:

Reference: ☐

Type: :string

Length: 9 Min Length: 9 Max Length: 9

Pattern: ^([0-9])+

6. Return to the SCHEMA and click BT\_ADDR1:
7. Choose **Edit > Add item > Schema Element** and fill out the box like this.  
PHONE\_NUM will be at the bottom of the drop-down list after the built-in types.

**Adding Schema Element**

Name: BT\_PHONE\_NUM

Type

☒ Simple ☐ Complex ☐ Reference

PHONE\_NUM

Where

☒ Before ☐ After ☐ Within

Selected Item: Element 'BT\_ADDR1'

There is no colon at the beginning of a type that you create.

Finish adding the element.

8. Add ST\_PHONE\_NUM after BT\_PHONE\_NUM


ST_NAME	:string
BT_PHONE_NUM	PHONE_NUM
ST_PHONE_NUM	PHONE_NUM
BT_ADDR1	ST_ADDR12

### Example - Complex Type

Create a complex type CONTACT in the dictionary and then use it in the schema.




1. Under **Dictionary Objects**, click **Simple Types** and create this type in the Simple Types dictionary:  
NAME Type :string Min 3 Max 20
2. Under Dictionary Objects, click **Complex Types**.
3. Select **Edit > Create a new item ... > Schema Complex Type** and fill out the box like this:



The 'Create Dictionary' dialog box has a blue title bar. It contains three input fields: 'ID' with the text 'CONTACT', 'Description' with the text 'Contact person name and phone', and 'Purpose' which is empty.

Close the box.

4. Save.
5. With CONTACT selected, choose **Edit > Add item ... > Schema Element** and add this simple element:



The 'Adding Schema Element' dialog box has a blue title bar. It contains several sections: 'Name' with the text 'ContactName'; 'Type' with three radio buttons ('Simple' is selected), a dropdown menu showing 'NAME', and 'Where' with three radio buttons ('Within' is selected). There is also a 'Selected Item' field showing 'Schema Object 'CONTACT''.

6. Highlight ContactName and add this after:

**Adding Schema Element**

Name:

Type

☒ Simple ☐ Complex ☐ Reference

Where

☐ Before ☒ After ☐ Within

Selected Item:

7. Save.

Now use this type in the SCHEMA:

1. Click ST\_COUNTRY in the SCHEMA and choose **Edit > Add item > Schema Element**.
2. Fill out the box like this:

**Adding Schema Element**

Name:

Type

☐ Simple ☒ Complex ☐ Reference

Where

☐ Before ☒ After ☐ Within

Selected Item:

3. Save.

4. Expand CONTACT\_PERSON in the SCHEMA to see this:




Notice the Italic *ContactName* and *ContactPhone*, indicating that these are being supplied from the Complex Types dictionary.

You can use this type as often as you'd like. It is the same as having a local complex group that contains NAME and PHONE, only you can maintain it centrally from the dictionary.


## Changing an Element's Type

You can change an element's type by:


- Clicking (or double-clicking, depending on your preferences) on its type in the top pane:



- Or, by clicking the Change type button at the end of the Type field in the Detail pane:



- This displays the Change Element Type dialog:



Where:


<b>Selected Item</b>	Name and type of the current element. Parentheses at the end of the type line contain one of these:	
	<b>Complex</b>	Selected type has child elements.
	<b>ComplexContent</b>	Selected type contains data and has child elements.
	<b>Simple Type</b>	Selected type contains data.
<b>Type</b>	Select a type:	
	<b>None</b>	Deletes the type from the element.
	<b>Simple</b>	Drop-down list offers all built-in simple types or those from your Simple Types dictionary.

	<b>Complex</b>	Drop-down list offers all complex types from your Complex Types dictionary.
	<b>Reference</b>	Drop-down list offers all types defined elsewhere in the document
<b>Keep children</b>	Save the current child elements and add the one(s) from the selected type. Available if you have child elements that are local (See <a href="#">Localizing an element.</a> )	
<b>Discard children</b>	Delete the current child elements and add the one(s) from the selected type. Available if you have child elements that are local (See <a href="#">Localizing an element.</a> )	

## Localizing an Element

If an element uses a complex type from the dictionary, its children will display in *Italic* in the top pane. In this example, the ST\_ADDR1 complex element in the SCHEMA has a type of ST\_ADDR12 – which you can see in the Complex Types dictionary.

STR\_ADDR1 is simply pointing to the dictionary element for its subordinate structure.




To remind you that it refers to a dictionary type, the Standards Editor displays the subordinates *StreetAddr1* and *StreetAddr2* in Italic font.

You cannot change anything in ST\_ADDR1 in the schema. Changes must be made in the dictionary, and they then will be reflected in all schema places where that element type is used.

If you want to make changes that are local to just one place in the schema, you can “localize” the complex element:

1. Right-click on the complex element that is using the dictionary type.
2. Choose Localize.



The subordinates are no longer in Italic and the type is in parentheses – indicating that it was based on the type shown, but is no longer attached to it.




You can now edit the element in the SCHEMA. It will not affect any other location. If there are other dictionary types within this element, they remain attached to their complex types unless you localize them.

To re-attach a localized element to its dictionary element, right-click on it and choose


Localize.

## Reference Example

In this example, PO\_DATE under KAVR850g has Reference selected in the detail pane so that it uses the definition of DATES under SCHEMA:




PO\_DATE's Type is set up like this:




## Business Rules

In the business rules dialog, you can define variables with XML:




A dialog box titled "Local Variable" with a label "Element Contents Assigned to Variable:" followed by a text input field.

You can also use all of these buttons with XML:



Three buttons labeled "New...", "Edit...", and "Delete" arranged horizontally.

With XML, you can use these features of the business rules dialog:



A screenshot of the "Condition and Rule Definition" dialog box. It has two main sections: "When to Run Rule" and "What Rule to Run".

**When to Run Rule:** Includes radio buttons for "Always" and "Conditionally" (selected). Below is a table with columns "Local Variable", "Operator", and "Constant".

	Local Variable	Operator	Constant
And	when BILLNAME	DOESN'T EXIST	
	when SHIPNAME	DOESN'T EXIST	

**What Rule to Run:** Includes a dropdown menu with "\* Call External Routine" selected, a function icon, and fields for "Server:", "Function:", and "Parameters:".

### External routines you can use with XML

Rule	Use with XML?
Reserved variables	
Current_Date	✓
Current_Delim	
Current_Element	✓
Current_ErrCount	✓
Current_LoopCount	



External routines you can use with XML	
Rule	Use with XML?
Current_LoopKey	
Current_Row and Next_Row	✓
Current_Time	✓
GLOBAL_FILENAME	
GLOBAL_FILEPATHNAME	
Using reserved variables in a message	✓
BusinessRules.CCI	
CCIInit	
CCICollect	
CCIANalyze	
BusinessRules.CodeLookup	
FindCode	✓
FindCodeWithDate	✓
FindUserCode	✓
FindUserCodeWithDate	✓
ValidateZipState	✓
BusinessRules.CustRec	

External routines you can use with XML	
Rule	Use with XML?
DefineCustomRec	✓
OutputCustomRec	✓
RemoveCustomRecord	✓
BusinessRules.DateTime	
CheckDateInRange	✓
CompareDate	✓
DateCalc	✓
GetGMTDateTime	✓
ValidateDateTimeUN and ValidateDateTimeX12	
BusinessRules.DBServer	
DBExecute	✓
DBQuery	✓
InvokeWebService	✓
BusinessRules.Exits	
ClearExits	
KeepOrder	
SetCompositePreExit	
SetElementPostExit	

External routines you can use with XML	
Rule	Use with XML?
SetLoopPostExit	
SetLoopPostInstanceExit	
SetSegmentPreExit	
UserExitWithoutWait	
UserExitWithWait	
BusinessRules.List	
ClearList	✓
InList	✓
ListCheck	✓
ListContig	✓
ListCount	✓
ListGetVar	✓
ListInsert	✓
ListMinMax	✓
BusinessRules.Looping	
ForEach	✓
Next	✓
ExitLoop	✓

External routines you can use with XML	
Rule	Use with XML?
BusinessRules.ODBC	
Setting up your ODBC Connection String	✓
DBOpen	✓
DBCclose	✓
DBQuery	✓
DBExecute	✓
BusinessRules.Run	
RunAlways	
RunNoData	
BusinessRules.Substitute	
DeleteSegment	
InsertSegment	
MakeKey	
Substitute	
SubstituteFind	
SubstituteReplace	
BusinessRules.Utilities	
AppendString	✓

External routines you can use with XML	
Rule	Use with XML?
BuildString	✓
ChangeCase	✓
ChangeElmAttribute	
CheckFormat	✓
CreateFSUID	✓
DisplayErrorByNumber	✓
FindString	✓
GetToken	✓
Identify	✓
IdentifierLookup	
InsertIdentifier	
Match	✓
MatchApplList	
Normalize	✓
Numbers	✓
OracleLookup and OracleLookupWithDate	✓
OutputCTX	
ReplaceChars	✓

External routines you can use with XML	
Rule	Use with XML?
ReplaceString	✓
SetCheckCTT and SetCheckCTTCount	
SetIdentifier	
SubString	✓
Trim	✓
TrimWhitespace	✓
BusinessRules.Variable	
SetLocalVariable	
SetVar	✓
AddVar	✓
Divide	✓
DumpVars	✓
Balance	✓
CompareNstring	✓
CompareNumeric	✓
CompareString and CompareStringNoCase	✓
Clear	✓
ClearLocalVariable	✓

External routines you can use with XML	
Rule	Use with XML?
FileTable Rules	✓
GetInfo	✓
GetLength	✓
GetValueFromSegment	
IsAlpha	✓
IsAlphaNum	✓
IsNum	✓
SaveCurrentSegment	
CheckCTT	
CheckDigit	
X12 234-235 CheckDigit	
EDIFACT 3039-3055 CheckDigit	
Other CheckDigit options	
User Defined check digit	
DateTime	✓
FSVExit.DisplayMessage	
ProductUtilities	

## Business Rules that Do Not Apply to XML

Additionally, these do not work with XML files:

\*Set Usage/Status

\*Use Application Value List

\*Use Code Set

ICD Business Rules (HIPAA Only)

Lookahead Business Rules

## Properties

To set the properties for an XML guideline, use one of these:

- Choose **File > Properties > XML Schema**
- Use the properties toolbar button:
- Use the **Properties** button on the Save dialog

The XML Schema tab looks like this:



**Guideline Properties**

General XML Schema Level Notes

Target Namespace:

Schema ID:

Schema Version:

Element Form Default:  Attribute Form Default:

Block Default:  Final Default:

Other Namespaces

msdata=urn:schemas-microsoft-com:xml-msdata  
xmlns=  
xs=http://www.w3.org/2001/XMLSchema

OK Cancel


Field	Contents
Target Namespace	Namespace for this schema. For your own use. TIBCO Foresight products do not use this field.
Schema ID	ID for this schema. For your own use. TIBCO Foresight products do not use this field.
Schema Version	Version for your own use. TIBCO Foresight products do not use this field.
Element Form Default	<p>Determines the default Form setting for elements in your schema: must they be qualified by the target namespace?</p> <p>If set to Default in the Properties dialog, then the default setting for XML will be used.</p>
Attribute Form	Determines the default Form setting for attributes in your schema: they

Field	Contents
Default	must be qualified by the target namespace? If set to Default here, then the default setting for XML will be used.
Block Default	Determines the default Block setting for your schema: elements with which derivations should be blocked from replacing this element. If set to Default here, then the default setting for XML will be used.
Final Default	Determines the default Final setting for your schema: how can this element be derived? If set to Default here, then the default setting for XML will be used.
Other Namespaces	Other namespaces used to qualify elements in this schema

## Exporting a schema or DTD

To export the current schema to an .xsd file:

**i** **Note:** For HL7 document, if the **Full Enveloping** option is checked, then the exported XML schema contains outer HL7 envelope segments.



## Procedure

1. Save the changes.
2. Choose **File > Export > Export Current Guideline > To Schema or To DTD**.
3. Choose the filename and location.

## SEF

EDISIM stores guidelines in a public domain format called SEF in two ways:

- You can export an XML guideline in SEF format by using **Export < Export Current Guideline < To SEF**.
- When you import a schema or DTD into EDISIM, it is stored as a file with the extension STD in EDISIM's **User Files\Public Guidelines** directory. This file is also in SEF format.

The SEF format that captures schema information has expanded from its earlier formats. If you use EDISIM's SEF files in other applications, please contact TIBCO Foresight technical support.

# Printing DTDs and schemas

## Printing formatted guideline documentation

EDISIM Document Builder will print formatted guideline documentation for XML schemas and DTDs that have been imported into Standards Editor.

Because of the nature of XML, the Doc Builder output has been adjusted and does not match the Doc Builder EDI output exactly.

Doc Builder example page 1

XML Schema Layout for XML_PO_F				
Page No.	Name	Type	Usage	
2	PO	Sequential	>>>	
2	PURCHAGTNAME	:string		
2	PO_NUMBER	:string		
2	PO_DATE	:string		
2	BT_NAME	:string		
2	ST_NAME	:string		

SCHEMA				
[-] PQ			1	1
[-] Group	Seq		1	1
[-] PURCHAGTNAME	:string		0	1
[-] PO_NUMBER	:string		0	2 L1
[-] PO_DATE	:string		0	1
[-] BT_NAME	:string		0	1 BV
[-] ST_NAME	:string		0	1 BV, BZ

Doc Builder example page 2

Element: **PO**  
Occurrences: 1

Attribute and Sub-Element Summary

Name	Description	Type	Usage
<b>Child Elements and Groups</b>			
<b>PURCHAGTNAME</b>	Purchase Order name Occurrences: None to 1, XML ID: PO_KC	:string	Optional
<b>PO_NUMBER</b>	Occurrences: None to 2, Length: / 9, Pattern: PO[1-9]+ This value must start with PO followed by up to 7 digits	:string	Optional

Key

Group	Type	Min	Max	Indicators
PO	Group	1	1	
PURCHAGTNAME	:string	0	1	
PO_NUMBER	:string	0	2	L1
PO_DATE				
BT_NAME				

PO\_NUMBER Element

Pattern: PO[1-9]+

Abstract ☐ Nilable: ☐

Substitution Group:

Form: Default Block: D

Minimum Occurrences: 0

Level Notes

Element PO\_NUMBER, SCHEMA

Level Notes: Level 1 note

This value must start with PO followed by up to 7 digits

Many Doc Builder profile settings apply to XML guidelines.


Profile Tab	Setting
Formatting	All work with XML
Fonts	All work with XML
Usage Indicators	Most do not apply to XML Element indicator for Must Use affects the “segment table”
Shading	Shading works for Level Notes

Profile Tab	Setting
Transaction Items	Does not apply to XML
Segment Items	Does not apply to XML
Element Items	Does not apply to XML
Segment Usage Notes	Does not apply to XML
Element Usage Notes	Does not apply to XML
Global Items	Level Notes

## Printing a text report

You can print your current XML guideline in tabular or CSV format right from the Standards Editor.

1. Open the schema.
2. Choose **File > Print**.
3. Choose the options that you want:
  - Indentation prints an indented tabular report.
  - Comma Separated Fields creates a CSV file suitable for importing into a spreadsheet or other application. If this is not selected, you will get a tabular text report.
  - The other selections determine the content of the output



4. After clicking OK, you can use the Save As... and Print buttons at the bottom right.



# Using TIBCO Foresight EDISIM Validator with XML

---

## Before you validate XML

For XML validation, you must first import the corresponding schema into Foresight EDISIM so that it will be put into the Foresight EDISIM database in the form of an STD file and become available during validation.

## TIBCO Foresight programs that validate XML




These TIBCO Foresight products validate XML:

<b>Foresight EDISIM Validator</b>	This program is the most convenient way to validate XML since it is installed as part of Foresight EDISIM 6.0 and later. It will validate your XML data without copying files anywhere.
<b>Foresight HIPAA Validator Desktop</b>	Copy the XML guideline's <b>STD</b> file from Foresight EDISIM's <b>User Files\Public Guidelines</b> directory to Foresight HIPAA Validator Desktop's <b>Database</b> directory. You can then use the Foresight HIPAA Validator Desktop and validate XML against that guideline.
<b>Foresight Instream</b>	Copy the XML guideline's <b>STD</b> file from Foresight EDISIM's <b>User Files\Public Guidelines</b> directory to Foresight Instream's <b>Database</b> directory. You can then use Foresight Instream to validate XML against that guideline.

The rest of this section describes how to validate with Foresight EDISIM Validator.

# Opening TIBCO Foresight EDISIM Validator

To open Foresight EDISIM Validator, use one of these methods:

- From the Standards Editor, click the toolbar icon for Foresight EDISIM Validator:  or  or  (depending on the Foresight EDISIM version).
- From the Start menu, select **Programs > FORESIGHT > EDISIM > Validator**.
- From Windows Explorer, go to Foresight EDISIM's **Bin** directory and double-click on **Validtr.exe**.

## Validating XML data

You can validate XML with:

- Foresight EDISIM validator (data correction not available for XML)
- Foresight HIPAA Validator Desktop (data correction not available for XML)
- Foresight Instream (and optionally use trading partner automation - see *TIBCO Foresight® Instream® Trading Partner Automation*.)

## Validating with TIBCO Foresight EDISIM Validator

1. Open Foresight EDISIM Validator.
2. Open an XML file:
  - Choose **File > Open**.
  - Navigate to the file. You can see some XML files in Foresight EDISIM's Samples directory.

As an XML example, you can choose **XML\_PO\_f.xml**.


3. Choose the XML guideline that defines how the data should look.  
If you are validating XML\_PO\_f, choose XML\_PO\_F.
4. Click OK.

- Click OK when the analysis is complete.

You can also use trading partner automation to select guideline and profile for XML validations. See *TIBCO Foresight® Instream® Trading Partner Automation*.

## Viewing the results

The top pane contains diagnostic messages and the bottom pane contains the EDI segments or XML elements.



- Click on the first line in the top pane.  
The corresponding line in the data is highlighted in the bottom pane.
- Use your cursor keys to move down line by line in the top pane, noticing what happens in the bottom pane.
- When you click on a blue line (an error), the bottom pane highlights the location of the error.

4. Continue scrolling down and looking at each message

## Creating an HTML report of XML validation results

You can create an HTML report from your XML validation. Please see *TIBCO Foresight® Instream® Validation Highlighter*.

# Splitting XML data

XML splitting is available on Windows platforms only.

Docsplitter on Windows can split XML at any complex element that repeats.

For example: you can split at ORDERS or TOTALLINES, which are complex elements and have a Max of greater than 1.

Key	Group	Type	Use	M.	Max
SCHEMA					
PO				1	1
Group	Seq			1	1
PURCHAGTNAME		:string		0	1
PO_NUMBER		:string		0	1
PO_DATE		:string		0	1
BT_NAME		:string		0	1
ST_NAME		:string		0	1
BT_ADDR1		:string		0	1
ST_ADDR1		:string		0	1
BT_ADDR2		:string		0	1
ST_ADDR2		:string		0	1
BT_CITY		:string		0	1
ST_CITY		:string		0	1
BT_STATE		:string		0	1
ST_STATE		:string		0	1
BT_COUNTRY		:string		0	1
BT_ZIP		:string		0	1
ST_ZIP		:string		0	1
ST_COUNTRY		:string		0	1
REQSHIP		:string		0	1
ORDERS				0	>1
Group	Seq			1	1
LINE_ITEM		:string		1	1
PROD_QTY		:string		1	1
PROD_QTY2		:string		0	1
PROD_UNITS		:string		1	1
UNIT_PRICE		:string		1	1
PROD_NUM		:string		1	1
PROD_DESC		:string		0	1
TOTALLINES				0	>1
Group	Seq			1	1
TOTAL		:string		0	1
TOTALAMOUNT		:string		0	1
NewDataSet				1	1

## XML splitting Demo

**V\_DS\_XML\_split\_PO** in the **Scripts** directory of Foresight Instream.

# INI file for splitting XML data

XML splitting is controlled by the Docsplitter INI file.

## [Split Point] section

It looks like this:

```
[Split Point]
Xml=PO|PO/ORDERS
```

The format is:

```
[Split Point]
Xml=ns:rootelem|PathToSplit
```

where

[Split Point]	Literal Text
XML=	Literal Text
<i>ns:rootelem PathToSplit</i>	The prefix ns: with the root element followed by a vertical bar and then the path from the root element to the split point, with each element separated by a slash

**i Note:** The prefix ns: is optional and is used only when it is set up in the schema.

## Example 1

The root element is PO and the split point is at the ORDERS complex element:

Key	Group	Type	
SCHEMA			
PO			
Group	Seq		
PURCHAGTNAME		:string	
PO_NUMBER		:string	
PO_DATE		:string	
BT_NAME		:string	
ST_NAME		:string	
BT_ADDR1		:string	
ST_ADDR1		:string	
BT_ADDR2		:string	
ST_ADDR2		:string	
BT_CITY		:string	
ST_CITY		:string	
BT_STATE		:string	
ST_STATE		:string	
BT_COUNTRY		:string	
BT_ZIP		:string	
ST_ZIP		:string	
ST_COUNTRY		:string	
REQSHIP		:string	
ORDERS			
Group	Seq		
LINE_ITEM		:string	
PROD_QTY		:string	
PROD_QTY2		:string	
PROD_UNITS		:string	
UNIT_PRICE		:string	
PROD_NUM		:string	
PROD_DESC		:string	

The INI file will contain this:

```
[Split Point]
```

```
Xml=PO|PO/ORDERS
```

This INI file will cause the XML data to split at the bold lines if an error is encountered within an ORDERS element:

```
<?xml version="1.0" standalone="yes"?>
<PO>
  <PURCHAGTNAME>ARTHUR JONES</PURCHAGTNAME>
  <PO_NUMBER>76766541</PO_NUMBER>
  <PO_DATE>19970905</PO_DATE>
  <REQSHIP>19971201</REQSHIP>
  <ORDERS>
    <LINE_ITEM>1</LINE_ITEM>
    <PROD_QTY>1000</PROD_QTY>
    <PROD_UNITS>EA</PROD_UNITS>
    <UNIT_PRICE>0.04</UNIT_PRICE>
```

```

<PROD_NUM>2837645985</PROD_NUM>
<PROD_DESC>BOOT EYELETS</PROD_DESC>
</ORDERS>
<ORDERS>
<LINE_ITEM>2</LINE_ITEM>
<PROD_QTY>40</PROD_QTY>
<PROD_UNITS>CA</PROD_UNITS>
<UNIT_PRICE>54.00</UNIT_PRICE>
<PROD_NUM>SAL3337465</PROD_NUM>
<PROD_DESC>SOLE RESIN</PROD_DESC>
</ORDERS>

```

## Example 2

The path is complex element LINEITEM within ORDERS:

Group	Seq	Type	Value	Count
ORDERS	0	>1		
LINE_ITEM	1	1		
PROD_QTY	1	1		
PROD_QTY2	0	1		
PROD_UNITS	1	1		
UNIT_PRICE	1	1		
PROD_NUM	1	1		
PROD_DESC	0	1		

The INI file will contain this:

```

[Split Point]
Xml=PO|PO/ORDERS/LINEITEM

```

## [Summary Point] section

You can include an optional [Summary Point] section to display a count of the number of split points in the file.

The format is:

## [Summary Point]

Xml="element"

Where:



<b>[Summary Point]</b>	Literal text.
<b>Xml=</b>	Literal text.
<b>"&lt;element&gt;"</b>	An element to hold the count.

### Example 3

This INI file says the split point is the ORDERS element and the TOTAL element should contain a count of the ORDERS elements in the file. The TOTAL element here is reporting 10 ORDERS in the file:

INI file	Data
<pre> [Split Point] Xml=PO PO/ORDERS  [Summary Point] XML="&lt;TOTAL&gt;" </pre>	<pre> . . . &lt;PROD_NUM&gt;4335625486&lt;/PROD_NUM&gt; &lt;PROD_DESC&gt;PLASTIC STAKES&lt;/PROD_DESC&gt; &lt;/ORDERS&gt; &lt;ORDERS&gt;   &lt;LINE_ITEM&gt;10&lt;/LINE_ITEM&gt;   &lt;PROD_QTY&gt;5000&lt;/PROD_QTY&gt;   &lt;PROD_UNITS&gt;EACH&lt;/PROD_UNITS&gt;   &lt;UNIT_PRICE&gt;0.29&lt;/UNIT_PRICE&gt;   &lt;PROD_NUM&gt;5548876542&lt;/PROD_NUM&gt;   &lt;PROD_DESC&gt;KAVER INSIGNIA PATCHES&lt;/PROD_DESC&gt; &lt;/ORDERS&gt; - &lt;TOTALLINES&gt;   &lt;TOTAL&gt;10&lt;/TOTAL&gt;   &lt;TOTALAMOUNT&gt;186&lt;/TOTALAMOUNT&gt; &lt;/TOTALLINES&gt; &lt;/PO&gt; </pre>

## Guideline and APF changes for splitting XML data

No changes are needed to the XML guideline or the validation profile (APF).

# Docsplitter command line for splitting XML data

The command line is similar to the Docsplitter command line for splitting EDI data, with these considerations:

- 
- i     The i parameter is required and must point to a validation detail results file that was created by validating with an XML guideline.
- 
- s     The s parameter is required and must point to a Docsplitter INI file that contains, as a minimum, a [Split Point] section with an XML line. See [INI file for splitting XML](#).
- 

For an example, please see V\_DS\_XML\_split\_PO in the **Scripts** directory of Foresight Instream.

For details about the Docsplitter command line, see *TIBCO Foresight® Instream® Document Splitter*.

# TIBCO Documentation and Support Services

---

For information about this product, you can read the documentation, contact Support, and join TIBCO Community.

## How to Access TIBCO Documentation

Documentation for TIBCO products is available on the [Product Documentation website](#), mainly in HTML and PDF formats.

The [Product Documentation website](#) is updated frequently and is more current than any other documentation included with the product.

## Product-Specific Documentation

The documentation for this product is available on the [TIBCO Foresight® EDISIM® Documentation](#) page.

## How to Contact Support for TIBCO Products

You can contact the Support team in the following ways:

- To access the Support Knowledge Base and getting personalized content about products you are interested in, visit our [product Support website](#).
- To create a Support case, you must have a valid maintenance or support contract with a Cloud Software Group entity. You also need a username and password to log in to the [product Support website](#). If you do not have a username, you can request one by clicking **Register** on the website.

## How to Join TIBCO Community

TIBCO Community is the official channel for TIBCO customers, partners, and employee subject matter experts to share and access their collective experience. TIBCO Community offers access to Q&A forums, product wikis, and best practices. It also offers access to extensions, adapters, solution accelerators, and tools that extend and enable customers to gain full value from TIBCO products. In addition, users can submit and vote on feature

requests from within the [TIBCO Ideas Portal](#). For a free registration, go to [TIBCO Community](#).

# Legal-and-Third-Party-Notices

---

SOME CLOUD SOFTWARE GROUP, INC. (“CLOUD SG”) SOFTWARE AND CLOUD SERVICES EMBED, BUNDLE, OR OTHERWISE INCLUDE OTHER SOFTWARE, INCLUDING OTHER CLOUD SG SOFTWARE (COLLECTIVELY, “INCLUDED SOFTWARE”). USE OF INCLUDED SOFTWARE IS SOLELY TO ENABLE THE FUNCTIONALITY (OR PROVIDE LIMITED ADD-ON FUNCTIONALITY) OF THE LICENSED CLOUD SG SOFTWARE AND/OR CLOUD SERVICES. THE INCLUDED SOFTWARE IS NOT LICENSED TO BE USED OR ACCESSED BY ANY OTHER CLOUD SG SOFTWARE AND/OR CLOUD SERVICES OR FOR ANY OTHER PURPOSE.

USE OF CLOUD SG SOFTWARE AND CLOUD SERVICES IS SUBJECT TO THE TERMS AND CONDITIONS OF AN AGREEMENT FOUND IN EITHER A SEPARATELY EXECUTED AGREEMENT, OR, IF THERE IS NO SUCH SEPARATE AGREEMENT, THE CLICKWRAP END USER AGREEMENT WHICH IS DISPLAYED WHEN ACCESSING, DOWNLOADING, OR INSTALLING THE SOFTWARE OR CLOUD SERVICES (AND WHICH IS DUPLICATED IN THE LICENSE FILE) OR IF THERE IS NO SUCH LICENSE AGREEMENT OR CLICKWRAP END USER AGREEMENT, THE LICENSE(S) LOCATED IN THE “LICENSE” FILE(S) OF THE SOFTWARE. USE OF THIS DOCUMENT IS SUBJECT TO THOSE SAME TERMS AND CONDITIONS, AND YOUR USE HEREOF SHALL CONSTITUTE ACCEPTANCE OF AND AN AGREEMENT TO BE BOUND BY THE SAME.

This document is subject to U.S. and international copyright laws and treaties. No part of this document may be reproduced in any form without the written authorization of Cloud Software Group, Inc.

TIBCO, the TIBCO logo, the TIBCO O logo, and EDISIM are either registered trademarks or trademarks of Cloud Software Group, Inc. in the United States and/or other countries.

All other product and company names and marks mentioned in this document are the property of their respective owners and are mentioned for identification purposes only. You acknowledge that all rights to these third party marks are the exclusive property of their respective owners. Please refer to Cloud SG’s Third Party Trademark Notices (<https://www.cloud.com/legal>) for more information.

This document includes fonts that are licensed under the SIL Open Font License, Version 1.1, which is available at: <https://scripts.sil.org/OFL>

Copyright (c) Paul D. Hunt, with Reserved Font Name Source Sans Pro and Source Code Pro.

Cloud SG software may be available on multiple operating systems. However, not all operating system platforms for a specific software version are released at the same time. See the “readme” file for the availability of a specific version of Cloud SG software on a specific operating system platform.

THIS DOCUMENT IS PROVIDED “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENT COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THIS DOCUMENT. CLOUD SG MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S), THE PROGRAM(S), AND/OR THE SERVICES DESCRIBED IN THIS DOCUMENT AT ANY TIME WITHOUT NOTICE.

THE CONTENTS OF THIS DOCUMENT MAY BE MODIFIED AND/OR QUALIFIED, DIRECTLY OR INDIRECTLY, BY OTHER DOCUMENTATION WHICH ACCOMPANIES THIS SOFTWARE, INCLUDING BUT NOT LIMITED TO ANY RELEASE NOTES AND "README" FILES.

This and other products of Cloud SG may be covered by registered patents. For details, please refer to the Virtual Patent Marking document located at <https://www.cloud.com/legal>.

Copyright © 1991-2025. Cloud Software Group, Inc. All Rights Reserved.