



TIBCO iProcess® Workspace (Windows)

Installation

Version 11.10.0 | May 2025

Contents

Contents	2
Installation Overview	3
Installation Modes	3
Installation Types	3
Installation Requirements	5
Supported Platforms	5
Basic System Requirements	5
POSIX Threads (pthreads)	6
Installing TIBCO iProcess Workspace (Windows)	9
Installation in GUI Mode	9
Installation in Silent Mode	18
Creating a Response File	18
Performing a Silent Installation	19
Uninstalling TIBCO iProcess Workspace (Windows)	22
Pre-removal Considerations	22
Uninstalling	22
Post-installation Tasks	24
Configuring Data of Remote Procedure Calls (RPC) Servers	24
Troubleshooting	26
The Installer Encounters an Error Trying to Locate pthread.dll	26
TIBCO Documentation and Support Services	28
Legal and Third-Party Notices	30

Installation Overview

This section provides an overview of the TIBCO iProcess Workspace (Windows) installer.

- [Installation Modes](#)
- [Installation Types](#)

Installation Modes

The installer can run in the following modes on Microsoft Windows platforms.

- [GUI Mode](#)
- [Silent Mode](#)

GUI Mode

In GUI mode, the installer presents panels that allow you to make choices about product selection, product location, and so on.

To invoke the installer in GUI mode, double-click the executable.

For detailed information, see [Installation in GUI Mode](#).

Silent Mode

In Silent mode, the installer uses a response file that was saved during an earlier installation. Silent mode installs without prompting you for information.

For detailed information, see [Installation in Silent Mode](#).

Installation Types

The following four installation types are available for TIBCO iProcess Workspace (Windows) installation.

- **Administrator** The Administrator installation type installs TIBCO iProcess Workspace (Windows) and TIBCO iProcess Administrator.
- **Custom** The Custom installation type is recommended for advanced users. Choosing this installation type allows you to specify which components to install, such as TIBCO iProcess Workspace (Windows), TIBCO iProcess Modeler, iProcess Workspace Plug-ins, TIBCO iProcess Administrator, and so on. This option also enables you to uninstall existing installed components.
- **Modeler** The Modeler installation type installs TIBCO iProcess Workspace (Windows), TIBCO iProcess Administrator, and TIBCO iProcess Modeler.
- **User** The User installation type installs TIBCO iProcess Workspace (Windows) only.

Installation Requirements

This section describes the installation requirements for this product.

- [Supported Platforms](#)
- [Basic System Requirements](#)
- [POSIX Threads \(pthreads\)](#)

Supported Platforms

The following Microsoft Windows platforms are supported:

- Microsoft Windows 11 (64-bit)
- Microsoft Windows Server 2019 (64-bit)
- Microsoft Windows Server 2022 (64-bit)
- Microsoft Windows Server 2019 (64-bit) on AWS
- Microsoft Windows Server 2022 (64-bit) on AWS
- Microsoft Windows Server 2019 (64-bit) on Azure
- Microsoft Windows Server 2022 (64-bit) on Azure

Basic System Requirements

Before installing TIBCO iProcess Workspace (Windows), make sure your system meets the system requirements listed in the following table. See Microsoft Windows documentation for more information about system requirements.

System Requirements

Component	Requirement
Printer memory	64 MB of printer memory is required to print procedures.
Disk space	56 MB of free space on the hard disk is required.
File system	NTFS FAT partitions are not supported by TIBCO iProcess Workspace (Windows).
Microsoft .Net Framework 3.5	Install this or higher version before starting TIBCO iProcess Workspace (Windows) installation. Refer to Microsoft docs for installing the .Net framework.

POSIX Threads (pthreads)

When you install or upgrade to TIBCO iProcess Workspace (Windows), you must have the following files before installation begins:

- pthread.dll version 2.7.0 (32-bit)
- pthread.dll version 2.9.1 (64-bit)

If you upgrade TIBCO iProcess Workspace (Windows) to version 11.8x and above, then you must download the latest version of pthreads.dll from the [TIBCO Software Product Download](#) website and replace the older one in the %windir% folder.

Downloading the pthreads Library

If you do not already have a POSIX Threads (pthreads) library, you can obtain it for the Windows distribution set from Cloud Software Group, Inc.. To download POSIX Threads (pthreads), perform the following steps:

1. Go to the TIBCO Software Product Download (<http://www.tibco.com/downloads>) website.
2. You can log in to the website using your credentials.

3. To navigate to the product, enter the product name in the search field. For example, search TIBCO iProcess Workspace.
4. Click **TIBCO iProcess Workspace** and then click **Go to download**.
5. Select the required version number from the **Versions** dropdown list and the operating system from the **Operating system** dropdown list. Select the checkbox for [Cloud Software Group End User Agreement \("EUA"\)](#).
6. Under the **Download options**, select the **Individual file download** radio button and then click **Download**.

You can see different components of the product with the expand (+) icon.

i Note: In **Download options**, you have the following two options to select:

- **Full product download:** All the installation files for all components of **TIBCO iProcess Workspace** are downloaded in one folder at C:\Downloads\TIBCO location.
- **Individual file download:** You can download the installation files separately for each component of **TIBCO iProcess Workspace**.

7. For TIBCO iProcess Workspace (Windows), click the expand (+) icon.
All the installation files for TIBCO iProcess Workspace (Windows) are displayed.
8. Click the file that you want to download. For example, to download the pthread installer file, click the TIB_iprocess_win_pthread_2.9.1.html file.
9. When you double-click the TIB_iprocess_win_pthread_2.9.1.html file, the iprocess_win_pthread_2.9.1_installer.zip file is downloaded.
10. Extract the iprocess_win_pthread_2.9.1_installer.zip file.
The extracted folder contains the pthread_installer.bat script, the readme, and the two pthread.dll files.
The readme has the complete instructions to run and install pthread.dlls.
11. To copy the dll files into the %windir% folder, perform the steps as given in the readme file.
The script copies the following files to the %windir% folder.
 - x86\pthread.dll to %windir%\SysWOW64
 - x64\pthread.dll to %windir%\system32



Warning: If a supported version of the pthread.dll library is not available on the system PATH when you run the installer, the installer immediately exits with an error message. For more information, see [The Installer Encounters an Error Trying to Locate pthread.dll](#).

Installing TIBCO iProcess Workspace (Windows)

This section explains how to install or upgrade TIBCO iProcess Workspace (Windows).

i Note: You must log on to Microsoft Windows as a user who is a member of the *Administrators* group. Otherwise, you are not able to run the installer.

Installation in GUI Mode

To install TIBCO iProcess Workspace (Windows) in GUI mode, complete the following steps:

1. Log on to Microsoft Windows as a user who is a member of the *Administrators* group.
2. Open the physical media or download the TIBCO iProcess Workspace (Windows) installation package from a network server.
3. Extract the product's file to a temporary directory and navigate to the temporary directory.

i Note: Make sure that you have already copied the `Pthread.dll` file to the appropriate directory. For detailed information, see [POSIX Threads \(pthreads\)](#).


4. Run `Setup.exe`. The Welcome dialog appears.

i Note: Always choose the **Install a new instance of this application** irrespective of a new installation or an upgrade.

5. Review the information in the Welcome dialog and click the **Next** button. The Software License Agreement dialog appear.
6. Review the entire TIBCO Software Inc. End User License Agreement.

- Click the **No** button if you do not agree to the terms of the license agreement, and then exit from the installation process.
- Click the **Yes** button if you agree to the terms of the license agreement. The Choose Destination Location dialog appears, as shown in Figure 1.

Figure 1: Choose Destination Location dialog




7. Click the **Browse...** button to specify a Destination Folder where you want to install iProcess Workspace (Windows).
 - If this is a new installation, go to step 8.
 - If you have already installed iProcess Workspace (Windows) in your chosen destination folder, a dialog appears and displays a message asking if you want to upgrade your previous installed iProcess Workspace (Windows).

Click the **Yes** button to upgrade your installation. The Select TIBCO iProcess Configuration dialog appears. You can either select an existing configuration set


from the TIBCO iProcess Configurations list to update, or enter a new configuration name.

8. Click the **Next** button. The Choose Setup Language dialog is displayed.



9. Select the language you want displayed in the text of the installation from the drop-down list and click the **OK** button. The Setup Type dialog appears, as shown in Figure 2.

Figure 2: Setup Type dialog




i Note: Please note that selecting the language does not change the language of the installer. It only changes the display language of the final installed application. The installer will only run in English.

10. Select one of the following installation types in the Setup Type dialog:

- **Modeler** Select this setup type to install , TIBCO iProcess Administrator, and TIBCO iProcess Modeler.
- **User** Select this setup type to install TIBCO iProcess Workspace (Windows) only.
- **Custom** Select this setup type if you want to specify which components to install, such as TIBCO iProcess Workspace (Windows), TIBCO iProcess Modeler, iProcess Workspace Plug-ins, TIBCO iProcess Administrator, and so on.

Click the **Next** button, the Select Components dialog appears, as shown in [Select Components dialog](#). Select the components that you want to install. See [Installed Components](#) for detailed information.


Figure 3: Select Components dialog



Installed Components


TIBCO iProcess Workspace (Windows)	Check the TIBCO iProcess Workspace (Windows) checkbox to install TIBCO iProcess Workspace (Windows) and Utility Server. <div>Note: You cannot select this option.</div>
TIBCO iProcess Administrator	Check the TIBCO iProcess Administrator checkbox to install TIBCO iProcess Administrator.
Case Close &	Check the Case Close and Purge facilities checkbox to install the

Purge Facilities	Case Administration features.
TIBCO iProcess Plug-in SDK	Check the TIBCO iProcess Plug-in SDK checkbox to install the SDK for developing your own EAI plug-ins.
TIBCO iProcess Open Forms SDK	Check the TIBCO iProcess Open Forms SDK checkbox to install the SDK that allows you to create your own Forms application for use with the iProcess.
TIBCO iProcess Modeler	<p>Check the TIBCO iProcess Modeler checkbox to install the iProcess Modeler.</p> <p>Note: You cannot clear this option if you have selected the EAI Plug-ins check-box, because the EAI Plug-ins option is dependent on the TIBCO iProcess Modeler option.</p>
EAI Plug-ins	<p>Check the EAI Plug-ins checkbox to install the available iProcess Workspace Plug-ins.</p> <p>Click the Change button in the Description area, the Select Sub-components dialog appears. Select each of the following sub-components that you want to install.</p> <ul style="list-style-type: none"> — EAI COM - TIBCO iProcess COM Client Plug-in — EAI MAIL - TIBCO iProcess Email Client Plug-in — EAI SCRIPT - TIBCO iProcess Script Client Plug-in — EAI DB - TIBCO iProcess Database Client Plug-in



11. Click the **Next** button, the Select TIBCO iProcess Engine dialog appears, as shown in [Select TIBCO iProcess Engine dialog](#).

Figure 4: Select TIBCO iProcess Engine dialog



Enter the details of the iProcess Engine that you want to connect to by default when you start TIBCO iProcess Workspace (Windows):

- Enter the Machine Name of the computer where the iProcess Engine has been installed.

If you do not fill in any Machine Name here, the installer uses the value of the COMPUTERNAME environment variable. (This is the name of the computer on which you are installing TIBCO iProcess Workspace (Windows)).

- Enter the RPC Program Number of the iProcess Engine that you want to connect to.

i Note: Most iProcess Engines use RPC numbers in the range from 391875 to 391879 inclusive, and using numbers in this range needs to prevent clashes with other applications. If you enter a number outside this range, a warning message appears. You can choose to use the number you have entered, or to enter another.

Alternatively, you can change the RPC program number using the iProcess Preference Editor `swpref.exe` after installation, if you know that your iProcess Engine uses a different RPC program number. For detailed information, see “Using the iProcess Preference Editor” in *TIBCO iProcess Workspace (Windows) Manager’s Guide*.

12. Click the **Next** button, the Select Program Folder dialog appears. You can specify a folder name for TIBCO iProcess Workspace (Windows) in the Program Folders field or select an existing folder from the Existing Folders list. After installation, you can see this specified folder when selecting All Programs from the Start menu.

i Note: If you want to keep an earlier version of TIBCO iProcess Workspace (Windows) on the same computer, TIBCO suggests that you use a different folder to avoid conflicts.

13. Click the **Next** button, the Start Copying Files dialog appears. Review your installation options in this dialog:

- If you want to change any of your choices, click **Back** to move back to the appropriate dialog.
- If you are satisfied with your choices, click the **Next** button. The installer then installs TIBCO iProcess Workspace (Windows) on your computer.

14. Complete the installation. After completing the installation, the Install Complete dialog appears.

i Note: If the installer has installed any system files, you need to restart your computer before using iProcess Workspace (Windows). A dialog appears to inform you of this and gives you the option to restart either now or later.

15. Click the **Finish** button to exit the installation program.

i Note: No program folders or shortcuts are created for TIBCO iProcess Modeler. You can only start TIBCO iProcess Modeler from TIBCO iProcess Workspace (Windows). See *TIBCO iProcess Workspace (Windows) User's Guide* for more information.

Installation in Silent Mode

If you want to install TIBCO iProcess Workspace (Windows) in silent mode, you must have previously installed it in GUI mode on a computer and generated a response file that provides all the configuration information. You can subsequently use this response file as a script to run a similar installation automatically, without having to manually enter values in the dialogs. Installation in silent mode makes it easier to roll out TIBCO iProcess Workspace (Windows) across a network, using either simple batch files or network management software.

i Note: Make sure that the machine you use to create the response file is in the same state as the machines where you want to perform the installations in silent mode. Otherwise, you may have a problem with extra dialogs.

For example, if you create the response file on a machine that has a previous installation of iProcess Workspace (Windows) then an extra dialog is displayed asking if you want to upgrade this installation. If you then try and perform a silent installation with this response file on a machine that does not have a previous installation of iProcess Workspace (Windows) then the responses in the response file will not match the dialogs displayed in the installation program.

The following procedure explains how to install TIBCO iProcess Workspace (Windows) in silent mode.

- [Creating a Response File](#)
- [Performing a Silent Installation](#)

Creating a Response File

To generate a response file, complete the following steps:

1. Open a command prompt and type the following command:

```
setupDir\setup.exe -r -f1responseFileDir:\setup.iss
```

where:

- *setupDir* is the directory where you run the installer in GUI mode.
- *responseFileDir* is the directory where you want to store your generated response file.

For example:

```
E:\TIBCO\setup.exe -r -f1C:\setup.iss
```

2. Run `setup.exe`, entering the required values to all the prompts as normal. See [Installation in GUI Mode](#). The installer records your responses in the specified `Setup.iss` file.
3. Start TIBCO iProcess Workspace (Windows) to make sure that it has been correctly installed.

Performing a Silent Installation

To perform an installation in silent mode, complete the following steps:

1. Prepare a response file `Setup.iss`. For detailed information, see [Creating a Response File](#).
2. Log on to Windows as a user who is a member of the Administrators group.
3. Open a command prompt and type the following command:

```
setupDir\setup.exe -s -f1"responseFileDir:\setup.iss" -f2"logfileDir:\setup.log" /SMS
```

where:

- *setupDir* is the directory from which you ran the installer in GUI mode.
- *responseFileDir* is directory containing the response file.
- *logfileDir* is the full path of a log file you want to create. You can review the log file to determine whether the silent installation worked. For detailed information about the log file, see [Viewing the Log File](#). If you do not use the `-f2` parameter, the `Setup.log` file will be created in the directory where Windows is installed by default.

- SMS is used to make sure that the silent installation is complete before the installer and any network connections close.

i Note: Strings must be included in quotes, for example “c:\setup.iss”.

4. Press the **Enter** key on the keyboard. The installer installs iProcess Workspace (Windows), automatically getting the necessary information from the response file.
5. Start iProcess Workspace (Windows) to make sure that it has been correctly installed.

Viewing the Log File

The log file contains three sections:

- **[InstallShield Silent]** identifies the version of InstallShield Silent used in the silent installation. It also identifies the file as a log file.
- **[Application]** identifies which application and version have been installed. This section is only created if the [ResponseResult] section contains the result code **0**, indicating that the installation was successful.
- **[ResponseResult]** contains one of the following result codes shown in [Response Result Codes](#), indicating whether or not the silent installation succeeded.

Response Result Codes

0	Success.
-1	General error.
-2	Invalid mode.
-3	Required data not found in the response file.
-4	Not enough memory available.
-5	File does not exist.
-6	Cannot write to the response file.

-7	Unable to write to the log file.
-8	Invalid path to the response file.
-9	Not a valid list type (string or number).
-10	Data type is invalid.
-11	Unknown error during setup.
-12	Dialogs are out of order.
-51	Cannot create the specified folder.
-52	Cannot access the specified file or folder.
-53	Invalid option selected.

Uninstalling TIBCO iProcess Workspace (Windows)

This section describes how to uninstall TIBCO iProcess Workspace (Windows).

Pre-removal Considerations

Before uninstalling your TIBCO iProcess Workspace (Windows), TIBCO reminds you:

- The uninstallation procedure uninstalls any or all components that have been installed by the iProcess Workspace (Windows) installation, such as TIBCO iProcess Modeler.
- You must uninstall any additional iProcess Workspace (Windows) components that you have installed separately. For example, TIBCO iProcess Java Plug-in or any plug-in that you have created before uninstalling iProcess Workspace (Windows). For more information about how to uninstall these components, see the installation guides.

Uninstalling

To uninstall TIBCO iProcess Workspace (Windows) from your computer, complete the following steps:

1. Open the **Control Panel** window on your computer.
2. Double-click the **Add or Remove Programs** button and select the **TIBCO iProcess Workspace (Windows) *version*** item from the list, where *version* is the version number of your TIBCO iProcess Workspace (Windows) installation. Then click the **Change/Remove** button to perform the uninstallation process.

i Note: On Windows 10, double-click the **Programs and Features** button and double-click **TIBCO iProcess Workspace (Windows)*version*** from the list, where *version* is the version number of your TIBCO iProcess Workspace (Windows) installation to perform the uninstallation process.

Post-installation Tasks

This section lists the post-installation tasks.


Configuring Data of Remote Procedure Calls (RPC) Servers

TIBCO iProcess Workspace communicates with TIBCO iProcess Engine by making Remote Procedure Calls (RPC). You need to configure the data of RPC servers before setting up connection between TIBCO iProcess Workspace and TIBCO iProcess Engine servers.

For more information, see "TIBCO iProcess Workspace and TIBCO iProcess Engine Network Communication" in *TIBCO iProcess Engine Architecture Guide*.

To configure the data of RPC servers, perform the following steps in the Registry Editor after installing TIBCO iProcess Workspace (Windows):

1. Start the Registry Editor from the machine where you install TIBCO iProcess Workspace (Windows) and navigate to the *RegistryLocation*\TIBCO iProcess\TIBCO iProcess Workspace (Windows)\Default\RPC Servers directory.
Where *RegistryLocation* is the \HKEY_LOCAL_MACHINE\Software directory.
2. Right-click the **RPC Servers** folder or the right panel, and then select **New > String Value** from the menu that is displayed.
3. Rename the **New Value** in the Name column that you have just created, and then double click it. The Edit String dialog is displayed.
4. In the Value data field of the Edit String dialog, specify the data of the server.

 **Note:** Separate the data value with comma. For example, 127.0.0.1,391875,1,server.

The data of the server includes the following parts:

Data	Description
IP or host name	The IP address or host name of the machine where the server locates.
RPC number	The RPC number of the server. The RPC number is in the SWDIR\swdefs file.
Enable Password field	<ul style="list-style-type: none"> Set 1 to enable the Password field in the Login For System Administration dialog, which is displayed when you log in to TIBCO iProcess Administrator. Set 0 to disable the Password field in the Login For System Administration dialog, which is displayed when you log in to TIBCO iProcess Administrator.
Description	The description for the iProcess Engine server.
Internet Protocol Version	<ul style="list-style-type: none"> 1 (IPv6) 0 or Null (IPv4)

- Click the **OK** button to finish the configuration.

After configuring the RPC servers data, the server is available to communicate. When you log in to TIBCO iProcess Administrator through the Login For System Administration dialog, the description of the server is displayed in the drop-down list of the Server field. See “Logging In to TIBCO iProcess Administrator” in *TIBCO iProcess Workspace Manager’s Guide* for more information.

Troubleshooting

This section describes how to deal with errors that you may encounter when installing TIBCO iProcess Workspace (Windows).

i Note: If the information in this appendix does not help you to resolve the problem, or if you are in any way unsure as to how to proceed, contact TIBCO Support for further assistance.

The Installer Encounters an Error Trying to Locate pthread.dll

Problem Description

When you run the installer, the installer exits immediately with one of the following error messages:

- Failed to locate the 'pthread.dll' component
- The minimum 'pthread.dll' component version required is 2.7.0. The version available on the system is 2.6.0
- Failed to load the 'pthread.dll' component as no version information could be found in it
- Failed to determine the version of the 'pthread.dll' component.

accompanied by the following message:

POSIX Threads (pthreads) for Win32 is required in order for the software to run correctly. Please refer to the Installation Guide for information on where to get hold of this component and how to install it.

What to Do

To resolve this problem:

1. Obtain the POSIX Threads (pthreads) library for Windows distribution set library from Cloud Software Group, Inc. and make it available on your system PATH. For detailed information, see [POSIX Threads \(pthreads\)](#).
2. Run the installer again.

TIBCO Documentation and Support Services

For information about this product, you can read the documentation, contact TIBCO Support, and join TIBCO Community.

How to Access TIBCO Documentation

Documentation for TIBCO products is available on the [Product Documentation website](#), mainly in HTML and PDF formats.

The [Product Documentation website](#) is updated frequently and is more current than any other documentation included with the product.

Product-Specific Documentation

The following documentation for this product is available on the [TIBCO iProcess® Workspace \(Windows\) Product Documentation](#) page:

Other TIBCO Product Documentation

When working with TIBCO iProcess® Workspace (Windows), you may find it useful to read the documentation of the following TIBCO products:

- TIBCO ActiveMatrix BusinessWorks™
- TIBCO Business Studio™
- TIBCO Enterprise Message Service™
- TIBCO Hawk®
- TIBCO Rendezvous®

How to Contact Support for TIBCO Products

You can contact the Support team in the following ways:

- To access the Support Knowledge Base and getting personalized content about

products you are interested in, visit our [product Support website](#).

- To create a Support case, you must have a valid maintenance or support contract with a Cloud Software Group entity. You also need a username and password to log in to the [product Support website](#). If you do not have a username, you can request one by clicking **Register** on the website.

How to Join TIBCO Community

TIBCO Community is the official channel for TIBCO customers, partners, and employee subject matter experts to share and access their collective experience. TIBCO Community offers access to Q&A forums, product wikis, and best practices. It also offers access to extensions, adapters, solution accelerators, and tools that extend and enable customers to gain full value from TIBCO products. In addition, users can submit and vote on feature requests from within the [TIBCO Ideas Portal](#). For a free registration, go to [TIBCO Community](#).

Legal and Third-Party Notices

SOME CLOUD SOFTWARE GROUP, INC. (“CLOUD SG”) SOFTWARE AND CLOUD SERVICES EMBED, BUNDLE, OR OTHERWISE INCLUDE OTHER SOFTWARE, INCLUDING OTHER CLOUD SG SOFTWARE (COLLECTIVELY, “INCLUDED SOFTWARE”). USE OF INCLUDED SOFTWARE IS SOLELY TO ENABLE THE FUNCTIONALITY (OR PROVIDE LIMITED ADD-ON FUNCTIONALITY) OF THE LICENSED CLOUD SG SOFTWARE AND/OR CLOUD SERVICES. THE INCLUDED SOFTWARE IS NOT LICENSED TO BE USED OR ACCESSED BY ANY OTHER CLOUD SG SOFTWARE AND/OR CLOUD SERVICES OR FOR ANY OTHER PURPOSE.

USE OF CLOUD SG SOFTWARE AND CLOUD SERVICES IS SUBJECT TO THE TERMS AND CONDITIONS OF AN AGREEMENT FOUND IN EITHER A SEPARATELY EXECUTED AGREEMENT, OR, IF THERE IS NO SUCH SEPARATE AGREEMENT, THE CLICKWRAP END USER AGREEMENT WHICH IS DISPLAYED WHEN ACCESSING, DOWNLOADING, OR INSTALLING THE SOFTWARE OR CLOUD SERVICES (AND WHICH IS DUPLICATED IN THE LICENSE FILE) OR IF THERE IS NO SUCH LICENSE AGREEMENT OR CLICKWRAP END USER AGREEMENT, THE LICENSE(S) LOCATED IN THE “LICENSE” FILE(S) OF THE SOFTWARE. USE OF THIS DOCUMENT IS SUBJECT TO THOSE SAME TERMS AND CONDITIONS, AND YOUR USE HEREOF SHALL CONSTITUTE ACCEPTANCE OF AND AN AGREEMENT TO BE BOUND BY THE SAME.

This document is subject to U.S. and international copyright laws and treaties. No part of this document may be reproduced in any form without the written authorization of Cloud Software Group, Inc.

TIBCO, the TIBCO logo, the TIBCO O logo, ActiveMatrix BusinessWorks, TIBCO Business Studio, Enterprise Message Service, Hawk, iProcess, and Rendezvous are either registered trademarks or trademarks of Cloud Software Group, Inc. in the United States and/or other countries.

All other product and company names and marks mentioned in this document are the property of their respective owners and are mentioned for identification purposes only. You acknowledge that all rights to these third party marks are the exclusive property of their respective owners. Please refer to Cloud SG’s Third Party Trademark Notices (<https://www.cloud.com/legal>) for more information.

This document includes fonts that are licensed under the SIL Open Font License, Version 1.1, which is available at: <https://scripts.sil.org/OFL>

Copyright (c) Paul D. Hunt, with Reserved Font Name Source Sans Pro and Source Code Pro.

Cloud SG software may be available on multiple operating systems. However, not all operating system platforms for a specific software version are released at the same time. See the “readme” file for the availability of a specific version of Cloud SG software on a specific operating system platform.

THIS DOCUMENT IS PROVIDED “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENT COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THIS DOCUMENT. CLOUD SG MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT(S), THE PROGRAM(S), AND/OR THE SERVICES DESCRIBED IN THIS DOCUMENT AT ANY TIME WITHOUT NOTICE.

THE CONTENTS OF THIS DOCUMENT MAY BE MODIFIED AND/OR QUALIFIED, DIRECTLY OR INDIRECTLY, BY OTHER DOCUMENTATION WHICH ACCOMPANIES THIS SOFTWARE, INCLUDING BUT NOT LIMITED TO ANY RELEASE NOTES AND "README" FILES.

This and other products of Cloud SG may be covered by registered patents. For details, please refer to the Virtual Patent Marking document located at <https://www.cloud.com/legal>.

Copyright © 1994-2025. Cloud Software Group, Inc. All Rights Reserved.